OS-2

子二甲 吳翊弘 U13157005


BlinkLEDExt
main.cpp
main.cpp > mainTask(void *)
#include "pico/stdlib.h"
//Standard Task priority
#define TASK_PRIORITY (tskIDLE_PRIORITY + 1UL)
//LED PAD to use
#define LED_PAD 25
//Blink Delay
#define DELAY 202
/***
* Main task to blink external LED
* @param params - unused
*/
void mainTask(void *params){
printf("Main task started\n");
const uint ledPad = LED_PAD;
gpio_init(ledPad);
gpio_set_dir(ledPad, GPIO_OUT);
while (true) { // Loop forever
gpio_put(ledPad, 1);
vTaskDelay(DELAY);
gpio_put(ledPad, 0);
vTaskDelay(DELAY);
printf("Hello, MCUT U13157005\n");
}
}
PROBLEMS OUTPUT DEBUG CONSOLE TERMINAL PORTS MEMORY XRTOS SERIAL MONITOR
Open an additional monitor
Monitor Mode Serial View Mode Text Port COM3 - USB 序列裝置 (COM3) Baud rate 115200 Line ending
Stop Monitoring
Hello, MCUT U13157005
Hello, MCUT U13157005
Type in a message to send to the serial port.
ASUS


Help
BlinkLEDExt
main.cpp
src > main.cpp > mainTask(void *)
/***
* Demo program to flash an LED attached to GPIO PAD 0.
* Uses FreeRTOS Task
* Jon Durrant
* 15-Aug-2022
*/
//U13157005 吳翊弘
#include "pico/stdlib.h"
#include "FreeRTOS.h"
#include "task.h"
#include <stdio.h>
//Standard Task priority
#define TASK_PRIORITY (tskIDLE_PRIORITY + 1UL)
//LED PAD to use
#define LED_PAD 25
//Blink Delay
#define DELAY 202
/***
* Main task to blink external LED
* @param params - unused
*/
void mainTask(void *params){
printf("Main task started\n");
const uint ledPad = LED_PAD;
PROBLEMS OUTPUT DEBUG CONSOLE TERMINAL PORTS MEMORY XRTOS SERIAL MONITOR
Open an additional monitor
Monitor Mode Serial View Mode Text Port COM3 - USB 序列裝置 (COM3) Baud rate 115200 Line ending None
Stop Monitoring
Hello, MCUT U13157005
Hello, MCUT U13157005
Type in a message to send to the serial port.
Send as Text
Ln 47, Col 5 Spaces: 4 UTF-8 LF {} C++
ASUS

READ ME

此程式使用V S Code燒入至RP2040，執行後程式進入無限迴圈，每隔 1 秒會使用printf輸出一次字串「Hello, MCUT U13157005」，並設定LED pin腳，延遲為202設定輸出間隔。