11/25/24, 11:24 AM Check Answers

# 12.3.10 Lab: Secure a Home Wireless Network

Candidate: Richard Habib () Time Spent: 00:33

Score: 0%								

# **Task Summary**

### **Required Actions**

- X Change the Wireless Network Name (SSID) to PoliceVan
- X Configure the wireless security settings **Show Details**
- X Change the wireless access point's default administrator authentication credentials Show Details

# Explanation



#### Complete this lab as follows:

- 1. Access, and sign into, the TPLink-AC1750 wireless access point.
  - a. In the URL field of Google Chrome, enter 192.168.0.254 and press Enter.
  - b. Maximize Google Chrome for easier viewing.
  - c. From the top menu bar, select the Wireless tab.
  - d. Enter the sign-in credentials:
    - Username: admin
    - Password: password
  - e. Select Sign In.
- 2. Change the Wireless Network Name (SSID) to PoliceVan.
  - a. Make sure the Wireless submenu of **Basic Settings** is selected.
  - b. Under Wireless Interface wlan0, change the Wireless Network Name (SSID) to PoliceVan.
  - c. Scroll down and select Apply Settings.
- 3. Configure the wireless security settings.
  - a. From the submenu bar, select the Wireless Security tab.
  - b. For Wireless Mode, use the drop-down list to select WPA.
  - c. Under Network Authentication, select WPA2 Personal.
  - d. Under WPA Algorithms, select CCMP-128 AES.
  - e. In the WPA Shared Key field, enter 4WatchingU.
  - f. (Optional) Select **Unmask** to verify your new shared key.
  - g. Scroll to the bottom and select Apply Settings.
- 4. Change the wireless access point's administration authentication credentials.
  - a. From the top menu bar, select the **Administration** tab.

11/25/24, 11:24 AM Check Answers

- b. Make sure the **Management** submenu is selected.
- c. Change the Router Password settings as follows:
  - Router Username: @dm1n (1 is the number 1)
  - Router Password: **StayOut!** (O is the capital letter O).
  - Re-enter to confirm: **StayOut!** (O is the capital letter O).
- d. Scroll to the bottom and select **Apply Settings**.
- e. Select **Save**.
- f. Select **Reboot Router**.
- g. When prompted, select Continue.
- 5. Configure the laptop to connect to the wireless network and save the wireless profile settings.
  - a. From the top left, select **Computer Desk**.
  - b. On the Home-Laptop monitor, select Click to view Windows 11.
  - c. From the Notification area of the taskbar, select the **Network** icon.
  - d. To the right of the wireless icon, select the > icon.
  - e. Select the PoliceVan wireless network.
  - f. Make sure **Connect automatically** is selected.
  - g. Select **Connect**.
  - h. Enter 4WatchingU (the passphrase/network security key).
  - i. Select **Next**.
  - j. From the Notification area of the taskbar, right-click the *network* icon and select **Network &**Internet settings to confirm the connection.