

Nimble HP and Damage Module

Manifest URL: <https://raw.githubusercontent.com/Rickrollnomicon/Nimble-HP-and-Damage/main/module.json>

Nimble HP and Damage adds functionality to streamline HP tracking and damage resolution. It can be used as a simple add/remove hit point tool, or it can automate damage application from rolled attacks and spells while preserving Nimble's monster armor and Defend mechanics. It also includes class-specific options that allow you to easily add extra modifiers such as Sneak Attack to an existing roll.

The Floating HUD is a live, map-based damage and healing tool that allows quick adjustments to hit points. It is based on current live targeting and supports adding or subtracting raw values for those who prefer to do the math manually. It also includes automation options for those who prefer a HUD-based interface over chat cards.

The Enhanced Chat Card functionality adds additional automation controls that allow for bypassing armor, applying resistance or vulnerability, and automating effects such as Vicious Opportunist or Sneak Attack directly from the chat card. It treats chat cards as self-contained and applies damage, healing, and effects only to the designated targets of the card, regardless of current live targeting.

Settings

The module settings allow you to determine how much functionality you wish to use. The GM can retain full control over HP application or allow players to apply damage to monsters. The Floating HUD and Enhanced Chat Card functionality can be enabled or disabled independently by the GM.

Nimble HP and Damage



Allow players to apply damage directly

☒

When enabled, players may target NPC tokens and apply damage/healing via the Floating HUD or Enhanced Chat Cards. (SocketLib module optional but recommended for best damage routing)

Enable Enhanced Chat Cards

☒

Adds enhanced damage application functionality to damage chat cards, including armor reduction/bypass, resistances/vulnerabilities, and select class abilities.

Enable Floating HUD

☒

Enable use of the Floating HUD. Individual players can choose to show/hide using a button in the left menu.

Show Damage Verification Chat Card

☒

When enhanced application is used, always post the verification chat card.

Enable enhanced/alternate dice pool functionality

☐

Enables alternate (legacy) pool management for Judgment and Fury Dice, adding options to the enhanced chat card and floating HUD.

Monster Armor Rule

Flat Reduction / Playtest

Choose how monster Medium/Heavy Armor reduces damage in the Floating HUD and Enhanced Chat Cards. Original uses dice-only damage; Flat Reduction is the current playtest rule.

Auto-apply Dying & Wounds to PCs

☒

Automatically apply the Dying condition and add one Wound to player characters when Hit Points reach zero. Additional damage adds an additional Wound.

Show tooltips

☒

Show hover tooltips on the Nimble HP HUD controls.

“Allow players to apply damage directly” applies to both the Floating HUD and the Enhanced Chat Cards. Note that the SocketLib module is not required for the mod itself, but highly recommended for proper damage routing if players are allowed to apply damage.

“Show Damage Verification Chat Cards” allows you to disable damage verification if you find it too verbose.

“Enable enhanced/alternate dice pool functionality” enables legacy mod management of Fury Dice pools and application of Judgment Dice at the point of damage application. The core Nimble ruleset now allows pool management, so this feature can be left off to avoid redundancy.


“Monster Armor Rule” allows you to toggle between the “just the dice” rule from the original core rulebook, or the alternate flat -5/-10 reduction method.

Note that if the Floating HUD is active, individual players have the option to show/hide it using a button in Foundry’s left sidebar.




Floating HUD

The default Floating HUD interface shows information for the selected token for the GM. For players, it always shows information for their owned PC, regardless of whether it's selected.



The -/+ buttons decrease or increase by the value entered in the text box (or by 1 if no value is entered). Entering a value in the text box and hitting Enter sets the HP to that absolute value.


Temp HP are listed and tracked separately.



Targeted Features

Additional functions are available to the GM, as well as to players if the GM enables the "Allow players to apply damage directly" setting. For GMs, these functions work well in combination with the Nimble Combat System, as both systems rely on standard Foundry targeting.

When a token is targeted, the interface expands to show information and functions that can be applied to the targeted actor. If the targeted actor is a PC, the targeting information changes to green for emphasis.



The -/+ buttons function the same for targeted vs. selected/owned tokens, except that entering a value and hitting Enter for a targeted token defaults to applying that amount of damage rather than setting to an absolute value.

The -/+ buttons have additional right-click functionality for specific use-cases.



If multiple tokens are targeted, a total count is given; a tooltip shows all targeted tokens if the list truncates.




If multiple tokens are targeted and a PC is included, a “Friendly Fire” warning is given.



Armor information is automatically pulled from targeted tokens. The button can be clicked to manually override this (e.g., Sunder Armor). Medium Armor allows manual bypass; Heavy Armor allows reducing one step or bypassing entirely. Values in the text box update automatically when the armor type is cycled to reflect the resulting damage.



Detailed Damage Verification Cards appear if enabled in Settings. When multiple targets are selected that have different armor types, damage application through this tool (both via the Floating HUD or Enhanced Chat Card functionality) automatically applies damage correctly to each target based on its armor type. If armor reduction/bypass is applied, the setting is applied consistently across multiple targets.





If the targeted token is a PC, the Armor button changes to the Defend button (green tint for emphasis).



Toggle the button if the target is defending, and the appropriate amount is calculated from the character sheet and deducted from damage.



Note: If the targeted PC actor has a shield equipped, it provides 4 options to allow for the “Deflect” optional rule: None -> Armor Only -> Shield Only -> Armor+Shield.

Auto-Fill From Chat

When right-clicking into a text field, it automatically pulls the information from the latest roll in chat made by the owned character (or latest roll by the GM if they right-click).


Damage is broken down into dice/flat for purposes of the Core rulebook “just the dice” Monster Armor rule.

If the chat card indicates a critical hit, all damage calculations automatically bypass armor for both the HUD and the Enhanced Chat Cards. Armor bypass always applies on crits, so this cannot be overridden.

If a spell, ability, or weapon has the “Ignore Armor” box checked, damage shown in the Enhanced Chat Card and/or pulled into the HUD automatically ignores any monster armor, and the Armor button is automatically set to bypass mode (can be manually cycled back on to account for exceptions to the rule).

Conditions

If the chat card indicates a condition that is to be applied on hit/damage, an additional button appears in the tool to allow the player to apply that condition directly (the button disappears when damage is applied, so conditions should be applied first).



If the “Auto-apply Dying and Wounds” setting is enabled (on by default):

- Any PC reduced to 0 HP via this tool (either via the Floating HUD or Enhanced Chat Card functionality) automatically receives the Dying condition and 1 Wound.
- Any additional damage taken while the Dying condition is active adds 1 additional Wound (allowing for manual application per table-specific rules).
- Healing a PC above 0 HP via this tool automatically removes the Dying condition.

Extra Damage Options

If the controlled PC is a The Cheat, Oathsworn, or Berserker, clicking the Extra Damage Options button allows you to add class-specific damage to the running total in the text box. The values/calculations are automatically set based on the class and level of the character. As with the core interface window, the Extra Damage popup is draggable and remembers the last position used.



The Extra Damage popup closes automatically on a roll, but can be re-opened to verify the last roll or to re-roll.

If a Cheat rolls a non-crit and right-clicks to pull the value into the HUD, the Extra Damage Options button shows the Vicious Opportunist option, which automatically re-rolls the attack with the primary die maximized.



NOTE: Judgment and Fury Dice pool functionality are now largely redundant due to the pool management functionality of the core Nimble ruleset. These functions are off by default to avoid any redundancy, but can be activated via the settings if preferred.

Oathsworn Judgment dice function the same way as The Cheat through this tool. This is different timing than RAW, as the dice are rolled at the time of the attack instead of when Judgment is gained. From the perspective of the VTT, there's no practical difference in the end, and it's easier to apply this way, since unlike Fury Dice, it's not a pool that is maintained between turns.


Berserkers can track, spend, and re-roll Fury Dice via the Extra Damage button.




Note: the value of the Fury Dice pool is not automatically added to the total if Fury Dice have already been rolled. You must click the Extra Damage button to add it – again, to account for any edge cases.

Enhanced Chat Cards


The Enhanced Chat Card functionality allows for much of the same damage manipulation as the Floating HUD but treats chat cards as self-contained. Targets can be added, removed, or changed after the roll, and all applied damage and conditions are applied only to the targets listed on the card, regardless of current live targeting. As buttons are toggled, the “Damage” line updates automatically.




The “Armor” button only appears on armored targets and applies the same reduce/bypass behavior as on the Floating HUD.




“Res/Vuln” applies resistances or vulnerabilities.



“Misc Bonus” allows you to add any additional values to the roll that might not be accounted for in existing automation. If the core “just the dice” mode is activated, this is separated into flat and dice values, which are calculated properly for monster armor. If the playtest mode is activated, only a flat value box is provided, as the dice/flat distinction doesn’t matter in that case.



If the attacking PC is a Cheat, the Vicious Opportunist button shows on any attack that does not crit (note, the mod is not smart enough to determine if features such as Vicious Opportunist have already been used this turn, so the players/GM must track usage).



Clicking the button deletes the current chat card entry and re-rolls it as a critical hit.

If a Cheat's attack is a crit, the Sneak Attack button appears and can be clicked to roll Sneak Attack dice and add them to the total.

Cheat

Now



Sickle
Critical Hit

TARGETS + 



Gnoll

!

CRIT

10

Slashing

Primary Die Value: 4
Primary Die Modifier: 0

Res/Vuln



Sneak Attack



Misc Bonus

Flat Dice


Damage 10 → 10

Apply Damage

Note: If the chat card indicates a critical hit, all damage calculations automatically bypass armor for both the HUD and the Enhanced Chat Cards. Armor bypass always applies on crits, so this cannot be overridden.


If a spell, ability, or weapon has the “Ignore Armor” box checked, damage shown in the Enhanced Chat Card and/or pulled into the HUD automatically ignores any monster armor, and the Armor button is automatically set to bypass mode (can be manually cycled back on to account for exceptions to the rule).

If the Enhanced/Alternate Dice Pool setting is activated, Oathsworn's Judgment Dice are rolled and added to the total by clicking the button. For Berserkers, the Fury Dice window pops up, as with the Floating HUD.



Note that Fury Dice are not automatically added to the damage output on the chat card. You must click the button on the chat card to open/manage the pool, and the current value will be added when closing the Fury Dice window – again, to account for any edge cases and keep certain things manual.

When a condition indicator appears on a chat card with Enhanced Chat Card functionality enabled, clicking the name of the condition applies it to the target listed on the chat card instead of the currently selected token. This preserves internal consistency.



Once all toggles have been set within the chat card, the Apply Damage button applies the total shown on the “Damage” line to the listed target(s).

If a PC is the target of the attack, the “Defend” button appears, with similar functionality to the Floating HUD

