

Documentation for Sinacofi_R11_F1.R11_FRONT

Description of the Mapping Flow

This documentation contains file-specific information.

Attributes

| Key word | Value |
|---------------|---|
| Name | /Sinacofi_R11_F1/Mapping Flows/R11_FRONT.dmlflw |
| Last modified | -0400 |
| Label | |

Content


Configuration Parameters

| Configuration parameter | Value |
|--|-------|
| Check input attributes | Yes |
| Stop on first input attribute check error | No |
| Check input validation rules | Yes |
| Stop on first input validation rule error | No |
| Check output attributes | No |
| Stop on first output attribute check error | No |
| Check output validation rules | No |
| Stop on first output validation rule error | No |
| Continue message processing on error | No |
| Concatenate all resulting instances | No |
| Keep exact value | Yes |
| Copy all attributes | Yes |

Node Expressions

```
Mapping
Flow
        Expression
node
        if %var error1 = "" then {
          %correlativoPrefijo:= getSubString(getAttribute( "B2BXGIReceive_ConsumptionFil
Set1
          %MovimientoProcesado:=InsertMovTBL(%correlativoPrefijo, null , count(in:\Regis
        %correlativoPrefijo:= getSubString(getAttribute( "B2BXGIReceive_ConsumptionFiler
        setDocumentAttributeToOutput( "out1", "B2BXGISend_ProductionFilename",%correlat
Set1
        setDocumentAttributeToOutput( "out2",
                                                "B2BXGISend_ProductionFilename", getSubSt
If1
        countString(getTraces(), "IO Error: The Network Adapter could not establish the
        %debug:= getTraces();
        if( (%var_error1 <> "OK"))then{
            %var error1:=Sinacofi R11 F1.InsertErrorTBL(
              %correlativoPrefijo,
              "000",
Set1
              "Error Interno: "&getSubString(%debug, 1, 4000),
              formatString(getDateAndTime(), "CCYY'-'MM'-'DD hh':'mm':'ss")
        };
        %var_error1:= InsertMovTBL(%correlativoPrefijo, null, %var_registro1, null, "00"
        %correlativoPrefijo:= getSubString(getAttribute( "B2BXGIReceive ConsumptionFiler
        %resEstructuraValida:= ValidarEstructuraCAR( %correlativoPrefijo, "PA1" );
        if( %resEstructuraValida = "NK" )then{
          %var error1:= InsertErrorTBL(
            %correlativoPrefijo,
            "000",
            "Estructura de caratula ha sido modificada",
Set1
            formatString(getDateAndTime(), "CCYY'-'MM'-'DD hh':'mm':'ss")
          %var_error1:= InsertMovTBL(%correlativoPrefijo, null, %var_registro1, null, "(
          else {
          %ValoresConcatenados:= in1:\Datos\!34! & "|" & in1:\Datos\PA1;
          %MovimientoProcesado:=InsertMovTBL(%correlativoPrefijo, null , null, null, "34
          %resCargarCampos:= CargarCampos( %correlativoPrefijo , %ValoresConcatenados )
```

Design



Dependencies

| var | /Sinacofi R11 F1/Extended Objects/MovimientoProcesado.var |
|------|--|
| var | /Sinacofi_R11_F1/Extended Objects/Detalles2.var |
| var | /Sinacofi_R11_F1/Extended Objects/usuarioNAPrefijo.var |
| bdoc | /Sinacofi R11 F1/Business Documents/ArchivosMomentaneos/R11 Archivo Datos Val.bdoc |
| var | /Sinacofi_R11_F1/Extended Objects/debug.var |
| var | /Sinacofi_R11_F1/Extended Objects/TipoArchivo.var |
| bdoc | /Sinacofi_R11_F1/Business Documents/ArchivosEntrada/R11_Archivo_Datos.bdoc |
| fct | /Sinacofi_R11_F1/Extended Objects/GetEntidadByCasilla.fct |
| mdm | /Sinacofi R11 F1/Maps/Calcular Campos.mdm |
| var | /Sinacofi_R11_F1/Extended Objects/ValoresConcatenados.var |
| fct | /Sinacofi_R11_F1/Extended Objects/InsertErrorTBL.fct |
| var | /Sinacofi_R11_F1/Extended Objects/usuarioPrefijo.var |

| var | /Sinacofi_R11_F1/Extended Objects/tipoDocumentoPrefijo.var |
|------|---|
| fct | /Sinacofi_R11_F1/Extended Objects/GetLargoRegistroByTD.fct |
| var | /Sinacofi_R11_F1/Extended Objects/var_registro1.var |
| var | /Sinacofi_R11_F1/Extended Objects/indice3.var |
| var | /Sinacofi_R11_F1/Extended Objects/indice.var |
| bdoc | /Sinacofi_R11_F1/Business Documents/Salida/R11_Caratula_Salida.bdoc |
| var | /Sinacofi_R11_F1/Extended Objects/resCargarCampos.var |
| mdm | /Sinacofi_R11_F1/Maps/ArchivoDatosVal_A_ArchivoDatos_FRONT.mdm |
| var | /Sinacofi_R11_F1/Extended Objects/var_error1.var |
| var | /Sinacofi_R11_F1/Extended Objects/correlativoPrefijo.var |
| fct | /Sinacofi_R11_F1/Extended Objects/InsertMovTBL.fct |
| var | /Sinacofi_R11_F1/Extended Objects/CodigoError.var |
| var | /Sinacofi_R11_F1/Extended Objects/indice2.var |
| var | /Sinacofi_R11_F1/Extended Objects/resEstructuraValida.var |
| fct | /Sinacofi_R11_F1/Extended Objects/CargarCampos.fct |
| var | /Sinacofi_R11_F1/Extended Objects/indiceLoop.var |
| fct | /Sinacofi R11 F1/Extended Objects/ValidarEstructuraCAR.fct |

Creation Date: October 8, 2024

Generated with Mapping Services

Axway