


CSigUnit_RM.c File Reference

```
#include <errno.h>
#include <stdio.h>
#include <stdlib.h>
#include <stdbool.h>
#include <string.h>
#include <unistd.h>
#include <devctl.h>
#include <sys/iofunc.h>
#include <sys/dispatch.h>
#include <sys/neutrino.h>
#include <sys/procmgr.h>
#include <sys/resmgr.h>
#include <sys/siginfo.h>
#include "CSigUnit_Cfg.h"
#include "CSigUnit_RM.h"
#include "CSigUnit_HwIf.h"
#include "CSigUnit_Debug.h"
```

Include dependency graph for CSigUnit_RM.c:



Macros

```
#define SIG_UNIT_RESMGR_NPARTS_MAX (1U)
#define SIG_UNIT_RESMGR_MSGSIZE_MAX (2048U)
#define IO_ATTR_MODE (mode_t)S_IFREG | (mode_t)S_IRUSR | (mode_t)S_IWUSR | (mode_t)S_IRGRP | (mode_t)S_IWGRP | (mode_t)S_IROTH | (mode_t)S_IWOTH
```

Functions

```
static int32_t sigunit_io_devctl (resmgr_context_t *sigDevctlctx_p, io_devctl_t *p_msg_UP, RESMGR_OCB_T *p_ocr_SP)
    Function for devctl. This function is called when an application calls the devctl() function. More...

static int32_t sigunit_io_open (resmgr_context_t *sigOpenctx_p, io_open_t *p_msg_UP, RESMGR_HANDLE_T *p_handle_SP, void *p_extra_VP)
    Function for open. This function is called when an application calls the open() function. More...

static uint32_t sigunit_init (ts_sigunit_dev_t *p_sig_create_dev_SP)
    Function for creating a sigunit device.
    More...
```

static void	sigunit_exit_handler (int32_t sig)	Function for handling the exit scenario of a sigunit device. More...
static bool	sigunit_getopt_chk (char *const p_opt, const int32_t p_argc, char *const p_argv[])	Function to check the options passed while starting the Driver. More...
static bool	sigunit_options (const int32_t argc, char **const argv, ts_sigunit_dev_t *p_dev_options_SP)	Function to check the options passed while starting the Driver. More...
static void	sigunit_usage (void)	Function will be called if user pass illegal or invalid options. More...
static bool	sigunit_fini (ts_sigunit_dev_t *p_sig_fini_dev_SP)	Function to free all the resources allocated to the Signature Unit Driver. More...
int	main (int argc, char **argv)	

Variables

ts_sigunit_dev_t	sigunit_dev
uint8_t	verbose
slog2_buffer_set_config_t	slog_config
slog2_buffer_t	slog_handle
static resmgr_attr_t	rattrib
static iofunc_attr_t	ioattrib
static resmgr_connect_funcs_t	ts_sigunit_connect_funcs
static resmgr_io_funcs_t	ts_sigunit_io_funcs
struct sigaction	sigAct
static bool	g_sigunit_done_BOOL = false

Macro Definition Documentation

◆ IO_ATTR_MODE

#define IO_ATTR_MODE (mode_t)S_IFREG | (mode_t)S_IRUSR | (mode_t)S_IWUSR | (mode_t)S_IRGRP | (mode_t)S_IWGRP | (mode_t)S_IROTH | (mode_t)S_IWOTH

◆ SIG_UNIT_RESMGR_MSGSIZE_MAX

#define SIG_UNIT_RESMGR_MSGSIZE_MAX (2048U)

◆ SIG_UNIT_RESMGR_NPARTS_MAX

#define SIG_UNIT_RESMGR_NPARTS_MAX (1U)

Function Documentation

◆ main()


```
static void sigunit_exit_handler ( int32_t sig )
```

static

Function for handling the exit scenario of a sigunit device.

Function name(sigunit_exit_handler)

Returns
void

requirement ID 744949

Here is the caller graph for this function:



◆ sigunit_fini()

```
static bool sigunit_fini ( ts_sigunit_dev_t * p_sig_fini_dev_SP )
```

static


Function to free all the resources allocated to the Signature Unit Driver.

Parameters
void

Returns
l_fini_ret_BOOL

requirement ID 744954, 744949

Here is the call graph for this function:



Here is the caller graph for this function:



◆ sigunit_getopt_chk()

```
static bool sigunit_getopt_chk ( char *const p_opt,  
                                const int32_t p_argc,  
                                char *const p_argv[]  
                                )
```


static

Function to check the options passed while starting the Driver.

Returns
l_ret_val_BOOL true when success false when failed

requirement ID 744947

Here is the caller graph for this function:



◆ sigunit_init()

```
static uint32_t sigunit_init ( ts_sigunit_dev_t * p_sig_create_dev_SP )
```

static

Function for creating a sigunit device.


Function name(sigunit_init)

Returns

int32 - Return value to indicate success or error code

requirement ID 744949

Here is the call graph for this function:



Here is the caller graph for this function:



◆ sigunit_io_devctl()

```
static int32_t sigunit_io_devctl ( resmgr_context_t* sigDevctlctp_p,
                                io_devctl_t*      p_msg_UP,
                                RESMGR_OCB_T*      p_ocb_SP
                                )
```

static

Function for devctl. This function is called when an application calls the **devctl()** function.

Variable to handle SIGTERM signal

Parameters


- [in] **sigDevctlctp_p** - resmgr_context_t* Resource Manager Context
- [in] **p_msg_UP** - io_devctl_t* io_open message structure. Contains the message that the Resource Manager received.
- [in] **p_handle_SP** - RESMGR_HANDLE_T* defines the characteristics of the device that the resource manager is controlling

Returns

int32 - Return value to indicate success or error code

requirement ID 744949, 744956, 744957, 744958 744959, 744960, 744952

Here is the call graph for this function:



Here is the caller graph for this function:



◆ sigunit_io_open()

```
static int32_t sigunit_io_open ( resmgr_context_t *   sigOpenctp_p,
                               io_open_t *         p_msg_UP,
                               RESMGR_HANDLE_T *    p_handle_SP,
                               void *               p_extra_VP
                               )
```

static

Function for open. This function is called when an application calls the **open()** function.

Parameters

- [in] **sigOpenctp_p** - resmgr_context_t* Resource Manager Context
- [in] **p_msg_UP** - io_open_t* io_open message structure. Contains the message that the Resource Manager received.
- [in] **p_handle_SP** - RESMGR_HANDLE_T* defines the characteristics of the device that the resource manager is controlling
- [in] **p_extra_VP** - void* Extra information from the library

Returns


int32 - Return value to indicate success or error code

requirement ID 744947

Here is the call graph for this function:



Here is the caller graph for this function:



◆ sigunit_options()

```
static bool sigunit_options ( const int32_t   argc,
                              char **const   argv,
                              ts_sigunit_dev_t * p_dev_options_SP
                              )
```

static


Function to check the options passed while starting the Driver.

Returns

_ret_val_BOOL true when success false when failed

requirement ID 744947

Here is the call graph for this function:



Here is the caller graph for this function:



◆ sigunit_usage()

```
static void sigunit_usage ( void )
```

static

Function will be called if user pass illegal or invalid options.

Parameters


void Usage: resmgr_siguint number

Returns

void

requirement ID 744947

Here is the caller graph for this function:



Variable Documentation

◆ g_sigunit_done_BOOL

bool g_sigunit_done_BOOL = false

static

◆ ioattr

iofunc_attr_t ioattr

static

◆ rattr

resmgr_attr_t rattr

static

◆ sigAct

struct sigaction sigAct

◆ sigunit_dev

ts_sigunit_dev_t sigunit_dev

◆ slog_config

slog2_buffer_set_config_t slog_config

◆ slog_handle

slog2_buffer_t slog_handle

◆ ts_sigunit_connect_funcs

resmgr_connect_funcs_t ts_sigunit_connect_funcs

static

◆ ts_sigunit_io_funcs

resmgr_io_funcs_t ts_sigunit_io_funcs

static

◆ verbose

uint8_t verbose