


wd.c File Reference

```
#include <drivers/device_manager/sciclient.h>
#include <drivers/bootloader.h>
#include <sdl/rti/v0/sdl_rti.h>
#include <sdl/sdl_esm.h>
#include <sdl/rti/v0/sdl_ip_rti.h>
#include <sdl/dpl/sdl_dpl.h>
#include <drivers/sciclient.h>
#include <drivers/hw_include/cslr.h>
#include <drivers/hw_include/am62px/cslr_mcu_ctrl_mmr.h>
#include <kernel/dpl/AddrTranslateP.h>
#include "wd.h"
```

Include dependency graph for wd.c:



Macros

```
#define RTI_CLOCK_SOURCE_32KHZ_FREQ_KHZ (32U)
#define RTI_CLOCK_SOURCE_12_5MHZ_FREQ_KHZ (12500U)
#define RTI_CLOCK_SOURCE_25MHZ_FREQ_KHZ (25000U)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI1_CLKSEL_CLK_SEL_MASK (0x00000007U)
#define SDL_MCU_CTRL_MMR_CFG0_BASE (0x4500000UL)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI0_CLKSEL (0x045080B0U)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI0_CLKSEL_CLK_SEL_MASK (0x00000007U)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI0_CLKSEL_CLK_SEL_SHIFT (0x00000000U)
#define CFG0_WKUP_CTRL_MMR_WKUP_WWD0_CLKSEL (0x43008380u)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI1_CLKSEL (0x00008184U)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI1_CLKSEL_CLK_SEL_SHIFT (0x00000000U)
#define SDL_MCU_CTRL_MMR_CFG0_MCU_RTI1_CLKSEL_CLK_SEL_MAX (0x00000007U)
```

Typedefs

```
typedef enum rtiClockSource rtiClockSource_t
```

Enumerations

```
enum rtiClockSource { RTI_CLOCK_SOURCE_HFOSC0_CLKOUT = 0U , RTI_CLOCK_SOURCE_LFOSC_CLKOUT = 1U , RTI_CLOCK_SOURCE_12_5MHZ = 2U , RTI_CLOCK_SOURCE_32KHZ = 3U }
```

Functions

```
static int32_t SDL_ESM_applicationCallbackFunction (SDL_ESM_Inst esmInst, SDL_ESM_IntType esmIntrType, uint32_t grpChannel, uint32_t index, uint32_t intSrc, void *arg)
static void RTISetClockSource (uint32_t rtiModuleSelect, uint32_t rtiClockSourceSelect)
static uint32_t RTIGetPreloadValue (uint32_t rtiClkSource, uint32_t timeoutVal)
static uint32_t Wdg_getStatus (uint32_t baseAddr, int Clear)
static uint32_t Wdg_getCounter (uint32_t baseAddr)
void InternalWatchdog_PrintResetStatus (void)
Prints status of RTI Watchdog, taken while enabling WD. More...
void InternalWatchdog_Service (void)
```

	Service (pet) the watchdog. More...
void	InternalWatchdog_DoReset (void) Cause the watchdog to reset the system. More...
static void	RTIWdStart (SDL_RTI_configParms *pConfig)
void	InternalWatchdog_Enable (void) Enable the watchdog, call after system init. More...

Variables

static uint32_t	Wdg_Status = 0
static const SDL_ESM_config	RTI_esmInitConfig_wkup

Macro Definition Documentation

◆	CFG0_WKUP_CTRL_MMR_WKUP_WWD0_CLKSEL #define CFG0_WKUP_CTRL_MMR_WKUP_WWD0_CLKSEL (0x43008380u)
◆	RTI_CLOCK_SOURCE_12_5MHZ_FREQ_KHZ #define RTI_CLOCK_SOURCE_12_5MHZ_FREQ_KHZ (12500U)
◆	RTI_CLOCK_SOURCE_25MHZ_FREQ_KHZ #define RTI_CLOCK_SOURCE_25MHZ_FREQ_KHZ (25000U)
◆	RTI_CLOCK_SOURCE_32KHZ_FREQ_KHZ #define RTI_CLOCK_SOURCE_32KHZ_FREQ_KHZ (32U)
◆	SDL_MCU_CTRL_MMR0_CFG0_BASE #define SDL_MCU_CTRL_MMR0_CFG0_BASE (0x4500000UL)
◆	SDL_MCU_CTRL_MMR_CFG0_MCU_RTIO_CLKSEL #define SDL_MCU_CTRL_MMR_CFG0_MCU_RTIO_CLKSEL (0x045080B0U)
◆	SDL_MCU_CTRL_MMR_CFG0_MCU_RTIO_CLKSEL_CLK_SEL_MASK #define SDL_MCU_CTRL_MMR_CFG0_MCU_RTIO_CLKSEL_CLK_SEL_MASK (0x00000007U)
◆	SDL_MCU_CTRL_MMR_CFG0_MCU_RTIO_CLKSEL_CLK_SEL_SHIFT

#define SDL_MCU_CTRL_MMR_CFG0_MCU_RT10_CLKSEL_CLK_SEL_SHIFT (0x00000000U)

◆ SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL

#define SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL (0x00008184U)

◆ SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL_CLK_SEL_MASK

#define SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL_CLK_SEL_MASK (0x00000007U)

◆ SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL_CLK_SEL_MAX

#define SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL_CLK_SEL_MAX (0x00000007U)

◆ SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL_CLK_SEL_SHIFT

#define SDL_MCU_CTRL_MMR_CFG0_MCU_RT11_CLKSEL_CLK_SEL_SHIFT (0x00000000U)

Typedef Documentation

◆ rtiClockSource_t

typedef enum **rtiClockSource** **rtiClockSource_t**

Enumeration Type Documentation

◆ rtiClockSource

enum **rtiClockSource**

Enumerator	
RTI_CLOCK_SOURCE_HFOSC0_CLKOUT	to select clock frequency of hfosc0
RTI_CLOCK_SOURCE_LFOSC_CLKOUT	to select clock frequency of lfosc
RTI_CLOCK_SOURCE_12_5MHZ	to select clock frequency of 12 MHz
RTI_CLOCK_SOURCE_32KHZ	to select clock frequency of 32KHz

Function Documentation

◆ InternalWatchdog_DoReset()

void InternalWatchdog_DoReset (void)

Cause the watchdog to reset the system.

Returns

void

◆ InternalWatchdog_Enable()


void InternalWatchdog_Enable (void)

Enable the watchdog, call after system init.

Returns

void

Here is the call graph for this function:



◆ InternalWatchdog_PrintResetStatus()

void InternalWatchdog_PrintResetStatus (void)

Prints status of RTI Watchdog, taken while enabling WD.

Returns

void

◆ InternalWatchdog_Service()

void InternalWatchdog_Service (void)

Service (pet) the watchdog.

Returns

void

◆ RTIGetPreloadValue()

```
static uint32_t RTIGetPreloadValue ( uint32_t  rtiClkSource,
                                     uint32_t  timeoutVal
                                   )
```

static

Here is the caller graph for this function:



◆ RTISetClockSource()

```
static void RTISetClockSource ( uint32_t  rtiModuleSelect,
                                uint32_t  rtiClockSourceSelect
                              )
```


static

◆ RTIWdStart()

```
static void RTIWdStart ( SDL_RTI_configParms * pConfig )
```

static

Here is the caller graph for this function:



◆ SDL_ESM_applicationCallbackFunction()

```
static int32_t SDL_ESM_applicationCallbackFunction ( SDL_ESM_Inst  esmInst,
                                                    SDL_ESM_InstType esmIntrType,
                                                    uint32_t      grpChannel,
                                                    uint32_t      index,
                                                    uint32_t      intSrc,
                                                    void *        arg
                                                  )
```

static

Here is the caller graph for this function:



◆ Wdg_getCounter()

```
static uint32_t Wdg_getCounter ( uint32_t  baseAddr )
```


static

◆ Wdg_getStatus()

```
static uint32_t Wdg_getStatus ( uint32_t  baseAddr,
                                int        Clear
                              )
```

static

Here is the caller graph for this function:



◆ RTI_esmInitConfig_wkup

const SDL_ESM_config RTI_esmInitConfig_wkup

static

Initial value:

```
=  
{  
    .esmErrorConfig = {0u, 3u},  
    .enableBitmap = {0x00000000u, 0x00000000u, 0x04000000u, 0x00000000u,  
                     },  
  
    .priorityBitmap = {0x00000000u, 0x00000000u, 0x04000000u, 0x00000000u,  
                      },  
  
    .errorpinBitmap = {0x00000000u, 0x00000000u, 0x00000000u, 0x00000000u,  
                      },  
}
```

◆ Wdg_Status

uint32_t Wdg_Status = 0

static