

```

1 *****
2 * Author: Roger Williams
3 * Date: 01/11/2021
4 * Purpose: Test to see if can create simple data entry screen
5 *           that saves and loads data PLUS has a report
6 * Tectonics: cobc
7 *****
8 IDENTIFICATION DIVISION.
9 PROGRAM-ID. STOCKENTRYScreen.
10 ENVIRONMENT DIVISION.
11 INPUT-OUTPUT SECTION.
12 FILE-CONTROL.
13 *>due to clever compiler design can assign the file to var
14 *>BEFORE it is even declared!
15     SELECT OPTIONAL APPEND-INVFILE ASSIGN TO DISK
16         ORGANIZATION IS RELATIVE
17         ACCESS MODE IS SEQUENTIAL
18         RELATIVE KEY IS INT-KEY.
19
20     SELECT OPTIONAL READ-INVFILE ASSIGN TO DISK
21         ORGANIZATION IS RELATIVE
22         ACCESS MODE IS SEQUENTIAL
23         RELATIVE KEY IS INT-KEY.
24
25     SELECT OPTIONAL WRITE-INVFILE ASSIGN TO DISK
26         ORGANIZATION IS RELATIVE
27         ACCESS MODE IS DYNAMIC
28         RELATIVE KEY IS INT-KEY.
29
30     SELECT OPTIONAL COPY-INVFILE ASSIGN TO DISK
31         ORGANIZATION IS RELATIVE
32         ACCESS MODE IS DYNAMIC
33         RELATIVE KEY IS INT-KEY.
34
35     SELECT OPTIONAL DELETE-INVFILE ASSIGN TO DISK
36         ORGANIZATION IS RELATIVE
37         ACCESS MODE IS SEQUENTIAL
38         RELATIVE KEY IS INT-KEY.
39
40     SELECT REPORT-INVFILE ASSIGN TO DISK
41         ORGANIZATION IS SEQUENTIAL.
42
43 DATA DIVISION.
44 FILE SECTION.
45 *>decalared the same file 3 times as each re/write operation
46 *>needs to seperately assigned!
47     FD APPEND-INVFILE
48         VALUE OF FILE-ID IS "INV.TXT".
49
50     01 APPEND-RECORD.
51         03 APPEND-KEY PIC 9(16) VALUE 0.
52         03 APPEND-ITEMID PIC X(20) VALUE SPACE.
53         03 APPEND-DESC PIC X(40) VALUE SPACE.
54         03 APPEND-REVISION PIC X(5) VALUE SPACE.
55         03 APPEND-REORDERQTY PIC 999999 VALUE 0.
56         03 APPEND-APPVENID PIC 9999 VALUE 0.
57         03 APPEND-PRICE PIC 999999.99 VALUE 0.
58         03 APPEND-UOM PIC X(10) VALUE SPACE.
59
60     FD READ-INVFILE
61         VALUE OF FILE-ID IS "INV.TXT".
62
63     01 READ-RECORD.
64         03 READ-KEY PIC 9(16) VALUE 0.
65         03 READ-ITEMID PIC X(20) VALUE SPACE.
66         03 READ-DESC PIC X(40) VALUE SPACE.
67         03 READ-REVISION PIC X(5) VALUE SPACE.
68         03 READ-REORDERQTY PIC 999999 VALUE 0.
69         03 READ-APPVENID PIC 9999 VALUE 0.

```

```

70          03 READ-PRICE PIC 999999.99 VALUE 0.
71          03 READ-UOM PIC X(10) VALUE SPACE.
72
73 FD WRITE-INVFILE
74 VALUE OF FILE-ID IS "INV.TXT".
75
76          01 WRITE-RECORD.
77              03 WRITE-KEY PIC 9(16) VALUE 0.
78              03 WRITE-ITEMID PIC X(20) VALUE SPACE.
79              03 WRITE-DESC PIC X(40) VALUE SPACE.
80              03 WRITE-REVISION PIC X(5) VALUE SPACE.
81              03 WRITE-REORDERQTY PIC 999999 VALUE 0.
82              03 WRITE-APPVENID PIC 9999 VALUE 0.
83              03 WRITE-PRICE PIC 99999.99 VALUE 0.
84              03 WRITE-UOM PIC X(10) VALUE SPACE.
85
86 FD COPY-INVFILE
87 VALUE OF FILE-ID IS "INV.CPY".
88
89          01 COPY-RECORD.
90              03 COPY-KEY PIC 9(16) VALUE 0.
91              03 COPY-ITEMID PIC X(20) VALUE SPACE.
92              03 COPY-DESC PIC X(40) VALUE SPACE.
93              03 COPY-REVISION PIC X(5) VALUE SPACE.
94              03 COPY-REORDERQTY PIC 999999 VALUE 0.
95              03 COPY-APPVENID PIC 9999 VALUE 0.
96              03 COPY-PRICE PIC 99999.99 VALUE 0.
97              03 COPY-UOM PIC X(10) VALUE SPACE.
98
99 FD DELETE-INVFILE
100 VALUE OF FILE-ID IS "INV.TXT".
101
102          01 DELETE-RECORD.
103              03 DELETE-KEY PIC 9(16) VALUE 0.
104              03 DELETE-ITEMID PIC X(20) VALUE SPACE.
105              03 DELETE-DESC PIC X(40) VALUE SPACE.
106              03 DELETE-REVISION PIC X(5) VALUE SPACE.
107              03 DELETE-REORDERQTY PIC 999999 VALUE 0.
108              03 DELETE-APPVENID PIC 9999 VALUE 0.
109              03 DELETE-PRICE PIC 999999.99 VALUE 0.
110              03 DELETE-UOM PIC X(10) VALUE SPACE.
111
112 FD REPORT-INVFILE
113 REPORT IS RPT-INV
114 VALUE OF FILE-ID IS "INVREPORT2.TXT".
115
116 WORKING-STORAGE SECTION.
117 01 INT-BACK-COLOUR PIC 9 VALUE 0.
118 01 INT-TEXT-COLOUR PIC 9 VALUE 7.
119 01 STR-CHOICE PIC X(1) VALUE SPACE.
120 01 SH-ESCAPEKEY PIC 9(1) VALUE 0.
121 *>used for titles on screens used for more than 1 function
122 01 STR-SCRTYPE PIC X(4) VALUE SPACE.
123 01 STR_SCRUND PIC X(5) VALUE SPACE.
124 01 LASTRECORD PIC 99 VALUE 0.
125 01 INTNUM PIC 99 VALUE 0.
126 01 INTCURREC PIC 99 VALUE 0.
127 01 BLN-BLNNEWFILE PIC 9 VALUE 0.
128 01 STRFILEDATE PIC X(8).
129 01 STR-INVFILEBACKUP PIC X(16).
130 77 INT-KEY PIC 9(16) VALUE 1.
131 77 BLN-EOF PIC 9(1) VALUE 0.
132
133 *>screen input variables
134 01 DATAFIELDS.
135     03 DAT-KEY PIC 9(16) VALUE 1.
136     03 DAT-ITEMID PIC X(20) VALUE SPACE.
137     03 DAT-ITEMDESC PIC X(40) VALUE SPACE.
138     03 DAT-REVISION PIC X(5) VALUE SPACE.

```

```

139      03 DAT-REORDERQTY PIC 999999 VALUE 0.
140      03 DAT-APPVENID   PIC 9999 VALUE 0.
141      03 DAT-PRICE      PIC 999999.99 VALUE 0.
142      03 DAT-UOM        PIC X(10) VALUE SPACE.
143
144      *>used for reading from data file
145      01 LST-DATAFIELDS.
146          03 LST-KEY      PIC 9(16) VALUE 0 OCCURS 20 TIMES.
147          03 LST-ITEMID   PIC X(20) VALUE SPACE OCCURS 20 TIMES.
148          03 LST-ITEMDESC PIC X(40) VALUE SPACE OCCURS 20 TIMES.
149          03 LST-REVISION PIC X(5) VALUE SPACE OCCURS 20 TIMES.
150          03 LST-REORDERQTY PIC 999999 VALUE 0 OCCURS 20 TIMES.
151          03 LST-APPVENID PIC 9999 VALUE 0 OCCURS 20 TIMES.
152          03 LST-PRICE    PIC 999999V99 VALUE 0 OCCURS 20 TIMES.
153          03 LST-UOM      PIC X(10) VALUE SPACE OCCURS 20 TIMES.
154
155      01 WS-CURRENT-DATE-INFO.
156          03 WS-CURRENT-DATE.
157              05 WS-CURRENT-YEAR PIC 9(4).
158              05 WS-CURRENT-MONTH PIC 9(2).
159              05 WS-CURRENT-DAY PIC 9(2).
160          03 WS-CURRENT-TIME.
161              05 WS-CURRENT-HOUR PIC 9(2).
162              05 WS-CURRENT-MINUTE PIC 9(2).
163              05 WS-CURRENT-SECOND PIC 9(2).
164              05 WS-CURRENT-MS PIC 9(2).
165          03 WS-DIFF-FROM-GMT PIC S9(4).
166
167      REPORT SECTION.
168      RD RPT-INV
169          PAGE LIMIT 64 LINES
170          FIRST DETAIL 6
171          LAST DETAIL 46
172          FOOTING 60.
173      *>report structure
174
175      01 TYPE PH.
176          03 LINE 1.
177              05 COL 44 VALUE "INVENTORY REPORT - ".
178              05 COL 63 PIC 9(2) SOURCE WS-CURRENT-DAY.
179              05 COL 65 VALUE "/" .
180              05 COL 66 PIC 9(2) SOURCE WS-CURRENT-MONTH.
181              05 COL 68 VALUE "/" .
182              05 COL 69 PIC 9(2) SOURCE WS-CURRENT-YEAR.
183
184          03 LINE 2.
185              05 COL 44 VALUE "===== ".
186          03 LINE 4.
187              05 COL 1 VALUE "ITEM ID".
188              05 COL 22 VALUE "DESC".
189              05 COL 44 VALUE "REVISION".
190              05 COL 54 VALUE "REORD QTY".
191              05 COL 64 VALUE "APP VEN ID".
192              05 COL 75 VALUE "PRICE".
193              05 COL 87 VALUE "UOM".
194          03 LINE 5.
195              05 COL 1 VALUE
196      "-----".
197              05 COL 51 VALUE
198      "-----".
199
200      01 RPT-DETAIL TYPE IS DETAIL.
201          03 LINE PLUS 1.
202              05 COL 1 PIC X(20) SOURCE READ-ITEMID.
203              05 COL 22 PIC X(40) SOURCE READ-DESC.
204              05 COL 44 PIC X(5) SOURCE READ-REVISION.
205              05 COL 54 PIC 999999 SOURCE READ-REORDERQTY.
206              05 COL 64 PIC 9999 SOURCE READ-APPVENID.
207              05 COL 75 PIC 999999.99 SOURCE READ-PRICE.

```

```

208         05 COL 87 PIC X(10) SOURCE READ-UOM.
209
210 01 TYPE PF.
211     03 LINE IS 60.
212         05 COL 78 VALUE "PAGE:".
213         05 COL 84 PIC 9999 SOURCE PAGE-COUNTER.
214
215
216 01 TYPE RF.
217     03 LINE IS 63.
218         05 COL 20 VALUE "***** END OF INVENTORY REPORT *****".
219
220
221
222 SCREEN SECTION.
223 *>5 screens required:
224 *>
225 *>- add new record
226 *>- edit new recprd
227 *>- delete record
228 *>- view record
229 *>- search screen
230 *>
231 *>when creating screen first line MUST be set colour/blank screen
232 *>
233
234 01 CLEAR-SCREEN
235     BLANK SCREEN.
236
237 01 SCR-STOCK-ENTRY-OPTIONS-SCREEN
238     BLANK LINE.
239     03 LINE 01 COLUMN 01 VALUE "STOCK DATA OPTIONS SCREEN".
240     03 LINE 02 COLUMN 01 VALUE "=====".
241
242     03 LINE 04 COLUMN 10 VALUE "A - ADD STOCK ITEM".
243
244     03 LINE 06 COLUMN 10 VALUE "V - VIEW STOCK ITEM(S)".
245
246     03 LINE 08 COLUMN 10 VALUE "D - DELETE STOCK ITEM".
247
248     03 LINE 10 COLUMN 10 VALUE "R - PRINT STOCK REPORT".
249
250     03 LINE 12 COLUMN 10 VALUE "X - EXIT".
251
252     03 LINE 16 COLUMN 10 VALUE "ENTER CHOICE: ".
253     03 PIC X(01) TO STR-CHOICE AUTO.
254
255
256 01 SCR-STOCK-VIEW-SCREEN
257     BLANK LINE.
258
259     03 LINE 01 COLUMN 01 VALUE "STOCK DATA VIEW SCREEN".
260
261     03 LINE 02 COLUMN 01 BLANK LINE
262     VALUE "=====".
263
264     03 LINE 04 COLUMN 01 VALUE "ITEM ID:".
265     03 PIC X(20) FROM DAT-ITEMID.
266
267     03 LINE 05 COLUMN 01 VALUE "ITEM NAME:".
268     03 PIC X(40) FROM DAT-ITEMDESC.
269
270     03 LINE 06 COLUMN 01 VALUE "REVISION:".
271     03 PIC X(5) FROM DAT-REVISION.
272
273     03 LINE 07 COLUMN 01 VALUE "REORDER QTY:".
274     03 PIC 999999 FROM DAT-REORDERQTY.
275
276     03 LINE 08 COLUMN 01 VALUE "APP. VENDOR ID:".

```

```

277      03 PIC 9999 FROM DAT-APPVENID.
278
279      03 LINE 09 COLUMN 01 VALUE "ITEM PRICE:".
280      03 PIC 9999,99 FROM DAT-PRICE.
281
282      03 LINE 10 COLUMN 01 VALUE "UOM:".
283      03 PIC X(10) FROM DAT-UOM.
284
285      03 LINE 15 COLUMN 01 VALUE "N=NEXT P=PREVIOUS X=EXIT:".
286      03 PIC X(01) TO STR-CHOICE AUTO.
287
288
289 01 SCR-STOCK-DELETE-SCREEN
290  BLANK LINE.
291      03 LINE 01 COLUMN 01 VALUE "STOCK DATA DELETE SCREEN".
292
293      03 LINE 02 COLUMN 01 BLANK LINE
294  VALUE "=====".
295
296      03 LINE 04 COLUMN 01 VALUE "ITEM ID:".
297      03 PIC X(20) FROM DAT-ITEMID.
298
299      03 LINE 05 COLUMN 01 VALUE "ITEM NAME:".
300      03 PIC X(40) FROM DAT-ITEMDESC.
301
302      03 LINE 06 COLUMN 01 VALUE "REVISION:".
303      03 PIC X(5) FROM DAT-REVISION.
304
305      03 LINE 07 COLUMN 01 VALUE "REORDER QTY:".
306      03 PIC 999999 FROM DAT-REORDERQTY.
307
308      03 LINE 08 COLUMN 01 VALUE "APP. VENDOR ID:".
309      03 PIC 9999 FROM DAT-APPVENID.
310
311      03 LINE 09 COLUMN 01 VALUE "ITEM PRICE:".
312      03 PIC 9999,99 FROM DAT-PRICE.
313
314      03 LINE 10 COLUMN 01 VALUE "UOM:".
315      03 PIC X(10) FROM DAT-UOM.
316
317      03 LINE 15 COLUMN 01
318  VALUE "N=NEXT P=PREVIOUS D=DELETE X=EXIT:".
319      03 PIC X(01) TO STR-CHOICE AUTO.
320
321
322 01 SCR-STOCK-ENTRY-SCREEN
323  BLANK LINE.
324      03 LINE 01 COLUMN 01 VALUE "STOCK DATA ".
325      03 LINE 01 COLUMN 12 PIC X(4) FROM STR-SCRTYPE.
326      03 LINE 01 COLUMN 16 VALUE " SCREEN".
327
328      03 LINE 02 COLUMN 01 VALUE "=====".
329      03 LINE 02 COLUMN 12 PIC X(5) FROM STR_SCRUND.
330      03 LINE 02 COLUMN 15 VALUE "=====".
331
332      03 LINE 04 COLUMN 01 VALUE "ITEM ID:".
333      03 PIC X(20) USING DAT-ITEMID
334  REQUIRED.
335
336      03 LINE 05 COLUMN 01 VALUE "ITEM NAME:".
337      03 PIC X(40) USING DAT-ITEMDESC
338  REQUIRED.
339
340      03 LINE 06 COLUMN 01 VALUE "REVISION:".
341      03 PIC X(5) USING DAT-REVISION.
342
343      03 LINE 07 COLUMN 01 VALUE "REORDER QTY:".
344      03 PIC 999999 USING DAT-REORDERQTY.
345

```

```

346         03 LINE 08 COLUMN 01 VALUE "APP. VENDOR ID:".
347         03 PIC 9999 USING DAT-APPVENID.
348
349         03 LINE 09 COLUMN 01 VALUE "ITEM PRICE:".
350         03 PIC 9999,99 USING DAT-PRICE.
351
352         03 LINE 10 COLUMN 01 VALUE "UOM:".
353         03 PIC X(10) USING DAT-UOM
354             REQUIRED.
355
356         03 LINE 15 COLUMN 01 VALUE "S=SAVE X=EXIT:".
357         03 PIC X(01) TO STR-CHOICE AUTO.
358
359
360     PROCEDURE DIVISION.
361     0000-MAIN.
362     *initialise variables
363     MOVE SPACE TO STR-CHOICE.
364     MOVE 1 TO INTCURREC.
365     *load invoice data file
366     PERFORM 0001-LOADINVDATA
367     *show main menu
368     PERFORM 0001-SHOWMAINMENU
369     *run till user choice is exit
370     UNTIL STR-CHOICE = "X"
371
372     STOP RUN.
373
374     0001-SHOWMAINMENU.
375     DISPLAY CLEAR-SCREEN.
376     *wait for user input
377     ACCEPT SCR-STOCK-ENTRY-OPTIONS-SCREEN.
378     *process user choice
379     EVALUATE STR-CHOICE
380         WHEN "X"
381             PERFORM 0001-EXIT
382         WHEN "A"
383     *       show record maintenance screen
384             DISPLAY INTCURREC
385             ACCEPT STR-CHOICE
386             PERFORM 0001-STOCKADDEDIT
387         WHEN "V"
388             PERFORM 0001-STOCKVIEW
389         WHEN "D"
390             PERFORM 0001-STOCKDELETE
391         WHEN "R"
392             PERFORM 0001-PRINTFILE
393         WHEN "X"
394             EXIT PARAGRAPH
395     END-EVALUATE.
396
397     0001-STOCKDELETE.
398     DISPLAY CLEAR-SCREEN.
399     *reset record position marker
400     MOVE 1 TO INTCURREC.
401     *show record delete screen to user exits
402     PERFORM 0001-STOCKDELETESHOW
403     UNTIL STR-CHOICE = "X".
404
405
406     0001-STOCKDELETESHOW.
407     *> show message if no records to view
408     IF LASTRECORD = 0 THEN
409         DISPLAY "NO RECORDS TO SHOW!"
410         ACCEPT STR-CHOICE
411     *>force exit if no records available to delete
412     MOVE "X" TO STR-CHOICE
413     EXIT PARAGRAPH
414     END-IF.

```

```

415
416 *>load record from array
417 MOVE LST-KEY(INTCURREC) TO DAT-KEY.
418 MOVE LST-ITEMID(INTCURREC) TO DAT-ITEMID.
419 MOVE LST-ITEMDESC(INTCURREC) TO DAT-ITEMDESC.
420 MOVE LST-REVISION(INTCURREC) TO DAT-REVISION.
421 MOVE LST-REORDERQTY(INTCURREC) TO DAT-REORDERQTY.
422 MOVE LST-APPVENID(INTCURREC) TO DAT-APPVENID.
423 MOVE LST-PRICE(INTCURREC) TO DAT-PRICE.
424 MOVE LST-UOM(INTCURREC) TO DAT-UOM.
425
426 ACCEPT SCR-STOCK-DELETE-SCREEN.
427 IF STR-CHOICE = "N" THEN
428 *   process current record position
429     IF INTCURREC IS GREATER THAN OR EQUAL TO LASTRECORD - 1 THEN
430         COMPUTE INTCURREC = LASTRECORD - 1
431     ELSE
432         ADD 1 TO INTCURREC
433     END-IF
434 END-IF.
435 *   process current record position
436 IF STR-CHOICE = "P" THEN
437     SUBTRACT 1 FROM INTCURREC
438     IF INTCURREC < 1 THEN MOVE 1 TO INTCURREC
439 END-IF.
440
441 IF STR-CHOICE = "D" THEN
442 *> deleing existing record
443 *> MOVE "N" TO BLN-EOF
444     MOVE FUNCTION CURRENT-DATE TO WS-CURRENT-DATE-INFO
445     STRING WS-CURRENT-DAY WS-CURRENT-MONTH
446           WS-CURRENT-YEAR INTO STRFILEDATE
447     STRING "INV_" STRFILEDATE ".TXT" INTO STR-INVFILEBACKUP
448 *>use OS to copy inv.txt with name as:
449 *> inv_<ddmmyyy>.txt
450     CALL "CBL_COPY_FILE" USING "INV.TXT" ,STR-INVFILEBACKUP
451
452 *> move record pointer to chosen record using READ
453 *> MOVE INTCURREC TO INT-KEY
454
455     OPEN OUTPUT COPY-INVFILE
456     OPEN INPUT DELETE-INVFILE
457
458     MOVE 0 TO INT-KEY
459 *> set record pointer to start of file cunningly using a record
460 *> of ZERO as all first records are ONE
461     START DELETE-INVFILE KEY IS GREATER THAN INT-KEY
462
463     MOVE 0 TO BLN-EOF
464 *>read data file into table
465 *>then write into output file as long as lst-status isn't D
466
467     PERFORM UNTIL BLN-EOF = 1
468         READ DELETE-INVFILE
469         NOT AT END
470             IF DELETE-KEY NOT EQUAL INTCURREC THEN
471                 MOVE DELETE-RECORD TO COPY-RECORD
472                 WRITE COPY-RECORD
473             END-IF
474         AT END
475             MOVE 1 TO BLN-EOF
476     END-READ
477 END-PERFORM
478 *   close files
479     CLOSE COPY-INVFILE
480     CLOSE DELETE-INVFILE
481
482 *>use OS to del inv.txt and rename stRfilename to inv.txt
483     CALL "CBL_DELETE_FILE" USING "INV.TXT"

```

```

484         CALL "CBL_RENAME_FILE" USING "INV.CPY","INV.TXT"
485
486     *> update the internal array with the file changes
487     PERFORM 0001-LOADINVDATA
488     END-IF.
489     * make sure not beyond BOF
490     IF INTCURREC = 0 THEN MOVE 1 TO INTCURREC.
491
492     0001-STOCKVIEW.
493     DISPLAY CLEAR-SCREEN.
494     *> reset record pointer to record 1
495     MOVE 1 TO INTCURREC.
496
497     PERFORM 0001-STOCKVIEWSHOW
498     UNTIL STR-CHOICE = "X".
499
500     0001-STOCKVIEWSHOW.
501     *> show message if no records to view
502     IF LASTRECORD = 1 THEN
503         DISPLAY "NO RECORDS TO SHOW!"
504         ACCEPT STR-CHOICE
505         EXIT PARAGRAPH
506     END-IF.
507
508     *>load record from array
509     MOVE LST-KEY(INTCURREC) TO DAT-KEY.
510     MOVE LST-ITEMID(INTCURREC) TO DAT-ITEMID.
511     MOVE LST-ITEMDESC(INTCURREC) TO DAT-ITEMDESC.
512     MOVE LST-REVISION(INTCURREC) TO DAT-REVISION.
513     MOVE LST-REORDERQTY(INTCURREC) TO DAT-REORDERQTY.
514     MOVE LST-APPVENID(INTCURREC) TO DAT-APPVENID.
515     MOVE LST-PRICE(INTCURREC) TO DAT-PRICE.
516     MOVE LST-UOM(INTCURREC) TO DAT-UOM.
517
518     ACCEPT SCR-STOCK-VIEW-SCREEN.
519     * process current record position
520     IF STR-CHOICE = "N" THEN
521         IF INTCURREC IS GREATER THAN OR EQUAL TO LASTRECORD - 1 THEN
522             COMPUTE INTCURREC = LASTRECORD - 1
523         ELSE
524             ADD 1 TO INTCURREC
525         END-IF
526     END-IF.
527     * process current record position
528     IF STR-CHOICE = "P" THEN
529         SUBTRACT 1 FROM INTCURREC
530         IF INTCURREC < 1 THEN MOVE 1 TO INTCURREC
531     END-IF.
532
533     IF STR-CHOICE = "E" THEN PERFORM 0001-STOCKADDEDIT.
534
535
536     0001-STOCKADDEDIT.
537     *>used for either adding or editing records
538     DISPLAY CLEAR-SCREEN.
539
540     IF STR-CHOICE = "A" THEN
541         MOVE "ADD" TO STR-SCRTYPE
542         MOVE "====" TO STR_SCRUND
543     *>clear temp variables
544     INITIALIZE DATAFIELDS
545     ELSE
546         MOVE "EDIT" TO STR-SCRTYPE
547         MOVE "====" TO STR_SCRUND
548     END-IF.
549
550     DISPLAY STR-SCRTYPE
551     ACCEPT SCR-STOCK-ENTRY-SCREEN
552     ON EXCEPTION

```

```

553             MOVE 1 TO SH-ESCAPEKEY EXIT PARAGRAPH.
554
555     IF STR-CHOICE = "X" THEN EXIT PARAGRAPH.
556
557     IF STR-CHOICE = "S" THEN
558     DISPLAY STR-SCRTYPE
559     ACCEPT STR-CHOICE
560
561 *> handle if adding or saving record
562     IF STR-SCRTYPE = "ADD" THEN
563 *>now save the contents of the screen variables to write record
564         INITIALIZE APPEND-RECORD
565         MOVE DAT-ITEMID TO APPEND-ITEMID
566         MOVE DAT-ITEMDESC TO APPEND-DESC
567         MOVE DAT-REVISION TO APPEND-REVISION
568         MOVE DAT-REORDERQTY TO APPEND-REORDERQTY
569         MOVE DAT-APPVENID TO APPEND-APPVENID
570         MOVE DAT-PRICE TO APPEND-PRICE
571         MOVE DAT-UOM TO APPEND-UOM
572 *> lastrecord is always 1 higher than actual last record
573         IF LASTRECORD = 1 THEN
574             MOVE INTCURREC TO APPEND-KEY
575             OPEN OUTPUT APPEND-INVFILE
576         ELSE
577             OPEN EXTEND APPEND-INVFILE
578             MOVE LASTRECORD TO APPEND-KEY
579         END-IF
580
581         DISPLAY "                                " LASTRECORD
582
583         WRITE APPEND-RECORD
584 *> increment record position
585         ADD 1 TO LASTRECORD
586         MOVE LASTRECORD TO INTCURREC
587
588         DISPLAY LASTRECORD ":" INTCURREC
589         ACCEPT STR-CHOICE
590         CLOSE APPEND-INVFILE
591 *> update the internal array with the file changes
592         PERFORM 0001-LOADINVDATA
593         END-IF
594
595     IF STR-SCRTYPE = "EDIT" THEN
596 *>updating existing record
597 *> move record pointer to chosen record using READ
598     *>read data file into table
599         MOVE INTCURREC TO INT-KEY
600         INITIALIZE WRITE-RECORD
601         OPEN I-O WRITE-INVFILE
602         START WRITE-INVFILE KEY IS = INT-KEY
603             INVALID KEY
604                 DISPLAY "Record Not Found!"
605                 ACCEPT STR-CHOICE
606             NOT INVALID KEY
607                 REWRITE WRITE-RECORD FROM DATAFIELDS
608         END-START
609
610 *>now save the contents of the screen variables to write record
611         CLOSE WRITE-INVFILE
612         END-IF
613
614 *>copy data from screen variables to record structure
615         MOVE INT-KEY TO LST-KEY(INTCURREC)
616         MOVE DAT-ITEMID TO LST-ITEMID(INTCURREC)
617         MOVE DAT-ITEMDESC TO LST-ITEMDESC(INTCURREC)
618         MOVE DAT-REVISION TO LST-REVISION(INTCURREC)
619         MOVE DAT-REORDERQTY TO LST-REORDERQTY(INTCURREC)
620         MOVE DAT-APPVENID TO LST-APPVENID(INTCURREC)
621         MOVE DAT-PRICE TO LST-PRICE(INTCURREC)

```

```

622         MOVE DAT-UOM TO LST-UOM(INTCURREC)
623
624         DISPLAY "RECORD SAVED! PRESS ANY KEY"
625         ACCEPT STR-CHOICE
626     END-IF.
627
628     0001-LOADINVDATA.
629     *>reset LASTRECORD
630     MOVE 1 TO LASTRECORD.
631     MOVE 0 TO BLN-EOF
632
633     OPEN INPUT READ-INVFILE
634
635     *>read data file into table
636     PERFORM UNTIL BLN-EOF = 1
637         READ READ-INVFILE
638         AT END
639             MOVE 1 TO BLN-EOF
640
641     *>make sure not adding blank record!
642     NOT AT END
643         MOVE READ-KEY TO LST-KEY(LASTRECORD)
644         MOVE READ-ITEMID TO LST-ITEMID(LASTRECORD)
645         MOVE READ-DESC TO LST-ITEMDESC(LASTRECORD)
646         MOVE READ-REVISION TO LST-REVISION(LASTRECORD)
647         MOVE READ-REORDERQTY TO LST-REORDERQTY(LASTRECORD)
648         MOVE READ-APPVENID TO LST-APPVENID(LASTRECORD)
649         MOVE READ-PRICE TO LST-PRICE(LASTRECORD)
650         MOVE READ-UOM TO LST-UOM(LASTRECORD)
651         ADD 1 TO LASTRECORD
652     END-READ
653     END-PERFORM.
654
655     CLOSE READ-INVFILE.
656
657     0001-PRINTFILE.
658     *>iternates through the array and prints the output as a report to: inv.rpt
659     *>MOVE "N" TO BLN-EOF.
660     MOVE FUNCTION CURRENT-DATE TO WS-CURRENT-DATE-INFO.
661
662     OPEN OUTPUT REPORT-INVFILE.
663     OPEN INPUT READ-INVFILE.
664     *> read first record
665     INITIALIZE READ-RECORD.
666     INITIATE RPT-INV.
667     MOVE 0 TO BLN-EOF
668
669     *>read data file into report
670     PERFORM UNTIL BLN-EOF = 1
671         READ READ-INVFILE
672         AT END
673             MOVE 1 TO BLN-EOF
674         NOT AT END
675             GENERATE RPT-DETAIL
676     END-PERFORM.
677
678     TERMINATE RPT-INV.
679     CLOSE REPORT-INVFILE.
680     CLOSE READ-INVFILE.
681
682     0001-EXIT.
683     DISPLAY CLEAR-SCREEN.
684     EXIT.
685

```