R-Type - Engine

Generated by Doxygen 1.9.1

1 Engine 1
1.1 Compilation
1.1.1 Linux
2 Hierarchical Index
2.1 Class Hierarchy
3 Class Index
3.1 Class List
4 Class Documentation
4.1 Archetypes Class Reference
4.2 Color Class Reference
4.2.1 Detailed Description
4.2.2 Constructor & Destructor Documentation
4.2.2.1 Color() [1/2]
4.2.2.2 Color() [2/2]
4.2.2.3 ~Color()
4.2.3 Member Function Documentation
4.2.3.1 fromSFMLColor()
4.2.3.2 getAlpha()
4.2.3.3 getBlue()
4.2.3.4 getGreen()
4.2.3.5 getRed()
4.2.3.6 operator sf::Color()
4.2.3.7 setAlpha()
4.2.3.8 setBlue()
4.2.3.9 setGreen()
4.2.3.10 setRed()
4.3 Components Class Reference
4.3.1 Detailed Description
4.3.2 Constructor & Destructor Documentation
4.3.2.1 Components()
4.3.2.2 ~Components()
4.3.3 Member Function Documentation
4.3.3.1 getBit()
4.3.3.2 init()
4.3.3.3 update()
4.4 DrawableComponent Class Reference
4.4.1 Detailed Description
4.4.2 Constructor & Destructor Documentation
4.4.2.1 ∼DrawableComponent()
4.4.3 Member Function Documentation

4.4.3.1 draw()	18
4.5 Entity Class Reference	18
4.5.1 Detailed Description	20
4.5.2 Constructor & Destructor Documentation	21
4.5.2.1 Entity() [1/2]	21
4.5.2.2 Entity() [2/2]	21
4.5.2.3 ∼Entity()	21
4.5.3 Member Function Documentation	22
4.5.3.1 addComponent()	22
4.5.3.2 addDrawable()	22
4.5.3.3 applyDeferredEntity()	23
4.5.3.4 drawEntity()	23
4.5.3.5 getActive()	23
4.5.3.6 getBit()	24
4.5.3.7 getComponent()	24
4.5.3.8 getComponentArrays()	24
4.5.3.9 getComponentBitset()	25
4.5.3.10 getComponentTypeID()	25
4.5.3.11 getDrawableComponents()	25
4.5.3.12 getName()	26
4.5.3.13 init()	26
4.5.3.14 removeComponent()	27
4.5.3.15 removeDrawable()	27
4.5.3.16 setActive()	27
4.5.3.17 setDeferredEntity()	28
4.5.3.18 setName()	28
4.5.3.19 update()	28
4.6 EntityManager Class Reference	29
4.6.1 Constructor & Destructor Documentation	30
4.6.1.1 EntityManager()	30
4.6.1.2 ∼EntityManager()	31
4.6.2 Member Function Documentation	31
4.6.2.1 addEntity()	31
4.6.2.2 getEntities()	32
4.6.2.3 getEntity()	32
4.6.2.4 getEntityMap()	32
4.6.2.5 init()	33
4.7 EntityManagerTest Class Reference	33
4.8 EntityTest Class Reference	35
4.9 EventEngine Class Reference	36
4.9.1 Detailed Description	36
4.9.2 Constructor & Destructor Documentation	37

4.9.2.1 EventEngine()	37
4.9.2.2 ~EventEngine()	37
4.9.3 Member Function Documentation	37
4.9.3.1 addKeyPressed()	37
4.9.3.2 addMouseButtonPressed()	38
4.9.3.3 addMouseMoved()	38
4.9.3.4 getEvent()	39
4.9.3.5 getKeyPressedMap()	39
4.9.3.6 getKeyStatesMap()	39
4.9.3.7 getMouseButtonPressedMap()	40
4.9.3.8 getMouseMovedMap()	40
4.9.3.9 setKeyStatesMap()	40
4.10 EventTest Class Reference	41
4.11 GameEngine Class Reference	42
4.11.1 Detailed Description	45
4.11.2 Constructor & Destructor Documentation	45
4.11.2.1 GameEngine() [1/2]	45
4.11.2.2 GameEngine() [2/2]	45
4.11.2.3 ∼GameEngine()	46
4.11.3 Member Function Documentation	46
4.11.3.1 addWorld()	46
4.11.3.2 eventGameEngine()	47
4.11.3.3 getClock()	47
4.11.3.4 getCurrentWorld()	47
4.11.3.5 getDeltaTime()	48
4.11.3.6 getEventEngine()	48
4.11.3.7 getFilesRessources()	48
4.11.3.8 getMapFont()	49
4.11.3.9 getMapMusic()	49
4.11.3.10 getMapSound()	49
4.11.3.11 getMapTexture()	50
4.11.3.12 getWindow()	50
4.11.3.13 getWorld()	50
4.11.3.14 getWorldMap()	51
4.11.3.15 initialize()	51
4.11.3.16 initializeAllFiles()	51
4.11.3.17 initializeFont()	52
4.11.3.18 initializeMusic()	52
4.11.3.19 initializeMusicFunction()	52
4.11.3.20 initializeSound()	53
4.11.3.21 initializeSoundFunction()	53
4.11.3.22 initializeSpriteFunction()	53

4.11.3.23 initializeTextFunction()	54
4.11.3.24 initializeTexture()	54
4.11.3.25 initializeWorldMap()	54
4.11.3.26 isWindowOpen()	55
4.11.3.27 renderGameEngine()	55
4.11.3.28 run()	55
4.11.3.29 setCurrentWorld()	57
4.11.3.30 setDeltaTime()	57
4.11.3.31 updateGameEngine()	58
4.12 GameEngineTest Class Reference	58
4.13 ITransform Class Reference	60
4.13.1 Detailed Description	60
4.13.2 Constructor & Destructor Documentation	60
4.13.2.1 ∼ITransform()	60
4.13.3 Member Function Documentation	61
4.13.3.1 getTransform()	61
4.14 Music Class Reference	61
4.14.1 Detailed Description	63
4.14.2 Constructor & Destructor Documentation	63
4.14.2.1 Music()	63
4.14.2.2 ~Music()	63
4.14.3 Member Function Documentation	63
4.14.3.1 applyDeferredMusic()	64
4.14.3.2 getBit()	64
4.14.3.3 getLoop()	64
4.14.3.4 getMusic()	65
4.14.3.5 getStatus()	65
4.14.3.6 getVolume()	65
4.14.3.7 init()	66
4.14.3.8 pause()	66
4.14.3.9 play()	66
4.14.3.10 setDeferredMusic()	67
4.14.3.11 setLoop()	67
4.14.3.12 setMusic()	67
4.14.3.13 setVolume()	68
4.14.3.14 stop()	68
4.14.3.15 update()	68
4.15 MusicTests Class Reference	69
4.16 Rect< T > Class Template Reference	70
4.16.1 Detailed Description	70
4.16.2 Constructor & Destructor Documentation	71
4 16 2 1 Rept()	71

4.16.2.2 ∼Rect()	71
4.16.3 Member Function Documentation	72
4.16.3.1 contains()	72
4.16.3.2 getHeight()	72
4.16.3.3 getLeft()	73
4.16.3.4 getRect()	73
4.16.3.5 getTop()	73
4.16.3.6 getWidth()	74
4.17 Script Class Reference	74
4.18 Sound Class Reference	75
4.18.1 Detailed Description	76
4.18.2 Constructor & Destructor Documentation	76
4.18.2.1 Sound()	76
4.18.2.2 \sim Sound()	77
4.18.3 Member Function Documentation	77
4.18.3.1 applyDeferredSound()	77
4.18.3.2 getBit()	77
4.18.3.3 getLoop()	78
4.18.3.4 getSound()	78
4.18.3.5 getVolume()	78
4.18.3.6 init()	79
4.18.3.7 isPlaying()	79
4.18.3.8 pause()	79
4.18.3.9 play()	80
4.18.3.10 setDeferredSound()	80
4.18.3.11 setLoop()	80
4.18.3.12 setSound() [1/2]	81
4.18.3.13 setSound() [2/2]	81
4.18.3.14 setVolume()	82
4.18.3.15 stop()	82
4.18.3.16 update()	82
4.19 SoundTest Class Reference	83
4.20 Sprite Class Reference	84
4.20.1 Detailed Description	85
4.20.2 Constructor & Destructor Documentation	85
4.20.2.1 Sprite()	85
4.20.2.2 ∼Sprite()	86
4.20.3 Member Function Documentation	86
4.20.3.1 applyDeferredSprite()	86
4.20.3.2 draw()	86
4.20.3.3 getBit()	87
4.20.3.4 getSprite()	87

4.20.3.5 getTransform()
4.20.3.6 init()
4.20.3.7 setDeferredSprite()
4.20.3.8 setSprite() [1/2]
4.20.3.9 setSprite() [2/2] 89
4.20.3.10 setTransform()
4.20.3.11 update()
4.21 SpriteTest Class Reference
4.22 TestRect Class Reference
4.23 TesttoSFML Class Reference
4.24 TestVector2 Class Reference
4.25 TestWorld Class Reference
4.26 Text Class Reference
4.26.1 Detailed Description
4.26.2 Constructor & Destructor Documentation
4.26.2.1 Text()
4.26.2.2 ~Text()
4.26.3 Member Function Documentation
4.26.3.1 applyDeferredText()
4.26.3.2 draw()
4.26.3.3 getBit()
4.26.3.4 getColorFill()
4.26.3.5 getColorOutline()
4.26.3.6 getFont()
4.26.3.7 getSize()
4.26.3.8 getStringText()
4.26.3.9 getText()
4.26.3.10 getTransform()
4.26.3.11 init()
4.26.3.12 setDeferredText()
4.26.3.13 setFillColor()
4.26.3.14 setFont()
4.26.3.15 setOutlineColor()
4.26.3.16 setSize()
4.26.3.17 setString()
4.26.3.18 setText() [1/2]
4.26.3.19 setText() [2/2]
4.26.3.20 setTransform()
4.26.3.21 update()
4.27 TextTest Class Reference
4.28 toSFML Class Reference
4.28.1 Detailed Description 108

4.28.2 Constructor & Destructor Documentation	80
4.28.2.1 toSFML()	80
4.28.2.2 ~toSFML()	09
4.28.3 Member Function Documentation	09
4.28.3.1 toSFMLRect()	09
4.29 Transform Class Reference	10
4.29.1 Detailed Description	11
4.29.2 Constructor & Destructor Documentation	11
4.29.2.1 Transform()	11
$4.29.2.2 \sim Transform()$	12
4.29.3 Member Function Documentation	12
4.29.3.1 applyDeferredTransform()	12
4.29.3.2 getBit()	12
4.29.3.3 getPosition()	14
4.29.3.4 getRotation()	14
4.29.3.5 getScale()	14
4.29.3.6 getTransform()	15
4.29.3.7 init()	15
4.29.3.8 setDeferredTransform()	15
4.29.3.9 setPosition()	16
4.29.3.10 setRotation()	16
4.29.3.11 setScale()	16
4.29.3.12 setTransform()	18
4.29.3.13 update()	18
4.30 TransformTest Class Reference	19
4.31 Vector2< T > Class Template Reference	20
4.31.1 Detailed Description	20
4.31.2 Constructor & Destructor Documentation	20
4.31.2.1 Vector2() [1/2]	20
4.31.2.2 Vector2() [2/2]	21
4.31.2.3 ~Vector2()	21
4.31.3 Member Function Documentation	22
4.31.3.1 getVector2Struct()	22
4.31.3.2 getX()	22
4.31.3.3 getY()	23
4.31.3.4 setX()	23
4.31.3.5 setY()	23
4.32 World Class Reference	24
4.32.1 Detailed Description	26
4.32.2 Constructor & Destructor Documentation	26
4.32.2.1 World()	26
4.32.2.2 ∼World()	26

	.32.3 Member Function Documentation
	4.32.3.1 addEntityManager()
	4.32.3.2 createEntities()
	4.32.3.3 getEntitiesManager()
	4.32.3.4 getEntityManager()
	4.32.3.5 getEntityManagerMap()
	4.32.3.6 getNameWorld()
	4.32.3.7 init()
	4.32.3.8 setNameWorld()
Index	131

Chapter 1

Engine

Compilation

1.1.1 Linux

Use the following command to compile the engine: $_{\tt cmake\ -Bbuild\ make\ -Cbuild\ }$

Use the following command to compile the engine and its tests: cmake <code>-Bbuild -DBUILD_TESTS=ON make -Cbuild</code>

Use the following command for create the package (.tgz or .zip) after compile: $_{\mbox{\scriptsize cd}}$ $_{\mbox{\scriptsize build}}$ $_{\mbox{\scriptsize cpack}}$

2 Engine

Chapter 2

Hierarchical Index

2.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Archetypes
Color
Components
Entity
EntityManager
World
GameEngine
Music
Sound
Transform
Sprite
Text 96
DrawableComponent
Sprite
Text
EventEngine
GameEngine
ITransform
Sprite
Text
Rect < T >
Rect< float >
Script
testing::Test
EntityManagerTest
EntityTest
EventTest
GameEngineTest
MusicTests
SoundTest
SpriteTest
TestRect
TestVector2
TestWorld

4 Hierarchical Index

TesttoSFML						 				 										 		93
TextTest						 				 									 	 		107
TransformTes	t	 				 				 									 	 		119
toSFML																						108
Sprite						 													 	 		84
Vector2 $<$ T $>$.																						120
Vector2< float >																						120

Chapter 3

Class Index

3.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Archetypes	7
Color	
Color class: Color is a class that use for the color in game	7
Components	
Components class: Components is a class that represents a component in the game	13
DrawableComponent	
DrawableComponent class: DrawableComponent is a class that represents a drawable compo-	
nent in the game	16
Entity	
Entity class: Entity is a class that represents an entity in the game	18
EntityManager	29
EntityManagerTest	33
EntityTest	35
EventEngine	
EventEngine class: EventEngine is a class that represents the event engine of the game	36
EventTest	41
GameEngine	
GameEngine class: GameEngine is a class that represents the game engine	42
GameEngineTest	58
ITransform	
ITransform class: ITransform is a class that represents an interface of the Component Transform	60
Music	
Music class: Music is a class that represents the music in the world	61
MusicTests	69
Rect < T >	
Rect class: Rect is a class that represents a rectangle	70
Script	74
Sound	7.
Sound class: Sound is a class that represents the sound properties of a Component	75
SoundTest	83
Sprite	84
Sprite class: Sprite is a class that represents the rendering properties of a Component	
SpriteTest	91
TestRect	92
TesttoSFML	93

6 Class Index

TestVect	tor2	94
TestWorl	ld	95
Text		
	Text class: Text is a class that represents the text in the world	96
TextTest toSFML		107
	ToSFML class: toSFML is a class that convert some class into SFML class	108
Transfori	m	
	Transform class: Transform is a class that represents the transform of a Component	110
Transfori	mTest	119
Vector2<	<t></t>	
	Vector class: Vector is a class that represents a vector in 2 dimensions	120
World		
	World class: World is a class that represents the world of the game	124

Chapter 4

Class Documentation

4.1 Archetypes Class Reference

The documentation for this class was generated from the following file:


• src/Archetype/include/Archetypes.h

4.2 Color Class Reference

Color class: Color is a class that use for the color in game.

#include <Color.h>

Collaboration diagram for Color:



Public Member Functions

```
• Color ()
```

< Represent the Alpha of a color between 0 and 255.

Color (const sf::Color &sfmlColor)

Color constructor with sf::Color& as parameter.

∼Color ()=default

Default override Color destructor.

• sf::Uint8 getRed () const

getRed(): Get the sf::Uint8 red.

· sf::Uint8 getGreen () const

getGreen(): Get the sf::Uint8 green.

sf::Uint8 getBlue () const

getBlue(): Get the sf::Uint8 blue.

• sf::Uint8 getAlpha () const

getAlpha(): Get the sf::Uint8 alpha.

void setRed (int newRed)

setRed(int): Set the sf::Uint8 red with an int and convert into sf::Unit8 in the function.

• void setGreen (int newGreen)

setGreen(int): Set the sf::Uint8 green with an int and convert into sf::Unit8 in the function.

void setBlue (int newBlue)

setBlue(int): Set the sf::Uint8 blue with an int and convert into sf::Unit8 in the function.

void setAlpha (int newAlpha)

setAlpha(int): Set the sf::Uint8 alpha with an int and convert into sf::Unit8 in the function.

operator sf::Color () const

operator sf::Color() const: Convert Color classes into sf::Color

Static Public Member Functions

static Color fromSFMLColor (const sf::Color &sfColor)

fromSFMLColor(const sf::Color&): Convert SFML color into Color class.

Static Public Attributes

- static const Color Black = Color::fromSFMLColor(sf::Color::Black)
- static const Color White = Color::fromSFMLColor(sf::Color::White)
- static const Color Red = Color::fromSFMLColor(sf::Color::Red)
- static const Color Green = Color::fromSFMLColor(sf::Color::Green)
- static const Color Blue = Color::fromSFMLColor(sf::Color::Blue)
- static const Color **Yellow** = Color::fromSFMLColor(sf::Color::Yellow)

static const Color Cyan = Color::fromSFMLColor(sf::Color::Cyan)

- static const Color Magenta = Color::fromSFMLColor(sf::Color::Magenta)
- static const Color **Transparent** = Color::fromSFMLColor(sf::Color::Transparent)

4.2.1 Detailed Description

Color class: Color is a class that use for the color in game.

The Color class manages the color.

4.2 Color Class Reference 9

4.2.2 Constructor & Destructor Documentation

4.2.2.1 Color() [1/2]

```
Color::Color ( ) [inline]
```

< Represent the Alpha of a color between 0 and 255.

Default Color constructor.

Set the default value to "Default" and initialize red, green, blue and alpha to 255 for initialize the color white.

Parameters

void

Returns

void

4.2.2.2 Color() [2/2]

Color constructor with sf::Color& as parameter.

Parameters

sfmlColor	Represent a color preset or no from SFML.
-----------	---

Returns

void

4.2.2.3 ∼Color()

```
Color::~Color ( ) [default]
```

Default override Color destructor.

D _o			- 4		
Pа	ra	m	eı	e	rs

void

Returns

void

4.2.3 Member Function Documentation

4.2.3.1 fromSFMLColor()

fromSFMLColor(const sf::Color&): Convert SFML color into Color class.

Parameters

sfColor	The color from SFML
---------	---------------------

Returns

Color: Color class.

4.2.3.2 getAlpha()

```
sf::Uint8 Color::getAlpha ( ) const
```

getAlpha(): Get the sf::Uint8 alpha.

Parameters



Returns

sf::Uint8: The value of alpha.

4.2 Color Class Reference

4.2.3.3 getBlue()

```
sf::Uint8 Color::getBlue ( ) const

getBlue(): Get the sf::Uint8 blue.

Parameters

void
```

Returns

sf::Uint8: The value of blue.

4.2.3.4 getGreen()

```
sf::Uint8 Color::getGreen ( ) const
getGreen(): Get the sf::Uint8 green.
Parameters
```

Returns

void

sf::Uint8: The value of green.

4.2.3.5 getRed()

```
sf::Uint8 Color::getRed ( ) const
getRed(): Get the sf::Uint8 red.
```

Parameters

void

Returns

sf::Uint8: The value of red.

4.2.3.6 operator sf::Color()

```
Color::operator sf::Color ( ) const [explicit]
```

operator sf::Color() const: Convert Color classes into sf::Color

Parameters

void

Returns

sf::Color: Get the Color in sf::Color

4.2.3.7 setAlpha()

setAlpha(int): Set the sf::Uint8 alpha with an int and convert into sf::Unit8 in the function.

Parameters

newAlpha

Returns

void

4.2.3.8 setBlue()

setBlue(int): Set the sf::Uint8 blue with an int and convert into sf::Unit8 in the function.

Parameters

newBlue

Returns

void

4.2.3.9 setGreen()

setGreen(int): Set the sf::Uint8 green with an int and convert into sf::Unit8 in the function.

Parameters

newGreen

Returns

void

4.2.3.10 setRed()

setRed(int): Set the sf::Uint8 red with an int and convert into sf::Unit8 in the function.

Parameters

nowRod	Number between 0 and 255.
Hewneu	i Nullibel belweell 0 and 255.

Returns

void

The documentation for this class was generated from the following files:


- src/Other/include/Color.h
- src/Other/Color.cpp

4.3 Components Class Reference

Components class: Components is a class that represents a component in the game.

```
#include <Components.h>
```

Inheritance diagram for Components:



Public Member Functions

• Components ()=default

Default Components constructor.

virtual ∼Components ()=default

Components destructor.

• virtual bool init ()=0

init(): Initialize the component

virtual int getBit ()=0

getBit(): Get the bitmask of the component

• virtual void update (sf::Time timeDelta)=0

update(): Update the component

4.3.1 Detailed Description

Components class: Components is a class that represents a component in the game.

Components are the building blocks of the game. They are attached to entities and define their behavior.

4.3.2 Constructor & Destructor Documentation

4.3.2.1 Components()

Components::Components () [default]

Default Components constructor.

Parameters

void

Returns

void

4.3.2.2 \sim Components()

virtual Components::~Components () [virtual], [default]

Components destructor.

Parameters

void

Returns

void

4.3.3 Member Function Documentation

4.3.3.1 getBit()

virtual int Components::getBit () [pure virtual]

getBit(): Get the bitmask of the component

Parameters

void

Returns

int: bitmask of the component

Implemented in Entity, Transform, Text, Sprite, Sound, and Music.

4.3.3.2 init()

```
virtual bool Components::init ( ) [pure virtual]
```

init(): Initialize the component

Parameters



Returns

bool: true if the component is initialized, false otherwise

Implemented in World, EntityManager, Entity, Transform, Text, Sprite, Sound, and Music.

4.3.3.3 update()

update(): Update the component

Parameters

timeDelta	time elapsed since the last update
-----------	------------------------------------

Returns

void

Implemented in Sound, Music, Entity, Transform, Text, and Sprite.

The documentation for this class was generated from the following file:


• src/Components/include/Components.h

4.4 DrawableComponent Class Reference

DrawableComponent class: DrawableComponent is a class that represents a drawable component in the game.

#include <DrawableComponent.h>

Inheritance diagram for DrawableComponent:



Public Member Functions

- virtual \sim DrawableComponent ()=default
 - Default DrawableComponent constructor.
- virtual void draw (sf::RenderWindow &window) const =0

draw(): Draw the component

4.4.1 Detailed Description

DrawableComponent class: DrawableComponent is a class that represents a drawable component in the game.

DrawableComponents are components that can be drawn on the screen.

4.4.2 Constructor & Destructor Documentation

4.4.2.1 ∼DrawableComponent()

Default DrawableComponent constructor.

Parameters

void

Returns

void

4.4.3 Member Function Documentation

4.4.3.1 draw()

draw(): Draw the component

Parameters

window	Window to draw the component on
--------	---------------------------------

Returns

void

Implemented in Text, and Sprite.

The documentation for this class was generated from the following file:

• src/Components/include/DrawableComponent.h

4.5 Entity Class Reference


Entity class: Entity is a class that represents an entity in the game.

```
#include <entity.h>
```

Inheritance diagram for Entity:



Collaboration diagram for Entity:



Public Member Functions

- Entity ()
 - Default Entity constructor.
- Entity (const std::string &nameEntity, Archetypes newArchetype=Archetypes())
 - Entity constructor.
- ∼Entity () override=default

```
Entity destructor.
• int getBit () override
      getBit(): Get the bit of the Sprite.
· bool init () override
     init(): Initialize the entity

    std::string getName () const

     genName(): Get the name of the entity

    void setName (std::string newName)

      setName(): Set the name of the entity

    void update (sf::Time deltaTime) override

      update(sf::Time): Update the component Music

    void addDrawable (Components *component)

      addDrawable(): Add a drawable component to the entity

    void removeDrawable (Components *component)

      removeDrawable(): Remove a drawable component to the entity
• void drawEntity (sf::RenderWindow &window)
      drawEntity(): Draw the entities
• template<typename T , typename... TArgs>
  T & addComponent (TArgs &&... args)
      addComponent(): Add a component to the entity
template<typename T >
  bool removeComponent ()
      removeComponent(): Remove a component to the entity
• template<typename T >
  T & getComponent ()
      getComponent(): Get a component from the entity
template<typename T >
  std::size_t getComponentTypeID () noexcept
      getComponentTypeID(): Get the ID of a component

    std::bitset< 6 > getComponentBitset () const

      getComponentBitset(): Get the bitset of the components

    std::vector < DrawableComponent * > getDrawableComponents () const

      getDrawableComponents(): Get the drawable components of the entity

    std::array< Components *, 6 > getComponentArrays () const

     getComponentArrays(): Get the array of components
• void setActive (bool isActive)
     setActive(bool): Set the value active for using entity or not
• bool getActive () const
      getActive(): Get the value active for knowing if entity is using or not.

    void setDeferredEntity (std::function < void() > setter)

      setDeferredEntity(std::function<void()>): Set the deferred entity.

    void applyDeferredEntity ()

      setDeferredEntity(std::function<void()>): Set the deferred entity.
```

Additional Inherited Members

4.5.1 Detailed Description

Entity class: Entity is a class that represents an entity in the game.

The Entity class manages components associated with the entity.

4.5.2 Constructor & Destructor Documentation

4.5.2.1 Entity() [1/2]

```
Entity::Entity ( ) [inline]
```

Default Entity constructor.

Parameters



Returns

void

4.5.2.2 Entity() [2/2]

Entity constructor.

Parameters

nameEntity	name of the entity
newArchetype	archetype of the entity (optional, default = new archetype)

Returns

void

4.5.2.3 \sim Entity()

```
Entity::~Entity ( ) [override], [default]
```

Entity destructor.

Parameters

void

Returns

void

4.5.3 Member Function Documentation

4.5.3.1 addComponent()

addComponent(): Add a component to the entity

Template Parameters

T	Type of the component
TArgs	Variadic template for component constructor arguments.

Parameters

args	arguments of the component
------	----------------------------

Returns

T&: reference of the component

4.5.3.2 addDrawable()

addDrawable(): Add a drawable component to the entity

Parameters

component	component to add

Returns

void

4.5.3.3 applyDeferredEntity()

```
void Entity::applyDeferredEntity ( )
```

setDeferredEntity(std::function<void()>): Set the deferred entity.

Parameters

setter Function that will set the entity.

Returns

void

4.5.3.4 drawEntity()

drawEntity(): Draw the entities

Parameters

window	window where the entities are drawn
--------	-------------------------------------

Returns

void

4.5.3.5 getActive()

```
bool Entity::getActive ( ) const
```

getActive(): Get the value active for knowing if entity is using or not.

Parameters

void

Returns

bool: True if the engine use this entity, false otherwise.

4.5.3.6 getBit()

```
int Entity::getBit ( ) [override], [virtual]
getBit(): Get the bit of the Sprite.
```

Parameters



Returns

int: The bit of the Sprite.


Implements Components.

4.5.3.7 getComponent()

```
template<typename T >
template Text & Entity::getComponent< Text > ( )
```

getComponent(): Get a component from the entity

Template Parameters



Parameters

void

Returns

T&: reference of the component

4.5.3.8 getComponentArrays()

```
std::array< Components *, 6 > Entity::getComponentArrays ( ) const
```

getComponentArrays(): Get the array of components

Parameters

void

Returns

```
std::array<Components*, 6>: array of components
```

4.5.3.9 getComponentBitset()

```
std::bitset< 6 > Entity::getComponentBitset ( ) const
getComponentBitset(): Get the bitset of the components
Parameters
void
```

Returns

std::bitset<6>: bitset of the components

4.5.3.10 getComponentTypeID()

```
template<typename T >
template std::size_t Entity::getComponentTypeID
Text > ( ) [noexcept]
getComponentTypeID(): Get the ID of a component
```

Template Parameters

T Type of the component

Parameters

void

Returns

std::size_t: ID of the component

4.5.3.11 getDrawableComponents()

```
{\tt std::vector} < {\tt DrawableComponent} \ * \ > \ {\tt Entity::getDrawableComponents} \ (\ ) \ \ {\tt const} {\tt getDrawableComponents} () : \ {\tt Get\ the\ drawable\ components} \ \ of\ the\ entity
```

Da					
ra	ra	m	eı	œ	rs

Returns

std::vector<DrawableComponent*>: drawable components of the entity

4.5.3.12 getName()

```
std::string Entity::getName ( ) const
```

genName(): Get the name of the entity

Parameters



Returns

std::string: name of the entity

4.5.3.13 init()

```
bool Entity::init ( ) [override], [virtual]
```

init(): Initialize the entity

Parameters



Returns

bool: true if the entity is initialized, false otherwise

Implements Components.

Reimplemented in World, and EntityManager.

4.5.3.14 removeComponent()

```
template<typename T > template bool Entity::removeComponent< Text > ( )
```

removeComponent(): Remove a component to the entity

Template Parameters

T Type of the component

Returns

T&: reference of the component

4.5.3.15 removeDrawable()

removeDrawable(): Remove a drawable component to the entity

Parameters

component | component to remove

Returns

void

4.5.3.16 setActive()

setActive(bool): Set the value active for using entity or not

Parameters

isActive True or false;

Returns

void

4.5.3.17 setDeferredEntity()

```
void Entity::setDeferredEntity ( {\tt std::function} < {\tt void}() > {\tt setter} \ )
```

setDeferredEntity(std::function<void()>): Set the deferred entity.

Parameters

setter Function that will set the entity.

Returns

void

4.5.3.18 setName()

setName(): Set the name of the entity

Parameters

newName new name of the entity

Returns

void

4.5.3.19 update()

update(sf::Time): Update the component Music

Parameters

timeDelta sf::Time of the game.

Returns

void

Implements Components.

The documentation for this class was generated from the following files:


- src/Entity/include/entity.h
- src/Entity/entity.cpp

4.6 EntityManager Class Reference

Inheritance diagram for EntityManager:



Collaboration diagram for EntityManager:



Public Member Functions

• EntityManager ()=default

Default EntityManager constructor.

• \sim EntityManager () override=default

EntityManager destructor.

• bool init () override

initEntityManager(): Initialize the EntityManager.

• Entity & addEntity (const std::string &nameEntity, Archetypes newArchetype=Archetypes())

addEntity(): Create and add a new entity to the entity manager.

• Entity & getEntity (const std::string &nameEntity)

getEntity(): Get an entity from the entity manager by its name.

std::map< std::string, Entity * > getEntities () const

getEntities(): Get the EntityManager's entities.

std::map< std::string, Entity * > getEntityMap () const

getEntityMap(): Get the EntityManager's entity map.

Additional Inherited Members

4.6.1 Constructor & Destructor Documentation

4.6.1.1 EntityManager()

EntityManager::EntityManager () [default]

Default EntityManager constructor.

Parameters

void

Returns

void

4.6.1.2 ∼EntityManager()

```
EntityManager::~EntityManager ( ) [override], [default]
```

EntityManager destructor.

Parameters

void

Returns

void

4.6.2 Member Function Documentation

4.6.2.1 addEntity()

addEntity(): Create and add a new entity to the entity manager.

Template Parameters

T	Type of the entity.	
TArgs	Type of the arguments.	

Parameters

args	Arguments of the entity.

4.6.2.2 getEntities()

```
std::map< std::string, Entity * > EntityManager::getEntities ( ) const
```

getEntities(): Get the EntityManager's entities.

Parameters




Returns

 $std::map{<}std::string,\ Entity\ *{>}:\ Entities.$

4.6.2.3 getEntity()

getEntity(): Get an entity from the entity manager by its name.

Template Parameters



Parameters

nameEntity Name of the entity.

Returns

T&: Reference of the entity.

4.6.2.4 getEntityMap()

```
\verb|std::map| < \verb|std::string|, Entity| * > EntityManager::getEntityMap ( ) const| \\
```

getEntityMap(): Get the EntityManager's entity map.

Parameters

void

Returns

Entity::EntityMap: Entity map.

4.6.2.5 init()

bool EntityManager::init () [override], [virtual]

initEntityManager(): Initialize the EntityManager.

Parameters

void

Returns

bool: true if the EntityManager is initialized, false otherwise.

Reimplemented from Entity.

Reimplemented in World.

The documentation for this class was generated from the following files:


- src/Entity/include/entityManager.h
- src/Entity/entityManager.cpp

4.7 EntityManagerTest Class Reference

Inheritance diagram for EntityManagerTest:



Collaboration diagram for EntityManagerTest:



Protected Member Functions

- void **SetUp** () override
- void **TearDown** () override

Protected Attributes


• EntityManager entityManager {}

The documentation for this class was generated from the following file:


• tests/Entity/TestEntityManager.cpp

4.8 EntityTest Class Reference

Inheritance diagram for EntityTest:



Collaboration diagram for EntityTest:



Protected Attributes

- Entity entity
- Entity entity1

The documentation for this class was generated from the following file:


• tests/Entity/TestEntity.cpp

4.9 EventEngine Class Reference

EventEngine class: EventEngine is a class that represents the event engine of the game.

#include <eventEngine.h>

Inheritance diagram for EventEngine:



Public Member Functions

• EventEngine ()=default

Default EventEngine constructor.

- virtual ∼EventEngine ()=default
 - EventEngine destructor.
- sf::Event & getEvent ()

getEvent(): Get the SFML Event.

- $\bullet \ \ void \ add Key Pressed \ (sf:: Key board:: Key \ key board, \ const \ std:: function < void () > \& function) \\$
 - addKeyPressed(): Add a key pressed to the map.
- void addMouseButtonPressed (sf::Mouse::Button mouse, const std::function < void() > &function)
 addMouseButtonPressed(): Add a mouse button pressed to the map.
- void addMouseMoved (const std::string &nameEntity, const std::function< void()> &function)
 addMouseMoved(): Add a mouse moved to the map.
- std::map< sf::Keyboard::Key, std::function< void()>> & getKeyPressedMap ()
 getKeyPressedMap(): Get the map of the key pressed.
- $\bullet \ \, \text{std::map}{<} \ \, \text{sf::Mouse::Button, std::function}{<} \ \, \text{void()}{>} \ \, \text{>} \ \, \text{getMouseButtonPressedMap ()}$

getMouseButtonPressedMap(): Get the map of the mouse button pressed.

- $\bullet \ \, \text{std::map}{<} \ \, \text{std::string, std::function}{<} \ \, \text{void()}{>} > \& \ \, \text{getMouseMovedMap ()}$
- getMouseMovedPressedMap(): Get the map of the key pressed.
 std::map< sf::Keyboard::Key, bool > & getKeyStatesMap ()

getKeyStatesMap(): Get the map of the key states.

void setKeyStatesMap (sf::Keyboard::Key key)

setKeyStatesMap(sf::Keyboard::Key): Initialize the map of the key states for the parameter value to false

4.9.1 Detailed Description

EventEngine class: EventEngine is a class that represents the event engine of the game.

The EventEngine class manages the events of the game.

4.9.2 Constructor & Destructor Documentation

4.9.2.1 EventEngine() EventEngine::EventEngine () [default] Default EventEngine constructor. **Parameters** void Returns void 4.9.2.2 ∼EventEngine() virtual EventEngine::~EventEngine () [virtual], [default] EventEngine destructor. **Parameters** void Returns void

4.9.3 Member Function Documentation

4.9.3.1 addKeyPressed()

```
void EventEngine::addKeyPressed (
          sf::Keyboard::Key keyboard,
          const std::function void()> & function )
```

addKeyPressed(): Add a key pressed to the map.

Parameters

keyboard	SFML Keyboard::Key of the key pressed.	
function	Function to execute when the key is pressed.	

Returns

void

4.9.3.2 addMouseButtonPressed()

```
void EventEngine::addMouseButtonPressed ( sf::Mouse::Button\ \textit{mouse,} const std::function<br/>< void()> & function )
```

addMouseButtonPressed(): Add a mouse button pressed to the map.

Parameters

mouse	SFML Mouse::Button of the mouse button pressed.
function	Function to execute when the mouse button is pressed.

Returns

void

4.9.3.3 addMouseMoved()

addMouseMoved(): Add a mouse moved to the map.

Parameters

nameEntity	: Name of the Entity you want.	
function	Function to execute when the mouse moved on entity.	

Returns

void

4.9.3.4 getEvent()

```
sf::Event & EventEngine::getEvent ( )

getEvent(): Get the SFML Event.

Parameters

void
```

Returns

sf::Event: The SFML Event.

4.9.3.5 getKeyPressedMap()

```
 std::map < sf::Keyboard::Key, std::function < void() > > \& EventEngine::getKeyPressedMap() ) \\ getKeyPressedMap(): Get the map of the key pressed.
```

Parameters

void

Returns

std::map<sf::Keyboard::Key, std::function<void()>>: The map of the key pressed.

4.9.3.6 getKeyStatesMap()

```
\label{eq:std:map} $$std::map< sf::Keyboard::Key, bool > \& EventEngine::getKeyStatesMap () $$ getKeyStatesMap(): Get the map of the key states.
```

Parameters

void

Returns

std::map<sf::Keyboard::Key, bool>&: The map of the key states.

4.9.3.7 getMouseButtonPressedMap()

 $\verb|std::map| < sf::Mouse::Button, std::function| < void() > > & EventEngine::getMouseButtonPressedMap () \\$

getMouseButtonPressedMap(): Get the map of the mouse button pressed.

Parameters



Returns

std::map<sf::Mouse::Button, std::function<void()>>: The map of the mouse button pressed.

4.9.3.8 getMouseMovedMap()

getMouseMovedPressedMap(): Get the map of the key pressed.

Parameters

void

Returns

std::map<std::string, std::function<void()>>: The map of the mouse moved.

4.9.3.9 setKeyStatesMap()

setKeyStatesMap(sf::Keyboard::Key): Initialize the map of the key states for the parameter value to false

Parameters

key The touch of the keyboard with using SFML.

Returns


void

The documentation for this class was generated from the following files:


- src/Event/include/eventEngine.h
- src/Event/eventEngine.cpp

4.10 EventTest Class Reference

Inheritance diagram for EventTest:



Collaboration diagram for EventTest:



Protected Attributes

• EventEngine eventEngine

The documentation for this class was generated from the following file:


• tests/Event/TestEvent.cpp

4.11 GameEngine Class Reference


GameEngine class: GameEngine is a class that represents the game engine.

#include <gameEngine.h>

Inheritance diagram for GameEngine:



Collaboration diagram for GameEngine:



Public Member Functions

- GameEngine ()=default
 - < Time of the game. Using with the Clock.
- GameEngine (sf::VideoMode mode, const sf::String &title, sf::Uint32 style=sf::Style::Default, const sf::← ContextSettings &settings=sf::ContextSettings())

GameEngine constructor with parameters.

• \sim GameEngine () override=default

GameEngine destructor.

void run (std::map< std::string, std::unique_ptr< World >> mapWorld, const std::map< std::string, std
 ::string > &pathRessources, const std::string &firstScene)

run(): Run the game engine (with parameters).

• void renderGameEngine ()

renderGameEngine(): Render the game engine.

· void eventGameEngine ()

eventGameEngine(): Manage the events of the game engine.

• void updateGameEngine ()

updateGameEngine(): Update the game engine.

• bool isWindowOpen ()

isWindowOpen(): Check if the window is open.

void initialize (std::map< std::string, std::unique_ptr< World >> mapWorld, const std::string, std::string > &pathRessources, const std::string &firstScene)

initialize(): Initialize the game engine.

```
· void initializeSpriteFunction () const
      initializeSpriteFunction(): Initialize the sprites function.
· void initializeSoundFunction () const
      initializeSoundFunction(): Initialize the sound function.

    void initializeMusicFunction () const

      initializeMusicFunction(): Initialize the music function.

    void initializeTextFunction () const

      initializeFontFunction(): Initialize the font function.

    void initializeAllFiles (const std::map< std::string, std::string > &pathRessources)

      initializeAllFiles(): Initialize all the ressources files the engine need.

    void initializeTexture (std::string path)

      initialize Texture(): Initialize the textures with their path.

    void initializeSound (std::string path)

      initializeSound(): Initialize the sound with their path.

    void initializeMusic (std::string path)

      initializeMusic(): Initialize the music with their path.

    void initializeFont (std::string path)

      initializeFont(): Initialize the font with their path.

    void initializeWorldMap (std::map < std::string, std::unique ptr < World >> mapWorld)

      initializeWorldMap(): Initialize the world map.

    sf::RenderWindow & getWindow ()

      getWindow(): Get the window.

    EventEngine & getEventEngine ()

      getEventEngine(): Get the event engine.

    void setCurrentWorld (World *world)

      setCurrentWorld(): Set GameEngine's current world.

    World * getCurrentWorld () const

      getCurrentWorld(): Get GameEngine's current world.

    World & addWorld (const std::string &nameWorld, std::unique ptr< World > world)

      addWorld(): Add a world to the world map.

    World & getWorld (const std::string &nameWorld)

      getWorld(): Get a world from the world map with its name.
- std::map < std::string, std::shared\_ptr < sf::Texture >> getMapTexture () const
      getMapTexture(): Get GameEngine's map of the textures.

    std::map< std::string, World * > getWorldMap () const

      getWorldMap(): Get GameEngine's map of the worlds.

    std::map< std::string, std::shared ptr< sf::Music >> getMapMusic () const

      getMapMusic(): Get GameEngine's map of the music.
• std::map< std::string, std::shared ptr< sf::SoundBuffer > > getMapSound () const
      getMapSound(): Get GameEngine's map of the sound.

    std::map< std::string, std::shared_ptr< sf::Font > > getMapFont () const

      getMapFont(): Get GameEngine's map of the font.
• sf::Clock getClock () const
      getClock(): Get GameEngine's clock.

    sf::Time getDeltaTime () const

      getDeltaTime(): Get GameEngine's deltaTime.

    void setDeltaTime (sf::Time newTimeDelta)

      setDeltaTime(): Set GameEngine's deltaTime.
```

Static Public Member Functions

• static std::vector< std::string > getFilesRessources (const std::string &pathDirectory) getFilesRessources(): Get all the ressources type files in the given directory.

Additional Inherited Members

4.11.1 Detailed Description

GameEngine class: GameEngine is a class that represents the game engine.

The GameEngine class manages the game engine.

4.11.2 Constructor & Destructor Documentation

4.11.2.1 GameEngine() [1/2]

```
GameEngine::GameEngine ( ) [default]
```

< Time of the game. Using with the Clock.

Default GameEngine constructor.

Parameters

void

Returns

void

4.11.2.2 GameEngine() [2/2]

GameEngine constructor with parameters.

Parameters

mode	Video mode.
type	Type of the graphics ("2D" or "3D").
title	Title of the window.
style	Style of the window (sf::Style::Default by default).
settings	Settings of the window.

Returns

void

4.11.2.3 ∼GameEngine()

```
GameEngine::~GameEngine ( ) [override], [default]
```

GameEngine destructor.

Parameters



Returns

void

4.11.3 Member Function Documentation

4.11.3.1 addWorld()

addWorld(): Add a world to the world map.

Parameters

nameWorld	Name of the world.
world	World to add.

Returns

World&: The world.

4.11.3.2 eventGameEngine()

```
void GameEngine::eventGameEngine ( )
```

eventGameEngine(): Manage the events of the game engine.

Parameters

void

Returns

void

4.11.3.3 getClock()

```
sf::Clock GameEngine::getClock ( ) const
```

getClock(): Get GameEngine's clock.

Parameters

void

Returns

sf::Clock: GameEngine's clock.

4.11.3.4 getCurrentWorld()

```
World * GameEngine::getCurrentWorld ( ) const
```

getCurrentWorld(): Get GameEngine's current world.

Parameters

void

Returns

World*: GameEngine's current world.

4.11.3.5 getDeltaTime()

```
sf::Time GameEngine::getDeltaTime ( ) const
```

getDeltaTime(): Get GameEngine's deltaTime.

Parameters



Returns

sf::Time: GameEngine's deltaTimes.

4.11.3.6 getEventEngine()

```
EventEngine & GameEngine::getEventEngine ( )
```

getEventEngine(): Get the event engine.

Parameters

void

Returns

EventEngine&: GameEngine's EventEngine.

4.11.3.7 getFilesRessources()

getFilesRessources(): Get all the ressources type files in the given directory.

Parameters

pathDirectory Path of the directory.

Returns

std::vector<std::string>: Vector of the ressources type files' names.

4.11.3.8 getMapFont()

std::map< std::string, std::shared_ptr< sf::Font > > GameEngine::getMapFont () const
getMapFont(): Get GameEngine's map of the font.

Parameters

void

Returns

std::map<std::string, std::shared_ptr<sf::Font>>: GameEngine's map of the musics.

4.11.3.9 getMapMusic()

std::map< std::string, std::shared_ptr< sf::Music > > GameEngine::getMapMusic () const
getMapMusic(): Get GameEngine's map of the music.

Parameters

void

Returns

std::map<std::string, std::shared ptr<sf::Music>>: GameEngine's map of the musics.

4.11.3.10 getMapSound()

std::map< std::string, std::shared_ptr< sf::SoundBuffer > > GameEngine::getMapSound () const
getMapSound(): Get GameEngine's map of the sound.

Parameters

void

Returns

std::map<std::string, std::shared_ptr<sf::SoundBuffer>>: GameEngine's map of the musics.

4.11.3.11 getMapTexture()

```
std::map< std::string, std::shared_ptr< sf::Texture > > GameEngine::getMapTexture ( ) const
getMapTexture(): Get GameEngine's map of the textures.
```

Parameters



Returns

std::map<std::string, std::shared_ptr<sf::Texture>>: GameEngine's map of the textures.

4.11.3.12 getWindow()

```
sf::RenderWindow & GameEngine::getWindow ( )
getWindow(): Get the window.
```

Parameters



Returns

sf::RenderWindow&: GameEngine's window.

4.11.3.13 getWorld()

getWorld(): Get a world from the world map with its name.

Parameters

Returns

World&: GameEngine's world.

4.11.3.14 getWorldMap()

```
\verb|std::map| < \verb|std::string|, | \verb|World| * > \verb|GameEngine::getWorldMap| ( ) | const| \\
```

getWorldMap(): Get GameEngine's map of the worlds.

Parameters



Returns

std::map<std::string, World*>: GameEngine's map of the worlds.

4.11.3.15 initialize()

```
void GameEngine::initialize (
    std::map< std::string, std::unique_ptr< World >> mapWorld,
    const std::map< std::string, std::string > & pathRessources,
    const std::string & firstScene )
```

initialize(): Initialize the game engine.

Parameters

mapWorld	Map of World classes' unique pointers.		
pathRessources	Map of the path of the ressources (assets).		
firstScene	Name of the first scene.		

Returns

void

4.11.3.16 initializeAllFiles()

initializeAllFiles(): Initialize all the ressources files the engine need.

Parameters

pathRessources	Map of the path of the ressources (assets).	1
----------------	---	---

Returns

void

4.11.3.17 initializeFont()

```
void GameEngine::initializeFont (
    std::string path )
```

initializeFont(): Initialize the font with their path.

Parameters

path Path of the font file.

Returns

void

4.11.3.18 initializeMusic()

```
\begin{tabular}{ll} \beg
```

initializeMusic(): Initialize the music with their path.

Parameters

path Path of the music file.

Returns

void

4.11.3.19 initializeMusicFunction()

```
{\tt void \ GameEngine::} initialize {\tt MusicFunction} \ (\ ) \ {\tt const} \\ {\tt initialize MusicFunction} (): {\tt Initialize \ the \ music \ function}.
```

Parameters
void
Returns
void
4.11.3.20 initializeSound()
<pre>void GameEngine::initializeSound (std::string path)</pre>
initializeSound(): Initialize the sound with their path.
Parameters
path Path of the sound file.
Returns
void
4.11.3.21 initializeSoundFunction()
void GameEngine::initializeSoundFunction () const
initializeSoundFunction(): Initialize the sound function.
Parameters
void
Returns
void
4.11.3.22 initializeSpriteFunction()

Generated by Doxygen

void GameEngine::initializeSpriteFunction () const

initializeSpriteFunction(): Initialize the sprites function.

Da			_ 1		
Pа	ra	m	eı	re	rs

void

Returns

void

4.11.3.23 initializeTextFunction()

```
void GameEngine::initializeTextFunction ( ) const
```

initializeFontFunction(): Initialize the font function.

Parameters

void

Returns

void

4.11.3.24 initializeTexture()

```
void GameEngine::initializeTexture ( {\tt std::string}\ path\ )
```

initializeTexture(): Initialize the textures with their path.

Parameters

path Path of the texture.

Returns

void

4.11.3.25 initializeWorldMap()

```
void GameEngine::initializeWorldMap ( std::map < \ std::string, \ std::unique\_ptr < \ World >> \ mapWorld )
```

initializeWorldMap(): Initialize the world map.

Parameters

mapWorld Map of World classes' unique pointers.

Returns

void

4.11.3.26 isWindowOpen()

```
bool GameEngine::isWindowOpen ( )
```

isWindowOpen(): Check if the window is open.

Parameters

void

Returns

bool: True if the window is open, false otherwise.

4.11.3.27 renderGameEngine()

```
void GameEngine::renderGameEngine ( )
```

renderGameEngine(): Render the game engine.

Parameters

void

Returns

void

4.11.3.28 run()

```
const std::map< std::string, std::string > & pathRessources, const std::string & firstScene)
```

run(): Run the game engine (with parameters).

Parameters

mapWorld	Map of World classes' unique pointers.
pathRessources	Map of the path of the ressources (assets).
firstScene	Name of the first scene.

Returns

void

4.11.3.29 setCurrentWorld()

setCurrentWorld(): Set GameEngine's current world.

Parameters

world	World to set.
-------	---------------

Returns

void

4.11.3.30 setDeltaTime()

setDeltaTime(): Set GameEngine's deltaTime.

Parameters

newTimeDelta	New deltaTime for GameEngine's deltaTime.
--------------	---

Returns

void

4.11.3.31 updateGameEngine()

void GameEngine::updateGameEngine ()

updateGameEngine(): Update the game engine.

Parameters



Returns

void

The documentation for this class was generated from the following files:


- src/GameEngine/include/gameEngine.h
- src/GameEngine/gameEngine.cpp

4.12 GameEngineTest Class Reference

Inheritance diagram for GameEngineTest:



Collaboration diagram for GameEngineTest:



Protected Member Functions

• void TearDown () override

Protected Attributes

• GameEngine * gameEngine

The documentation for this class was generated from the following file:


• tests/GameEngine/TestGameEngine.cpp

4.13 ITransform Class Reference

ITransform class: ITransform is a class that represents an interface of the Component Transform.

#include <ITransform.h>

Inheritance diagram for ITransform:



Public Member Functions

- virtual ~ITransform ()=default

 Default Virtual ITransform destructor.
- virtual Transform * getTransform ()=0

getTransform(): Get the reference of the component Transform of the same Entity

4.13.1 Detailed Description

ITransform class: ITransform is a class that represents an interface of the Component Transform.

The ITransform interface give to components which need to have a reference to Transform

4.13.2 Constructor & Destructor Documentation

4.13.2.1 ∼ITransform()

virtual ITransform::~ITransform () [virtual], [default]

Default Virtual ITransform destructor.

Parameters

void

Returns

void

4.13.3 Member Function Documentation

4.13.3.1 getTransform()

```
virtual Transform* ITransform::getTransform ( ) [pure virtual]
```

getTransform(): Get the reference of the component Transform of the same Entity

Virtual function which get the reference of the Transform component from the same Entity when a component need to use Transform. If Transform don't exist getTransform() return nullptr.

Parameters



Returns

Transform*: The reference of Transform or nullptr.

Implemented in Text, and Sprite.

The documentation for this class was generated from the following file:


 $\bullet \ src/Components/all_components/include/ITransform.h$

4.14 Music Class Reference


Music class: Music is a class that represents the music in the world.

```
#include <Music.h>
```

Inheritance diagram for Music:



Collaboration diagram for Music:



Public Member Functions

```
• Music ()=default
```

< Bit of the Music

∼Music () override=default

Default override Music destructor.

• int getBit () override

getBit(): Get the bit of the Music.

· void update (sf::Time timeDelta) override

update(sf::Time): Update the component Music

· bool init () override

init(): Initialize the component.

void setMusic (std::map< std::string, std::shared_ptr< sf::Music >> mapMusic, const std::string &name←
 Music)

setMusic(std::map<std::string, std::shared_ptr<sf::Music>>, const std::string&): Initialize the sf::Music of the class.

void setDeferredMusic (std::function< void()> setter)

setDeferredMusic(std::function< void()>): Set the deferred function for Music.

void applyDeferredMusic ()

 ${\it apply Deferred Music (): Apply the deferred function for {\it Music}}$

std::shared_ptr< sf::Music > getMusic () const

getMusic(): Get the music.

• void play ()

play(): Play the music.

• void pause ()

pause(): Pause the music.

• void stop ()

stop(): Stop the music.

void setLoop (bool loop)

setLoop(bool): Set the loop of the music.

• bool getLoop () const

getLoop(): Get if the loop is set to True or False.

void setVolume (float volume)

setVolume(float): Set the volume of the music.

• float getVolume () const

getVolume(): Get the volume of the music.

• sf::SoundSource::Status getStatus () const

getStatus(): Get the status of the music. Playing, pause or stop.

4.14.1 Detailed Description

4.14.2.1 Music()

Music class: Music is a class that represents the music in the world.

The music class manages the music from an Entity using SFML.

4.14.2 Constructor & Destructor Documentation

Music::Music () [default] < Bit of the Music Default Music constructor. **Parameters** void Returns void 4.14.2.2 ∼Music() Music::~Music () [override], [default] Default override Music destructor. **Parameters** void Returns void

4.14.3 Member Function Documentation

4.14.3.1 applyDeferredMusic()

```
void Music::applyDeferredMusic ( )
applyDeferredMusic(): Apply the deferred function for Music
Parameters
 void
Returns
     void
4.14.3.2 getBit()
int Music::getBit ( ) [override], [virtual]
getBit(): Get the bit of the Music.
Parameters
 void
Returns
     int: The bit of the Music.
Implements Components.
```

4.14.3.3 getLoop()

bool Music::getLoop () const

getLoop(): Get if the loop is set to True or False.

Parameters

void

Returns

bool: True or False. If no music set, return false.

4.14 Music Class Reference 65

4.14.3.4 getMusic()

 $\verb|std::shared_ptr<| \verb|sf::Music| > \verb|Music::getMusic| () | const| \\$ getMusic(): Get the music. **Parameters**

void

Returns

std::shared_ptr<sf::Music>: The shared ptr of the music.

4.14.3.5 getStatus()

sf::SoundSource::Status Music::getStatus () const

getStatus(): Get the status of the music. Playing, pause or stop.

Parameters

void

Returns

sf::SoundSource::Status: Enumerator of sf::SoundSource::Status which is (Stopped, Paused, Playing). If no music set, return Stopped.

4.14.3.6 getVolume()

float Music::getVolume () const

getVolume(): Get the volume of the music.

Parameters

void

Returns

float: Float number that represents the volume between 0 and 100 of the music. If no music set, return -100.

4.14.3.7 init()

```
bool Music::init ( ) [override], [virtual]
init(): Initialize the component.
Parameters
```

Returns

void

bool: true if the component is initialized, false otherwise

Implements Components.

4.14.3.8 pause()

void Music::pause ()
pause(): Pause the music.

Parameters

void

Returns

void

4.14.3.9 play()

void Music::play ()

play(): Play the music.

Parameters

void

Returns

void

4.14 Music Class Reference 67

4.14.3.10 setDeferredMusic()

```
void Music::setDeferredMusic ( {\tt std::function} < {\tt void()} > {\tt setter} \ )
```

setDeferredMusic(std::function<void()>): Set the deferred function for Music.

Parameters

setter Function that will use Music.

Returns

void

4.14.3.11 setLoop()

```
void Music::setLoop (
          bool loop )
```

setLoop(bool): Set the loop of the music.

Parameters

```
loop True or False.
```

Returns

void

4.14.3.12 setMusic()

```
void Music::setMusic (
          std::map< std::string, std::shared_ptr< sf::Music >> mapMusic,
          const std::string & nameMusic )
```

 $setMusic(std::map < std::string, std::shared_ptr < sf::Music >>, const std::string\&): Initialize the sf::Music of the class.$

Parameters

mapMusic	Map of all the music loaded.
nameMusic	Name of the music loaded.

Returns

void

4.14.3.13 setVolume()

setVolume(float): Set the volume of the music.

Parameters

volume Float number that represents the volume between 0 and 100 of the music.

Returns

void

4.14.3.14 stop()

```
void Music::stop ( )
```

stop(): Stop the music.

Parameters

void

Returns

void

4.14.3.15 update()

update(sf::Time): Update the component Music

Parameters

timeDelta sf::Time of the game	٠.
--------------------------------	----

Returns

void


Implements Components.

The documentation for this class was generated from the following files:


- src/Components/all_components/include/Music.h
- src/Components/all_components/Music.cpp

4.15 MusicTests Class Reference

Inheritance diagram for MusicTests:



Collaboration diagram for MusicTests:



Protected Member Functions

- void **SetUp** () override
- · void TearDown () override

Protected Attributes

· Music music

The documentation for this class was generated from the following file:

tests/Components/all_components/TestMusic.cpp

4.16 Rect < T > Class Template Reference

Rect class: Rect is a class that represents a rectangle.

```
#include <Rect.h>
```

Public Member Functions

```
• Rect (T left, T top, T width, T height)
```

< Rect is the variable you can use for change the data in RectStruct.

∼Rect ()=default

Rect destructor.

RectStruct getRect () const

```
getRect(): Get the using RectStruct.
```

• T getLeft () const

getLeft(): Get the using RectStruct left.

• T getTop () const

getTop(): Get the using RectStruct top.

T getWidth () const

getWidth(): Get the using RectStruct width.

• T getHeight () const

getHeight(): Get the using RectStruct height.

• bool contains (T x, T y) const

contains(): Check if a point is in the rectangle.

4.16.1 Detailed Description

```
template < typename T> class Rect < T>
```

Rect class: Rect is a class that represents a rectangle.

This create a rectangle and using for what you want.

4.16.2 Constructor & Destructor Documentation

4.16.2.1 Rect()

< Rect is the variable you can use for change the data in RectStruct.

Rect constructor with parameters.

Template Parameters

T Type of the rect.

Parameters

left	Position x.
top	Position y.
width	Width of your rectangle.
height	Height of your rectangle.

Returns


void

4.16.2.2 ∼Rect()

```
\label{template} $$ \ensuremath{\sf template}$ < typename T > $$ \ensuremath{\sf Rect}$ < T >:: \sim Rect ( ) [default] $$
```

Rect destructor.

Template Parameters



Parameters

void

Returns

void

4.16.3 Member Function Documentation

4.16.3.1 contains()

```
template<typename T > template bool Rect< T >::contains ( T x, T y ) const
```

contains(): Check if a point is in the rectangle.

Template Parameters

```
T Type of the rect.
```

Parameters

X	: Position x of the point.
У	: Position y of the point.

Returns


T: T is the type you want (float, int,...).

4.16.3.2 getHeight()

```
template<typename T >
template int Rect< T >::getHeight ( ) const
```

getHeight(): Get the using RectStruct height.

Template Parameters



Parameters

void

Returns

T: T is the type you want (float, int,...).

4.16.3.3 getLeft()

```
template<typename T > template int Rect< T >::getLeft ( ) const
```

getLeft(): Get the using RectStruct left.

Template Parameters

T Type of the rect.

Parameters

void

Returns

T: T is the type you want (float, int,...).

4.16.3.4 getRect()

```
\label{template} $$ \ensuremath{\mbox{template}$<$typename T >} $$ \ensuremath{\mbox{RectStruct Rect}$< T >} :: getRect ( ) const [inline]
```

getRect(): Get the using RectStruct.

Parameters

void

Returns

Rect

4.16.3.5 getTop()

```
template<typename T > template int Rect< T >::getTop ( ) const
```

getTop(): Get the using RectStruct top.

Template Parameters

Τ	Type of the rect.
---	-------------------

Parameters



Returns


T: T is the type you want (float, int,...).

4.16.3.6 getWidth()

```
template<typename T > template int Rect< T >::getWidth ( ) const
```

getWidth(): Get the using RectStruct width.

Template Parameters



Parameters

void

Returns

T: T is the type you want (float, int,...).

The documentation for this class was generated from the following files:

- src/Other/include/Rect.h
- src/Other/Rect.cpp

4.17 Script Class Reference

Public Member Functions

• virtual void execute ()=0

The documentation for this class was generated from the following file:


• src/Script/include/Script.h

4.18 Sound Class Reference


Sound class: Sound is a class that represents the sound properties of a Component.

#include <Sound.h>

Inheritance diagram for Sound:



Collaboration diagram for Sound:



Public Member Functions

- Sound ()=default
 - < Bit of the Sound.
- ∼Sound () override=default

Default override Sound destructor.

- int getBit () override
 - getBit(): Get the bit of the Sound.
- void update (sf::Time timeDelta) override

update(sf::Time): Update the component Sound

- bool init () override
 - init(): Initialize the component.
- void setSound (const sf::Sound &sound)

setSound(const sf::Sound&): Set the sound with an existing one. Automatically set the component sound buffer.

 void setSound (std::map< std::string, std::shared_ptr< sf::SoundBuffer >> mapSound, const std::string &nameSound)

setSound(std::map<std::string, std::shared_ptr<sf::SoundBuffer>>, const std::string&): Initialize the sf::Sound of the class.

void setDeferredSound (std::function < void() > setter)

setDeferredSound(std::function<void()>): Set the deferred function for Sound.

• void applyDeferredSound ()

applyDeferredSound(): Apply the deferred function for Sound

• const sf::Sound & getSound () const

getSound(): Get the sound.

· void play ()

play(): Play the sound.

· void pause ()

pause(): Pause the sound.

• void stop ()

stop(): Stop the sound.

void setLoop (bool loop)

setLoop(bool): Set the loop of the sound.

bool getLoop () const

getLoop(): Get if the loop is set to True or False.

void setVolume (float volume)

setVolume(float): Set the volume of the sound.

• float getVolume () const

getVolume(): Get the volume of the sound.

• bool isPlaying () const

isPlaying(): Check if the sound is currently playing.

4.18.1 Detailed Description

Sound class: Sound is a class that represents the sound properties of a Component.

The Sound class manages the sound representation of a Component using SFML.

4.18.2 Constructor & Destructor Documentation

4.18.2.1 Sound()

Sound::Sound () [default]

< Bit of the Sound.

Default Sound constructor.

Parameters

void

Returns void 4.18.2.2 ∼Sound() Sound::~Sound () [override], [default] Default override Sound destructor. **Parameters** void Returns void 4.18.3 Member Function Documentation 4.18.3.1 applyDeferredSound() void Sound::applyDeferredSound () applyDeferredSound(): Apply the deferred function for Sound **Parameters** void Returns void 4.18.3.2 getBit() int Sound::getBit () [override], [virtual]

getBit(): Get the bit of the Sound.

Parameters
void
void
Returns
int: The bit of the Sound.
Implements Components.
4.18.3.3 getLoop()
<pre>bool Sound::getLoop () const</pre>
getLoop(): Get if the loop is set to True or False.
Parameters
void
Returns
bool: True or False.
seen nac of raise.
4.18.3.4 getSound()
<pre>const sf::Sound & Sound::getSound () const</pre>
getSound(): Get the sound.
Parameters
void
Returns
const sf::Sound&: The shared ptr of the sound.

4.18.3.5 getVolume()

float Sound::getVolume () const
getVolume(): Get the volume of the sound.

Parameters

void	

Returns

float: Float number that represents the volume between 0 and 100 of the sound.

4.18.3.6 init()

```
bool Sound::init ( ) [override], [virtual]
```

init(): Initialize the component.

Parameters



Returns

bool: true if the component is initialized, false otherwise

Implements Components.

4.18.3.7 isPlaying()

```
bool Sound::isPlaying ( ) const
```

isPlaying(): Check if the sound is currently playing.

Parameters



Returns

bool: True if the sound is playing, false otherwise.

4.18.3.8 pause()

```
void Sound::pause ( )
```

pause(): Pause the sound.

Parameters

void

Returns

void

4.18.3.9 play()

```
void Sound::play ( )
```

play(): Play the sound.

Parameters

void

Returns

void

4.18.3.10 setDeferredSound()

 $setDeferredSound(std::function < void() >) : Set \ the \ deferred \ function \ for \ Sound.$

Parameters

setter | Function that will use Sound.

Returns

void

4.18.3.11 setLoop()

```
void Sound::setLoop (
    bool loop )
```

setLoop(bool): Set the loop of the sound.

Parameters

loop	True or False.
------	----------------

Returns

void

4.18.3.12 setSound() [1/2]

setSound(const sf::Sound&): Set the sound with an existing one. Automatically set the component sound buffer.

Parameters

sound SFML Sound for sound.

Returns

void

4.18.3.13 setSound() [2/2]

 $setSound(std::map{<}std::string, std::shared_ptr{<}sf::SoundBuffer{>>}, const std::string\&): Initialize the sf::Sound of the class.$

Parameters

mapSound	Map of all the sound loaded.
nameSound	Name of the sound loaded.

Returns

void

4.18.3.14 setVolume()

setVolume(float): Set the volume of the sound.

Parameters

volume

Float number that represents the volume between 0 and 100 of the sound.

Returns

void

4.18.3.15 stop()

```
void Sound::stop ( )
```

stop(): Stop the sound.

Parameters

void

Returns

void

4.18.3.16 update()

update(sf::Time): Update the component Sound

Parameters

timeDelta sf::Time of the game.

Returns

void


Implements Components.

The documentation for this class was generated from the following files:


- src/Components/all_components/include/Sound.h
- src/Components/all_components/Sound.cpp

4.19 SoundTest Class Reference

Inheritance diagram for SoundTest:



Collaboration diagram for SoundTest:



Protected Member Functions

- void SetUp () override
- · void TearDown () override

Protected Attributes

Sound sound

The documentation for this class was generated from the following file:


• tests/Components/all_components/TestSound.cpp

4.20 Sprite Class Reference


Sprite class: Sprite is a class that represents the rendering properties of a Component.

```
#include <Sprite.h>
```

Inheritance diagram for Sprite:



Collaboration diagram for Sprite:



Public Member Functions

```
• Sprite ()
```

< Doing the animation.

∼Sprite () override=default

Default override Sprite destructor.

Transform * getTransform () override

getTransform(): Get the reference to the component Transform.

· bool init () override

init(): Initialize the component.

• int getBit () override

getBit(): Get the bit of the Music.

• void draw (sf::RenderWindow &window) const override

draw(): Draw the Sprite.

• void update (sf::Time deltaTime) override

update(sf::Time): Update the component Music

• sf::Sprite getSprite () const

getSprite(): Get the SFML Sprite for rendering.

void setSprite (const sf::Sprite &sprite)

setSprite(sf::Sprite&): Set the SFML Sprite with an existing one for rendering.

void setSprite (std::map< std::string, std::shared_ptr< sf::Texture >> mapTexture, const std::string &name
 Texture, bool animate=false, const std::vector< Rect< int >> &newFrames=std::vector< Rect< int >>(), int durationOfFrame=100)

Sets the sprite of the component.

void setDeferredSprite (std::function < void() > setter)

setDeferredSprite(std::function< void()>): Set the deferred sprite.

• void applyDeferredSprite ()

applyDeferredSprite(): Apply the deferred sprite.

void setTransform (Transform &newTransform)

setTransform(Transform&): Set the reference of the Transform component.

4.20.1 Detailed Description

Sprite class: Sprite is a class that represents the rendering properties of a Component.

The Sprite class manages the graphical representation of a Component using SFML.

4.20.2 Constructor & Destructor Documentation

4.20.2.1 Sprite()

```
Sprite::Sprite ( ) [inline]
```

< Doing the animation.

Default Sprite constructor.

Parameters void
Returns void
4.20.2.2 ~Sprite()
Sprite::~Sprite () [override], [default]
Default override Sprite destructor.
Parameters void
Returns
void
4.20.3 Member Function Documentation
4.20.3.1 applyDeferredSprite()
<pre>void Sprite::applyDeferredSprite ()</pre>
applyDeferredSprite(): Apply the deferred sprite.
Parameters void

```
4.20.3.2 draw()
```

void

Returns

draw(): Draw the Sprite.

Parameters

window | SFML RenderWindow where the Sprite will be drawn.

Returns

void

Implements DrawableComponent.

4.20.3.3 getBit()

```
int Sprite::getBit ( ) [override], [virtual]
```

getBit(): Get the bit of the Music.

Parameters

void

Returns

int: The bit of the Music.

Implements Components.

4.20.3.4 getSprite()

```
sf::Sprite Sprite::getSprite ( ) const
```

getSprite(): Get the SFML Sprite for rendering.

Parameters

void

Returns

sf::Sprite: SFML Sprite for rendering

4.20.3.5 getTransform()

```
Transform * Sprite::getTransform ( ) [override], [virtual]
```

getTransform(): Get the reference to the component Transform.

Parameters



Returns

Transform*: Reference of Transform

Implements ITransform.

4.20.3.6 init()

```
bool Sprite::init ( ) [override], [virtual]
```

init(): Initialize the component.

Parameters

void

Returns

bool: true if the component is initialized, false otherwise

Implements Components.

4.20.3.7 setDeferredSprite()

```
void Sprite::setDeferredSprite (
    std::function< void()> setter )
```

setDeferredSprite(std::function<void()>): Set the deferred sprite.

Parameters

setter | Function that will set the sprite.

Returns

void

4.20.3.8 setSprite() [1/2]

setSprite(sf::Sprite&): Set the SFML Sprite with an existing one for rendering.

Parameters

```
sprite SFML Sprite for rendering
```

Returns

void

4.20.3.9 setSprite() [2/2]

```
void Sprite::setSprite (
    std::map< std::string, std::shared_ptr< sf::Texture >> mapTexture,
    const std::string & nameTexture,
    bool animate = false,
    const std::vector< Rect< int >> & newFrames = std::vector<Rect<int>>>(),
    int durationOfFrame = 100 )
```

Sets the sprite of the component.

This function sets the sprite of the component using the provided texture map and texture name. Optionally, it can enable animation by providing a vector of frames and the duration of each frame.

Parameters

mapTexture	A map of texture names and their corresponding shared pointers to sf::Texture objects.
nameTexture	The name of the texture to set as the sprite.
animate	Flag indicating whether to enable animation or not. Default is false.
newFrames	A vector of frames to use for animation. Default is an empty vector.
durationOfFrame	The duration of each frame in milliseconds. Default is 100 milliseconds.

Returns

void

4.20.3.10 setTransform()

setTransform(Transform&): Set the reference of the Transform component.

Parameters

newTransform Reference of Transform.

Returns

void

4.20.3.11 update()

update(sf::Time): Update the component Music

Parameters

timeDelta sf::Time of the game.

Returns

void


Implements Components.

The documentation for this class was generated from the following files:


- src/Components/all_components/include/Sprite.h
- src/Components/all_components/Sprite.cpp

4.21 SpriteTest Class Reference

Inheritance diagram for SpriteTest:



Collaboration diagram for SpriteTest:



Protected Attributes


· Sprite sprite

The documentation for this class was generated from the following file:


• tests/Components/all_components/TestSprite.cpp

4.22 TestRect Class Reference

Inheritance diagram for TestRect:



Collaboration diagram for TestRect:



Protected Attributes


• Rect< float > rect = Rect<float>(0, 0, 0, 0)

The documentation for this class was generated from the following file:


• tests/Other/TestRect.cpp

4.23 TesttoSFML Class Reference

Inheritance diagram for TesttoSFML:



Collaboration diagram for TesttoSFML:



Protected Attributes


• toSFML toSFML1 = toSFML()

The documentation for this class was generated from the following file:


• tests/toSFML/TesttoSFML.cpp

4.24 TestVector2 Class Reference

Inheritance diagram for TestVector2:



Collaboration diagram for TestVector2:



Protected Attributes


• Vector2< float > vector2 = Vector2<float>(0, 0)

The documentation for this class was generated from the following file:


• tests/Other/TestVector2.cpp

4.25 TestWorld Class Reference

Inheritance diagram for TestWorld:



Collaboration diagram for TestWorld:



Protected Attributes

World world

The documentation for this class was generated from the following file:


tests/World/TestWorld.cpp

4.26 Text Class Reference


Text class: Text is a class that represents the text in the world.

```
#include <Text.h>
```

Inheritance diagram for Text:



Collaboration diagram for Text:



Public Member Functions

- Text ()
 - < Bit of the Text.
- ∼Text () override=default

Default override Text destructor.

4.26 Text Class Reference 97

```
• int getBit () override
      getBit(): Get the bit of the Text.
· void draw (sf::RenderWindow &window) const override
      draw(): Draw the Text.

    void update (sf::Time deltaTime) override

      update(sf::Time): Update the component Text
· bool init () override
      init(): Initialize the component.

    void setText (std::map< std::string, std::shared_ptr< sf::Font >> mapFont, const std::string &nameFont,

  const std::string &newStringText, int sizeText, Color fillColor)
      Sets the text of the component.

    void setText (std::map< std::string, std::shared_ptr< sf::Font >> mapFont, const std::string &nameFont,

  const std::string &newStringText, int sizeText, Color fillColor, Color outlineColor)
      Sets the text of the component.

    void setFont (std::map< std::string, std::shared_ptr< sf::Font >> mapFont, const std::string &nameFont)

      setFont(std::map<std::string, std::shared_ptr<sf::Font>>, const std::string&): Set the font of Text.

    void setString (const std::string &newStringText)

      setString(const std::string&): Set the string of Text.

    void setSize (int sizeText)

      setSize(int): Set the size of Text.

    void setOutlineColor (Color outlineColor)

      setOutlineColor(Color): Set the outline color of Text.

    void setFillColor (Color fillColor)

      setFillColor(Color): Set the fill color of Text.

    sf::Text getText () const

      getText(): Get the Text.

    sf::Font getFont () const

      getFont(): Get the Font.

    std::string getStringText () const

      getStringText(): Get the string.
• int getSize () const
      getSize(): Get the size.

    Color getColorFill () const

      getColorFill(): Get the fill color.

    Color getColorOutline () const

      getColorOutline(): Get the outline color.
• Transform * getTransform () override
      getTransform(): Get the reference to the component Transform.

    void setTransform (Transform &newTransform)

      setTransform(Transform&): Set the reference of the Transform component.

    void setDeferredText (std::function < void() > setter)

      setDeferredText(std::function<void()>): Set the deferred text.

    void applyDeferredText ()

      applyDeferredText(): Apply the deferred text.
```

4.26.1 Detailed Description

Text class: Text is a class that represents the text in the world.

The text class manages the text from an Entity using SFML.

4.26.2 Constructor & Destructor Documentation

4.26.3.1 applyDeferredText()

void Text::applyDeferredText ()

applyDeferredText(): Apply the deferred text.

4.26.2.1 Text() Text::Text () [inline] < Bit of the Text. Default Text constructor. **Parameters** void Returns void 4.26.2.2 ∼Text() Text::~Text () [override], [default] Default override Text destructor. **Parameters** void Returns void 4.26.3 Member Function Documentation

4.26 Text Class Reference 99

Parameters Void
Returns void
4.26.3.2 draw()
<pre>void Text::draw (sf::RenderWindow & window) const [override], [virtual]</pre>
draw(): Draw the Text.
Parameters window SFML RenderWindow where the Text will be drawn.
Returns void
Implements DrawableComponent.
4.26.3.3 getBit()
<pre>int Text::getBit () [override], [virtual]</pre>
getBit(): Get the bit of the Text.
Parameters void
Returns int: The bit of the Text.

Implements Components.

4.26.3.4 getColorFill()

```
Color Text::getColorFill ( ) const

getColorFill(): Get the fill color.

Parameters

void
```

Returns

Color: Fill color of the text.

4.26.3.5 getColorOutline()

```
Color Text::getColorOutline ( ) const

getColorOutline(): Get the outline color.

Parameters

void
```

Returns

Color: Outline color of the text.

4.26.3.6 getFont()

```
sf::Font Text::getFont ( ) const
getFont(): Get the Font.
Parameters
```

Returns

void

sf::Font: Font of the Text.

4.26 Text Class Reference 101

4.26.3.7 getSize()

```
int Text::getSize ( ) const
getSize(): Get the size.
Parameters
```

Returns

void

int: int number that represents size of the text.

4.26.3.8 getStringText()

```
std::string Text::getStringText ( ) const
getStringText(): Get the string.
```

Parameters



Returns

std::string: String of the text.

4.26.3.9 getText()

```
sf::Text Text::getText ( ) const
getText(): Get the Text.
Parameters
```

void

Returns

sf::Text: Text for draw.

4.26.3.10 getTransform()

```
Transform * Text::getTransform ( ) [override], [virtual]
```

getTransform(): Get the reference to the component Transform.

Parameters



Returns

Transform*: Reference of Transform

Implements ITransform.

4.26.3.11 init()

```
bool Text::init ( ) [override], [virtual]
```

init(): Initialize the component.

Parameters

void

Returns

bool: true if the component is initialized, false otherwise. If no Transform is set, returns false.

Implements Components.

4.26.3.12 setDeferredText()

setDeferredText(std::function<void()>): Set the deferred text.

Parameters

setter Function that will set the text.

4.26 Text Class Reference 103

Returns

void

4.26.3.13 setFillColor()

setFillColor(Color): Set the fill color of Text.

Parameters

fillColor	Color for the text.

Returns

void

4.26.3.14 setFont()

setFont(std::map<std::string, std::shared_ptr<sf::Font>>, const std::string&): Set the font of Text.

Parameters

mapFont	Map of all the font loaded.
nameFont	Name of the font loaded.

Returns

void

4.26.3.15 setOutlineColor()

setOutlineColor(Color): Set the outline color of Text.

Parameters

outlineColor | Color for the border of the text.

Returns

void

4.26.3.16 setSize()

setSize(int): Set the size of Text.

Parameters

sizeText Size of the text.

Returns

void

4.26.3.17 setString()

setString(const std::string&): Set the string of Text.

Parameters

newStringText String text for draw.

Returns

void

4.26.3.18 setText() [1/2]

4.26 Text Class Reference 105

```
const std::string & nameFont,
const std::string & newStringText,
int sizeText,
Color fillColor )
```

Sets the text of the component.

This function sets the Text of the component using the provided font map, the font name, a string for set the Text, the size of character and fill color for color the text.

Parameters

mapFont	Map of all the font loaded.
nameFont	Name of the font loaded.
newStringText	String text for draw.
sizeText	Size of the text.
fillColor	Color for the text.

Returns

void

4.26.3.19 setText() [2/2]

Sets the text of the component.

This function sets the Text of the component using the provided font map, the font name, a string for set the Text, the size of character, fill color for color the text and outline color for the border of the text.

Parameters

mapFont	Map of all the font loaded.
nameFont	Name of the font loaded.
newStringText	String text for draw.
sizeText	Size of the text.
fillColor	Color for the text.
outlineColor	Color for the border of the text.

Returns

void

4.26.3.20 setTransform()

setTransform(Transform&): Set the reference of the Transform component.

Parameters

newTransform Reference of Transform.

Returns

void

4.26.3.21 update()

update(sf::Time): Update the component Text

Parameters

timeDelta sf::Time of the game.

Returns

void


Implements Components.

The documentation for this class was generated from the following files:


- src/Components/all_components/include/Text.h
- src/Components/all_components/Text.cpp

4.27 TextTest Class Reference

Inheritance diagram for TextTest:



Collaboration diagram for TextTest:



Protected Member Functions

- void SetUp () override
- void TearDown () override

Protected Attributes

Text text

The documentation for this class was generated from the following file:


tests/Components/all_components/TestText.cpp

4.28 toSFML Class Reference

toSFML class: toSFML is a class that convert some class into SFML class.

```
#include <toSFML.h>
```

Inheritance diagram for toSFML:



Public Member Functions

```
• toSFML ()=default
```

Default toSFML constructor.

• ~toSFML ()=default

toSFML destructor.

• template<typename T >

```
sf::Rect< T> toSFMLRect (Rect< T> rect)
```

toSFMLRect(): Convert your Rect<T> into sf::Rect<T>.

4.28.1 Detailed Description

toSFML class: toSFML is a class that convert some class into SFML class.

Convert some class in SFML class.

4.28.2 Constructor & Destructor Documentation

4.28.2.1 toSFML()

```
toSFML::toSFML ( ) [default]
```

Default toSFML constructor.

Parameters
void
Void
Returns
void
void
4.28.2.2 ∼toSFML()
toSFML::~toSFML () [default]
toSFML destructor.
Parameters
void
Returns

4.28.3 Member Function Documentation

4.28.3.1 toSFMLRect()

```
template<typename T > template sf::Rect< float > toSFML::toSFMLRect ( Rect < T > rect \ )
```

toSFMLRect(): Convert your Rect<T> into sf::Rect<T>.

Template Parameters

T Type of the rect.

Parameters

rect The rect you want to convert.

Returns

sf:Rect<T>: SFML rect.

The documentation for this class was generated from the following files:


- src/toSFML/include/toSFML.h
- src/toSFML/toSFML.cpp

4.29 Transform Class Reference


Transform class: Transform is a class that represents the transform of a Component.

```
#include <Transform.h>
```

Inheritance diagram for Transform:



Collaboration diagram for Transform:



Public Member Functions

• Transform ()

Default Transform constructor.

• bool init () override

init(): Initialize the component

∼Transform () override=default

Transform destructor.

• void update (sf::Time deltaTime) override

update(sf::Time): Update the component Music

• int getBit () override

getBit(): Get the bitmask of the component

Vector2< float > getPosition () const

getPositionVector(): Get the position vector of the component;

float getRotation () const

getRotationVector(): Get the rotation vector of the component;

Vector2< float > getScale () const

getScaleVector(): Get the scale vector of the component;

• TransformStruct getTransform () const

getTransform(): Get the the transform of the component;

void setTransform (Vector2< float > newPosition, float newRotation, Vector2< float > newScale)

setTransform(): Set the transform of the component;

void setPosition (Vector2< float > newPosition)

setPosition(): Set the transform position of the component;

void setRotation (float newRotation)

setRotation(): Set the transform rotation of the component;

void setScale (Vector2< float > newScale)

setScale(): Set the transform scale of the component;

void setDeferredTransform (const std::function < void() > &setter)

setDeferredTransform(): Set the deferred transform.

• void applyDeferredTransform ()

applyDeferredTransform(): Apply the deferred transform.

4.29.1 Detailed Description

Transform class: Transform is a class that represents the transform of a Component.

The Transform class manages the position, rotation and scale of a Component.

4.29.2 Constructor & Destructor Documentation

4.29.2.1 Transform()

Transform::Transform () [inline]

Default Transform constructor.

Parameters void
Returns void
4.29.2.2 ∼Transform()
Transform::~Transform () [override], [default] Transform destructor. Parameters void
void 4.29.3 Member Function Documentation
4.29.3.1 applyDeferredTransform()
<pre>void Transform::applyDeferredTransform ()</pre>
applyDeferredTransform(): Apply the deferred transform.
Parameters void
Returns void
4.29.3.2 getBit()

int Transform::getBit () [override], [virtual]

getBit(): Get the bitmask of the component

114
Parameters
void
Returns
int: bitmask of the component
·
Implements Components.
implements components.
400.00
4.29.3.3 getPosition()
<pre>Vector2< float > Transform::getPosition () const</pre>
getPositionVector(): Get the position vector of the component;
Parameters
void
Returns
std::vector <float>: position vector of the component</float>
· ·
4.29.3.4 getRotation()
float Transform::getRotation () const
and Data-time Visit and Visit and Addition a
getRotationVector(): Get the rotation vector of the component;
Parameters
void
Returns
std::vector <float>: rotation vector of the component</float>
4.29.3.5 getScale()
• ·-···································

Vector2< float > Transform::getScale () const

getScaleVector(): Get the scale vector of the component;

Parameters

void	

Returns

std::vector<float>: scale vector of the component

4.29.3.6 getTransform()

```
{\tt Transform::} {\tt TransformStruct\ Transform::} {\tt getTransform\ (\ )\ const}
```

getTransform(): Get the the transform of the component;

Parameters



Returns

TransformStruct: struct of the Transform.

4.29.3.7 init()

```
bool Transform::init ( ) [override], [virtual]
```

init(): Initialize the component

Parameters



Returns

bool: true if the component is initialized, false otherwise

Implements Components.

4.29.3.8 setDeferredTransform()

```
void Transform::setDeferredTransform ( const\ std::function<\ void()>\ \&\ setter\ )
```

setDeferredTransform(): Set the deferred transform.

Parameters

setter Function that will set the transform.
--

Returns

void

4.29.3.9 setPosition()

```
void Transform::setPosition ( \label{eq:vector2} \mbox{Vector2} < \mbox{float} \ > \mbox{\it newPosition} \ )
```

setPosition(): Set the transform position of the component;

Parameters

newPosition : the new Vector2<float> position.

Returns

void

4.29.3.10 setRotation()

setRotation(): Set the transform rotation of the component;

Parameters

```
newRotation: the new float rotation.
```

Returns

void

4.29.3.11 setScale()

```
void Transform::setScale ( {\tt Vector2} < {\tt float} > {\tt newScale} \ )
```

setScale(): Set the transform scale of the component;

Parameters

Returns

void

4.29.3.12 setTransform()

setTransform(): Set the transform of the component;

Parameters

newPosition	: the new Vector2 <float> position.</float>
newRotation	: the new float rotation.
newScale	: the new Vector2 <float> scale.</float>

Returns

void

4.29.3.13 update()

update(sf::Time): Update the component Music

Parameters

timeDelta sf::Time of the game.

Returns

void


Implements Components.

The documentation for this class was generated from the following files:


- src/Components/all_components/include/Transform.h
- src/Components/all_components/Transform.cpp

4.30 TransformTest Class Reference

Inheritance diagram for TransformTest:



Collaboration diagram for TransformTest:



Protected Member Functions

- void SetUp () override
- · void TearDown () override

Protected Attributes

· Transform transform

The documentation for this class was generated from the following file:

tests/Components/all_components/TestTransform.cpp

4.31 Vector2 < T > Class Template Reference

Vector class: Vector is a class that represents a vector in 2 dimensions.

```
#include <Vector2.h>
```

Public Member Functions

```
    Vector2 ()
```

< Variable for using the value of the Vector2Struct.

Vector2 (T x, T y)

Vector2 constructor with parameters.

∼Vector2 ()=default

Vector2 destructor.

• Vector2Struct getVector2Struct () const

getVector2Struct(): Get the using Vector2Struct.

• T getX () const

getX(): Get x of Vector2Struct.

• T getY () const

getY(): Get y of Vector2Struct.

void setX (T newX)

setX(): Set x of Vector2Struct.

void setY (T newY)

setY(): Set y of Vector2Struct.

4.31.1 Detailed Description

```
template<typename T> class Vector2< T>
```

Vector class: Vector is a class that represents a vector in 2 dimensions.

This create a vector with 2 value.

4.31.2 Constructor & Destructor Documentation

4.31.2.1 Vector2() [1/2]

```
template<typename T >
Vector2< T >::Vector2 ( ) [inline]
```

< Variable for using the value of the Vector2Struct.

Vector2 constructor with parameters.

Template Parameters

Т	Type of the vector.
	Type of the vector.

Parameters

Х	Position x.
У	Position y.

Returns

void

4.31.2.2 Vector2() [2/2]

Vector2 constructor with parameters.

Template Parameters

```
T Type of the vector.
```

Parameters

Х	Position x.
У	Position y.

Returns

void

4.31.2.3 \sim Vector2()

```
template<typename T >
Vector2< T >::~Vector2 ( ) [default]
```

Vector2 destructor.

Template Parameters T Type of the vector.
Parameters void
Returns
void
4.31.3 Member Function Documentation
4.31.3.1 getVector2Struct()
<pre>template<typename t=""> template Vector2< int >::Vector2Struct Vector2< T >::getVector2Struct () const</typename></pre>
getVector2Struct(): Get the using Vector2Struct.
getVector2Struct(): Get the using Vector2Struct. Parameters
Parameters
Parameters void
Parameters void Returns
Parameters void Returns

4.31.3.2 getX()

```
template<typename T > template int Vector2< T >::getX ( ) const
```

getX(): Get x of Vector2Struct.

Template Parameters



4.31.3.3 getY()


```
template<typename T >
template int Vector2< T >::getY ( ) const
getY(): Get y of Vector2Struct.
```

Template Parameters

4.31.3.4 setX()

setX(): Set x of Vector2Struct.

Template Parameters



Parameters

newX The new value of x.

Returns

void

4.31.3.5 setY()

setY(): Set y of Vector2Struct.

Template Parameters

T Type of the Vector2

Parameters

newY The new value	of y.
--------------------	-------

Returns

void

The documentation for this class was generated from the following files:


- src/Other/include/Vector2.h
- src/Other/Vector2.cpp

4.32 World Class Reference

World class: World is a class that represents the world of the game.


```
#include <world.h>
```

Inheritance diagram for World:



4.32 World Class Reference 125

Collaboration diagram for World:



Public Member Functions

• World ()=default

Default World constructor.

∼World () override=default

World destructor.

• bool init () override

init(): Initialize the world.

void createEntities (std::map< std::string, std::pair< std::unique_ptr< EntityManager >, std::vector< std
 ::string >>> &mapEntityManager)

createEntities(): Create the entities.

• EntityManager & addEntityManager (const std::string &NameEntityManager)

addEntityManager(): Add an entity manager to the map.

• EntityManager & getEntityManager (const std::string &NameEntityManager)

getEntityManager(): Get the entity manager.

void setNameWorld (std::string newName)

setNameWorld(): Set the name of the world.

• std::string getNameWorld () const

getNameWorld(): Get the name of the world.

• std::map< std::string, EntityManager * > getEntityManagerMap () const

getEntityManagerMap(): Get the map of the entity manager.

• std::map< std::string, EntityManager * > getEntitiesManager () const

getEntitiesManager(): Get the entities


Additional Inherited Members

4.32.1 Detailed Description

World class: World is a class that represents the world of the game.

The World class manages the world of the game.

4.32.2 Constructor & Destructor Documentation



4.32.3 Member Function Documentation

4.32 World Class Reference 127

4.32.3.1 addEntityManager()

addEntityManager(): Add an entity manager to the map.

Parameters

NameEntityManager	Name of the entity manager.
-------------------	-----------------------------

Returns

EntityManager&: The entity manager.

4.32.3.2 createEntities()

createEntities(): Create the entities.

Parameters

mapEntityManager	Map of the entities manager's unique pointers.
keyEntityManager	Key of the entities manager.

Returns

void

4.32.3.3 getEntitiesManager()

```
\verb|std::map| < \verb|std::string|, | EntityManager * > \verb|World::getEntitiesManager| ( ) | const| \\
```

getEntitiesManager(): Get the entities

Parameters

void

Returns

std::map<std::string, EntityManager*>: Get the entities.

4.32.3.4 getEntityManager()

getEntityManager(): Get the entity manager.

Parameters

NameEntityManager	Name of the entity manager.
-------------------	-----------------------------

Returns

EntityManager&: The entity manager.

4.32.3.5 getEntityManagerMap()

```
\verb|std::map| < \verb|std::string|, EntityManager * > \verb|World::getEntityManagerMap| ( ) constitution | constitution
```

getEntityManagerMap(): Get the map of the entity manager.

Parameters

void

Returns

std::map<std::string, EntityManager*>: The map of the entity manager.

4.32.3.6 getNameWorld()

std::string World::getNameWorld () const

getNameWorld(): Get the name of the world.

Parameters

void

4.32 World Class Reference 129

Returns

std::string: The name of the world.

4.32.3.7 init()

```
bool World::init ( ) [override], [virtual]
```

init(): Initialize the world.

Parameters



Returns

bool: True if the world is initialized, false otherwise.

Reimplemented from EntityManager.

4.32.3.8 setNameWorld()

setNameWorld(): Set the name of the world.

Parameters

newName New name of the wo

Returns

void

The documentation for this class was generated from the following files:

- src/World/include/world.h
- src/World/world.cpp

Index

\sim Color	GameEngine, 46
Color, 9	applyDeferredEntity
~Components	Entity, 22
Components, 15	applyDeferredMusic
\sim DrawableComponent	Music, 63
DrawableComponent, 17	applyDeferredSound
~Entity	Sound, 77
Entity, 21	applyDeferredSprite
~EntityManager	Sprite, 86
EntityManager, 31	applyDeferredText
~EventEngine	Text, 98
EventEngine, 37	applyDeferredTransform
~GameEngine	Transform, 112
GameEngine, 46	Archetypes, 7
~ITransform	, p, .
ITransform, 60	Color, 7
~Music	∼Color, 9
Music, 63	Color, 9
~Rect	fromSFMLColor, 10
Rect < T >, 71	getAlpha, 10
~Sound	getBlue, 10
Sound, 77	getGreen, 11
~Sprite	getRed, 11
	operator sf::Color, 11
Sprite, 86 ∼Text	setAlpha, 12
	setBlue, 12
Text, 98	setGreen, 12
~Transform	setRed, 13
Transform, 112	Components, 13
~Vector2	•
Vector2< T >, 121	~Components, 15
~World	Components, 14
World, 126	getBit, 15
∼toSFML	init, 16
toSFML, 109	update, 16
	contains
addComponent	Rect $<$ T $>$, 72
Entity, 22	createEntities
addDrawable	World, 127
Entity, 22	duan
addEntity	draw
EntityManager, 31	DrawableComponent, 18
addEntityManager	Sprite, 86
World, 126	Text, 99
addKeyPressed	DrawableComponent, 16
EventEngine, 37	~DrawableComponent, 17
addMouseButtonPressed	draw, 18
EventEngine, 38	drawEntity
addMouseMoved	Entity, 23
EventEngine, 38	-
addWorld	Entity, 18

\sim Entity, 21	getFilesRessources, 48
addComponent, 22	getMapFont, 49
addDrawable, 22	getMapMusic, 49
applyDeferredEntity, 22	getMapSound, 49
drawEntity, 23	getMapTexture, 50
Entity, 21	getWindow, 50
getActive, 23	getWorld, 50
getBit, 23	getWorldMap, 51
getComponent, 24	initialize, 51
getComponentArrays, 24	initializeAllFiles, 51
getComponentBitset, 25	initializeFont, 52
getComponentTypeID, 25	initializeMusic, 52
getDrawableComponents, 25	initializeMusicFunction, 52
getName, 26	initializeSound, 53
init, 26	initializeSoundFunction, 53
removeComponent, 26	initializeSpriteFunction, 53
removeDrawable, 27	initializeTextFunction, 54
setActive, 27	initializeTexture, 54
setDeferredEntity, 28	initializeWorldMap, 54
setName, 28	isWindowOpen, 55
update, 28	renderGameEngine, 55
EntityManager, 29	run, 55
∼EntityManager, 31	setCurrentWorld, 57
addEntity, 31	setDeltaTime, 57
EntityManager, 30	updateGameEngine, 57
getEntities, 31	GameEngineTest, 58
getEntity, 32	getActive
getEntityMap, 32	Entity, 23
init, 33	getAlpha
	•
EntityManagerTest, 33	Color, 10
EntityManagerTest, 33 EntityTest, 35	Color, 10 getBit
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36	Color, 10 getBit Components, 15
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36	Color, 10 getBit Components, 15 Entity, 23
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36	Color, 10 getBit Components, 15 Entity, 23 Music, 64
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 40 setKeyStatesMap, 40	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getKeyStatesMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46 addWorld, 46	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24 getComponentBitset
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46 addWorld, 46 eventGameEngine, 47	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24 getComponentBitset Entity, 25
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46 addWorld, 46 eventGameEngine, 47 GameEngine, 45	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24 getComponentBitset Entity, 25 getComponentTypeID
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46 addWorld, 46 eventGameEngine, 47 GameEngine, 45 getClock, 47	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24 getComponentBitset Entity, 25 getComponentTypeID Entity, 25
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46 addWorld, 46 eventGameEngine, 47 GameEngine, 45 getClock, 47 getCurrentWorld, 47	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24 getComponentBitset Entity, 25 getComponentTypeID Entity, 25 getCurrentWorld
EntityManagerTest, 33 EntityTest, 35 EventEngine, 36 ~EventEngine, 37 addKeyPressed, 37 addMouseButtonPressed, 38 addMouseMoved, 38 EventEngine, 37 getEvent, 38 getKeyPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseButtonPressedMap, 39 getMouseMovedMap, 40 setKeyStatesMap, 40 eventGameEngine GameEngine, 47 EventTest, 41 fromSFMLColor Color, 10 GameEngine, 42 ~GameEngine, 46 addWorld, 46 eventGameEngine, 47 GameEngine, 45 getClock, 47	Color, 10 getBit Components, 15 Entity, 23 Music, 64 Sound, 77 Sprite, 87 Text, 99 Transform, 112 getBlue Color, 10 getClock GameEngine, 47 getColorFill Text, 99 getColorOutline Text, 100 getComponent Entity, 24 getComponentArrays Entity, 24 getComponentBitset Entity, 25 getComponentTypeID Entity, 25 getCurrentWorld GameEngine, 47

getDrawableComponents	Color, 11
Entity, 25	getRotation
getEntities	Transform, 114
EntityManager, 31	getScale
getEntitiesManager	Transform, 114
World, 127	getSize
getEntity	Text, 100
EntityManager, 32	getSound
getEntityManager	Sound, 78
World, 128	getSprite
getEntityManagerMap	Sprite, 87
World, 128	getStatus
getEntityMap	Music, 65
EntityManager, 32	getStringText
getEvent	Text, 101
EventEngine, 38	getText
getEventEngine	Text, 101
GameEngine, 48	getTop
getFilesRessources	Rect $<$ T $>$, 73
GameEngine, 48	getTransform
getFont	ITransform, 61
Text, 100	Sprite, 87
getGreen	Text, 101
Color, 11	Transform, 115
getHeight	getVector2Struct
Rect $<$ T $>$, 72	Vector2 $<$ T $>$, 122
getKeyPressedMap	getVolume
EventEngine, 39	Music, 65
getKeyStatesMap	Sound, 78
EventEngine, 39	getWidth
getLeft	Rect $<$ T $>$, 74
Rect $<$ T $>$, 73	getWindow
getLoop	GameEngine, 50
Music, 64	getWorld
Sound, 78	GameEngine, 50
getMapFont	getWorldMap
GameEngine, 49	GameEngine, 51
getMapMusic	getX
GameEngine, 49	Vector2< T >, 122
getMapSound	getY
GameEngine, 49	Vector2< T >, 122
getMapTexture	init
GameEngine, 50	
getMouseButtonPressedMap	Components, 16
EventEngine, 39	Entity, 26
getMouseMovedMap	EntityManager, 33
EventEngine, 40	Music, 65
getMusic	Sound, 79
Music, 64	Sprite, 88
getName	Text, 102
Entity, 26	Transform, 115
getNameWorld	World, 129
World, 128	initialize
getPosition	GameEngine, 51
Transform, 114	initializeAllFiles
getRect	GameEngine, 51
Rect < T >, 73	initializeFont
getRed	GameEngine, 52
	initializeMusic

GameEngine, 52	getLeft, 73
initializeMusicFunction	getRect, 73
GameEngine, 52	getTop, 73
initializeSound	getWidth, 74
GameEngine, 53	Rect, 71
initializeSoundFunction	removeComponent
GameEngine, 53	Entity, 26
initializeSpriteFunction	removeDrawable
GameEngine, 53	Entity, 27
initializeTextFunction	renderGameEngine
GameEngine, 54	GameEngine, 55
initializeTexture	run
GameEngine, 54	GameEngine, 55
initializeWorldMap	Carint 74
GameEngine, 54	Script, 74 setActive
isPlaying	
Sound, 79	Entity, 27 setAlpha
isWindowOpen	Color, 12
GameEngine, 55	setBlue
ITransform, 60	Color, 12
~ITransform, 60	setCurrentWorld
getTransform, 61	GameEngine, 57
Music 61	setDeferredEntity
Music, 61	Entity, 28
~Music, 63	setDeferredMusic
applyDeferredMusic, 63 getBit, 64	Music, 66
getLoop, 64	setDeferredSound
getMusic, 64	Sound, 80
getStatus, 65	setDeferredSprite
getVolume, 65	Sprite, 88
init, 65	setDeferredText
	Text, 102
Music, 63	setDeferredTransform
pause, 66 play, 66	Transform, 115
setDeferredMusic, 66	setDeltaTime
setLoop, 67	GameEngine, 57
setMusic, 67	setFillColor
setVolume, 68	Text, 103
stop, 68	setFont
update, 68	Text, 103
MusicTests, 69	setGreen
Music rests, 00	Color, 12
operator sf::Color	setKeyStatesMap
Color, 11	EventEngine, 40
,	setLoop
pause	Music, 67
Music, 66	Sound, 80
Sound, 79	setMusic
play	Music, 67
Music, 66	setName
Sound, 80	Entity, 28
	setNameWorld
Rect	World, 129
Rect $<$ T $>$, 71	setOutlineColor
Rect $<$ T $>$, 70	Text, 103
∼Rect, 71	setPosition
contains, 72	Transform, 116
getHeight, 72	setRed

Color, 13	SpriteTest, 91
setRotation	stop
Transform, 116	Music, 68
setScale	Sound, 82
Transform, 116	
setSize	TestRect, 92
Text, 104	TesttoSFML, 93
setSound	TestVector2, 94
Sound, 81	TestWorld, 95
setSprite	Text, 96
Sprite, 89	\sim Text, 98
setString	applyDeferredText, 98
Text, 104	draw, 99
setText	getBit, 99
Text, 104, 105	getColorFill, 99
setTransform	getColorOutline, 100
Sprite, 89	getFont, 100
•	getSize, 100
Text, 105	getStringText, 101
Transform, 118	getText, 101
setVolume	getText, 101 getTransform, 101
Music, 68	init, 102
Sound, 81	
setX	setDeferredText, 102
Vector2 $<$ T $>$, 123	setFillColor, 103
setY	setFont, 103
Vector2< T >, 123	setOutlineColor, 103
Sound, 75	setSize, 104
\sim Sound, 77	setString, 104
applyDeferredSound, 77	setText, 104, 105
getBit, 77	setTransform, 105
getLoop, 78	Text, 98
getSound, 78	update, 106
getVolume, 78	TextTest, 107
init, 79	toSFML, 108
isPlaying, 79	\sim toSFML, 109
pause, 79	toSFML, 108
play, 80	toSFMLRect, 109
setDeferredSound, 80	toSFMLRect
setLoop, 80	toSFML, 109
setSound, 81	Transform, 110
setVolume, 81	\sim Transform, 112
Sound, 76	applyDeferredTransform, 112
stop, 82	getBit, 112
update, 82	getPosition, 114
SoundTest, 83	getRotation, 114
Sprite, 84	getScale, 114
•	getTransform, 115
~Sprite, 86	init, 115
applyDeferredSprite, 86	setDeferredTransform, 115
draw, 86	setPosition, 116
getBit, 87	setRotation, 116
getSprite, 87	setScale, 116
getTransform, 87	setTransform, 118
init, 88	
setDeferredSprite, 88	Transform, 111
setSprite, 89	update, 118
setTransform, 89	TransformTest, 119
Sprite, 85	undate
update, 90	update Components 16
	Components, 16

```
Entity, 28
     Music, 68
     Sound, 82
     Sprite, 90
     Text, 106
     Transform, 118
updateGameEngine
     GameEngine, 57
Vector2
     Vector2< T >, 120, 121
Vector2< T>, 120
     \sim\!\text{Vector2, } \textcolor{red}{\textbf{121}}
     getVector2Struct, 122
     getX, 122
     getY, 122
    setX, 123
     setY, 123
     Vector2, 120, 121
World, 124
     \simWorld, 126
     addEntityManager, 126
     createEntities, 127
     getEntitiesManager, 127
     getEntityManager, 128
     getEntityManagerMap, 128
     getNameWorld, 128
     init, 129
     setNameWorld, 129
     World, 126
```