



SUREN NETWORK



NETWORK THEME



 R1

```
*Aug 19 16:53:06.421: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
*Aug 19 16:53:06.422: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
*Aug 19 16:53:06.422: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
*Aug 19 16:53:06.422: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
*Aug 19 16:53:06.422: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
*Aug 19 16:53:06.422: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
*Aug 19 16:53:06.425: unix_ll_sock_notify: Invalid L1 socket file descriptor fd
= 6
```

```
R1#config t
```

```
Enter configuration commands, one per line. End with CNTL/Z.
```

```
R1(config)#int e0/0
```

```
*Aug 19 16:53:23.778: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to do
wn
```

```
*Aug 19 16:53:23.779: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to do
wn
```

```
*Aug 19 16:53:24.781: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to down
```

```
*Aug 19 16:53:24.782: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to down
```

```
R1(config)#int e0/0
```

```
R1(config-if)#ip add 12.0.1.129 255.255.255.240
```

```
R1(config-if)#no sh
```

```
R1(config-if)#exit
```

```
R1(config)#int e0/1
```

```
R1(config-if)#ip add 12.0.1.145 255.255.255.252
```

```
R1(config-if)#no sh
```

```
R1(config-if)#exit
```

```
R1(config)#int e0/0
```

```
R1(config-if)#ip helper-address 12.0.1.153
```

```
R1(config-if)#
```

 R2

*Aug 19 16:47:49.380: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to do
wn

*Aug 19 16:47:49.385: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to do
wn

*Aug 19 16:47:50.380: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to down

*Aug 19 16:47:50.385: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to down

R2#config t

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#int e0/0

R2(config-if)#ip add 12.0.1.1 255.255.255.128

R2(config-if)#no sh

R2(config-if)#exit

R2(config)#int e0/1

R2(config-if)#ip add 12.0.1.149 255.255.255.252

R2(config-if)#no sh

R2(config-if)#exit

R2(config)#exit

R2#shwo

*Aug 19 16:51:01.662: %SYS-5-CONFIG_I: Configured from console by console

R2#show int br

^

% Invalid input detected at '^' marker.

R2#show ip int br

Interface	IP-Address	OK?	Method	Status	Prot
Ethernet0/0	12.0.1.1	YES	manual	up	up
Ethernet0/1	12.0.1.149	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

R2#config t

Enter configuration commands, one per line. End with CNTL/Z.

R2(config)#int e0/0

R2(config-if)#ip helper-address 12.0.1.153

R2(config-if)#

*Aug 19 16:52:39.053: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

R2(config-if)#

 R3

```
R3(config-if)#no sh
R3(config-if)#exit
R3(config)#exit
R3#sh
*Aug 19 16:39:03.776: %SYS-5-CONFIG_I: Configured from console by console
R3#show ip int b


| Interface   | IP-Address | OK? | Method | Status | Prot |
|-------------|------------|-----|--------|--------|------|
| ocol        |            |     |        |        |      |
| Ethernet0/0 | 12.0.0.1   | YES | manual | up     | up   |
| Ethernet0/1 | 12.0.1.153 | YES | manual | up     | up   |
| Ethernet0/2 | unassigned | YES | TFTP   | down   | down |
| Ethernet0/3 | unassigned | YES | TFTP   | down   | down |


R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip dhcp pool 2nd floor suren network
R3(dhcp-config)#network 12.0.1.0 255.255.255.128
R3(dhcp-config)#default-router 12.0.1.1
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#ip dhcp pool suren network 1st floor
R3(dhcp-config)#network 12.0.1.128 255.255.255.240
R3(dhcp-config)#default-router 12.0.1.129
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#ip dhcp pool network theme 1st floor
R3(dhcp-config)#network 129.70.1.0 255.255.255.192
R3(dhcp-config)#default-router 129.70.1.1
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#ip dhcp pool network theme 2nd floor
R3(dhcp-config)#network 129.70.0.0 255.255.255.0
R3(dhcp-config)#default-router 129.70.0.1
R3(dhcp-config)#dns-server 8.8.8.8
R3(dhcp-config)#lease 1 2 3
R3(dhcp-config)#exit
R3(config)#
```

 R4

```
Router(config)#
*Aug 19 17:00:36.841: %LINK-3-UPDOWN: Interface Ethernet0/2, changed state to up
*Aug 19 17:00:37.841: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
2, changed state to up
Router(config)#int e0/3
Router(config-if)#ip add 129.70.1.66 255.255.255.252
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#intt
*Aug 19 17:01:47.483: %LINK-3-UPDOWN: Interface Ethernet0/3, changed state to up
*Aug 19 17:01:48.483: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet0/
3, changed state to up
Router(config)#int e1/0
Router(config-if)#ip add 129.70.1.70 255.255.255.252
Router(config-if)#no sh
Router(config-if)#exit
Router(config)#exit
Router#
*Aug 19 17:02:41.237: %LINK-3-UPDOWN: Interface Ethernet1/0, changed state to up
*Aug 19 17:02:42.237: %LINEPROTO-5-UPDOWN: Line protocol on Interface Ethernet1/
0, changed state to up
Router#sh
*Aug 19 17:02:42.836: %SYS-5-CONFIG_I: Configured from console by console
Router#show ip int br
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              12.0.1.146      YES manual up          up
Ethernet0/1              12.0.1.150      YES manual up          up
Ethernet0/2              12.0.1.154      YES manual up          up
Ethernet0/3              129.70.1.66     YES manual up          up
Ethernet1/0              129.70.1.70     YES manual up          up
Ethernet1/1              unassigned      YES unset  administratively down down
Ethernet1/2              unassigned      YES unset  administratively down down
Ethernet1/3              unassigned      YES unset  administratively down down
Router#
```

R5

```
R5(config-if)#no sh
R5(config-if)#exit
R5(config)#int e0/0
R5(config-if)#ip add 129.70.1.65 255.255.255.252
R5(config-if)#no sh
R5(config-if)#exit
R5(config)#exit
R5#sh
*Aug 19 17:07:39.687: %SYS-5-CONFIG_I: Configured from console by console
R5#show ip int br


| Interface   | IP-Address  | OK? | Method | Status | Prot |
|-------------|-------------|-----|--------|--------|------|
| occol       |             |     |        |        |      |
| Ethernet0/0 | 129.70.1.65 | YES | manual | up     | up   |
| Ethernet0/1 | 129.70.1.1  | YES | manual | up     | up   |
| Ethernet0/2 | unassigned  | YES | TFTP   | down   | down |
| Ethernet0/3 | unassigned  | YES | TFTP   | down   | down |


R5#config
Configuring from terminal, memory, or network [terminal]? t
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#config t
^
% Invalid input detected at '^' marker.
R5(config)#int eo/1
^
% Invalid input detected at '^' marker.
R5(config)#exit
R5#
*Aug 19 17:08:22.721: %SYS-5-CONFIG_I: Configured from console by console
R5#config t
Enter configuration commands, one per line. End with CNTL/Z.
R5(config)#int e0/1
R5(config-if)#ip d
*Aug 19 17:08:48.710: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R5(config-if)#ip helper-address 12.0.1.153
R5(config-if)#exit
R5(config)#
```

```
R6#
R6#config t
Enter configuration commands, one per line.  End with CNTL/Z.
R6(config)#int e0/0
R6(config-if)#ip add 129.70.1.69 255.255.255.252
R6(config-if)#no sh
R6(config-if)#exit
R6(config)#int e0/1
R6(config-if)#ip add 129.70.0.1 255.255.255.0
R6(config-if)#no sh
R6(config-if)#exit
R6(config)#int e0/1
R6(config-if)#ip helper-address 12.0.1.153
R6(config-if)#exit
R6(config)#exit
R6#show
*Aug 19 17:13:26.839: %SYS-5-CONFIG_I: Configured from console by console
R6#show ip int br

```

Interface	IP-Address	OK?	Method	Status	Prot
ocol					
Ethernet0/0	129.70.1.69	YES	manual	up	up
Ethernet0/1	129.70.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down
Ethernet0/3	unassigned	YES	TFTP	down	down

```
R6#
```

