DerivedStateModel

5.3

Generated by Doxygen 1.8.14

Contents

1	Mod	dule Index	1
	1.1	Modules	1
2	Nam	nespace Index	3
	2.1	Namespace List	3
3	Hier	rarchical Index	5
	3.1	Class Hierarchy	5
4	Data	a Structure Index	7
	4.1	Data Structures	7
5	File	Index	9
	5.1	File List	9
6	Mod	dule Documentation	11
	6.1	Models	11
		6.1.1 Detailed Description	11
	6.2	Dynamics	12
		6.2.1 Detailed Description	12
	6.3	DerivedState	13
		6.3.1 Detailed Description	14
7	Nam	nespace Documentation	15
	7.1	jeod Namespace Reference	15
		7.1.1 Detailed Description	16
		7.1.2 Variable Documentation	16
		7.1.2.1 epsilon	16

ii CONTENTS

Data	Structi	ture Documentation		17
8.1	jeod::D	DerivedState Class Reference		17
	8.1.1	Detailed Description		18
	8.1.2	Constructor & Destructor Documentation		18
		8.1.2.1 DerivedState() [1/2]		18
		8.1.2.2 ~DerivedState()		18
		8.1.2.3 DerivedState() [2/2]		18
	8.1.3	Member Function Documentation		19
		8.1.3.1 find_planet()		19
		8.1.3.2 initialize()		19
		8.1.3.3 operator=()		20
		8.1.3.4 set_reference_name()		20
		8.1.3.5 update()		20
	8.1.4	Friends And Related Function Documentation		21
		8.1.4.1 init_attrjeodDerivedState		21
		8.1.4.2 InputProcessor		21
	8.1.5	Field Documentation		21
		8.1.5.1 reference_name		21
		8.1.5.2 state_identifier		21
		8.1.5.3 subject		22
8.2	jeod::D	DerivedStateMessages Class Reference		22
	8.2.1	Detailed Description		23
	8.2.2	Constructor & Destructor Documentation		23
		8.2.2.1 DerivedStateMessages() [1/2]		23
		8.2.2.2 DerivedStateMessages() [2/2]		23
	8.2.3	Member Function Documentation		23
		8.2.3.1 operator=()		23
	8.2.4	Friends And Related Function Documentation		23
		8.2.4.1 init_attrjeodDerivedStateMessages		23
		8.2.4.2 InputProcessor		24
	8.1	8.1 jeod::l 8.1.1 8.1.2 8.1.3 8.1.4 8.1.5 8.2 jeod::l 8.2.1 8.2.2	8.1.1 Detailed Description 8.1.2 Constructor & Destructor Documentation 8.1.2.1 DerivedState() [1/2] 8.1.2.2 ~DerivedState() [2/2] 8.1.3.1 DerivedState() [2/2] 8.1.3.2 DerivedState() [2/2] 8.1.3.3 DerivedState() [2/2] 8.1.3.4 set_reference_name() 8.1.3.5 update() 8.1.3.5 update() 8.1.4.1 init_attrjeod_DerivedState 8.1.4.2 InputProcessor 8.1.5 Field Documentation 8.1.5.1 reference_name 8.1.5.2 state_identifier 8.1.5.3 subject 8.2 jeod::DerivedStateMessages Class Reference 8.2.1 Detailed Description 8.2.2.1 DerivedStateMessages() [1/2] 8.2.2.2 DerivedStateMessages() [1/2] 8.2.3.1 operator=() 8.2.4 Friends And Related Function Documentation 8.2.3.1 operator=() 8.2.4 Friends And Related Function Documentation 8.2.3.1 operator=() 8.2.4 Friends And Related Function Documentation 8.2.4.1 init_attrjeod_DerivedStateMessages	8.1 jeod::DerivedState Class Reference 8.1.1 Detailed Description 8.1.2 Constructor & Destructor Documentation 8.1.2.1 DerivedState() [1/2] 8.1.2.2 ~DerivedState() 8.1.3.3 DerivedState() [2/2] 8.1.3 Member Function Documentation 8.1.3.1 find_planet() 8.1.3.2 initialize() 8.1.3.3 operator=() 8.1.3.4 set_reference_name() 8.1.3.5 update() 8.1.4.1 init_attrjeod_DerivedState 8.1.4.2 InputProcessor 8.1.5 Field Documentation 8.1.5.1 reference_name 8.1.5.2 state_identifier 8.1.5.3 subject 8.2 jeod::DerivedStateMessages Class Reference 8.2.1 Detailed Description 8.2.2 Constructor & Destructor Documentation 8.2.2.1 DerivedStateMessages() [1/2] 8.2.2.2 DerivedStateMessages() [1/2] 8.2.3 Member Function Documentation 8.2.3.1 operator=() 8.2.4 Friends And Related Function Documentation 8.2.3.1 operator=() 8.2.4 Friends And Related Function Documentation 8.2.3.1 operator=()

CONTENTS

	8.2.5	Field Do	cumentation	24
		8.2.5.1	divide_by_zero	24
		8.2.5.2	fatal_error	24
		8.2.5.3	illegal_value	24
		8.2.5.4	invalid_name	25
		8.2.5.5	invalid_object	25
		8.2.5.6	null_pointer	25
		8.2.5.7	trace	25
8.3	jeod::E	ulerDerive	edState Class Reference	26
	8.3.1	Detailed	Description	27
	8.3.2	Construc	ctor & Destructor Documentation	27
		8.3.2.1	EulerDerivedState() [1/2]	27
		8.3.2.2	~EulerDerivedState()	27
		8.3.2.3	EulerDerivedState() [2/2]	27
	8.3.3	Member	Function Documentation	27
		8.3.3.1	initialize() [1/2]	27
		8.3.3.2	initialize() [2/2]	28
		8.3.3.3	operator=()	28
		8.3.3.4	update()	28
	8.3.4	Friends A	And Related Function Documentation	29
		8.3.4.1	init_attrjeodEulerDerivedState	29
		8.3.4.2	InputProcessor	29
	8.3.5	Field Do	cumentation	29
		8.3.5.1	body_ref_angles	29
		8.3.5.2	ref_body_angles	30
		8.3.5.3	rel_frame	30
		8.3.5.4	rel_state	30
		8.3.5.5	sequence	30
8.4	jeod::L	vlhDerived	dState Class Reference	31
	8.4.1	Detailed	Description	32

iv CONTENTS

8.4.2	Construc	ctor & Destructor Documentation	32
	8.4.2.1	LvlhDerivedState() [1/2]	32
	8.4.2.2	~LvIhDerivedState()	32
	8.4.2.3	LvlhDerivedState() [2/2]	32
8.4.3	Member	Function Documentation	32
	8.4.3.1	initialize()	32
	8.4.3.2	operator=()	33
	8.4.3.3	update()	33
8.4.4	Friends A	And Related Function Documentation	33
	8.4.4.1	init_attrjeodLvlhDerivedState	33
	8.4.4.2	InputProcessor	33
8.4.5	Field Do	cumentation	34
	8.4.5.1	local_dm	34
	8.4.5.2	lvlh_frame	34
	8.4.5.3	lvlh_state	34
	8.4.5.4	planet_centered_inertial	34
	8.4.5.5	register_frame	35
jeod::L	vlhRelativ	eDerivedState Class Reference	35
8.5.1	Detailed	Description	36
8.5.2	Construc	ctor & Destructor Documentation	36
	8.5.2.1	LvlhRelativeDerivedState() [1/2]	36
	8.5.2.2	$\sim \! LvIhRelativeDerivedState() \dots \dots \dots \dots \dots \dots \dots \dots \dots $	36
	8.5.2.3	LvlhRelativeDerivedState() [2/2]	37
8.5.3	Member	Function Documentation	37
	8.5.3.1	convert_circ_to_rect()	37
	8.5.3.2	convert_rect_to_circ()	37
	8.5.3.3	do_theta_dot_correction()	38
	8.5.3.4	initialize()	38
	8.5.3.5	operator=()	38
	8.5.3.6	update()	39
	8.4.3 8.4.4 8.4.5 jeod::L 8.5.1 8.5.2	8.4.2.1 8.4.2.2 8.4.2.3 8.4.2.3 8.4.3.1 8.4.3.2 8.4.3.3 8.4.4.1 8.4.4.2 8.4.5.1 8.4.5.2 8.4.5.3 8.4.5.4 8.4.5.5 jeod::LvlhRelativ 8.5.1 Detailed 8.5.2 Construct 8.5.2.1 8.5.2.2 8.5.2.3 8.5.3.3 8.5.3.1 8.5.3.2 8.5.3.3 8.5.3.4 8.5.3.5	8.4.2.1 LvlhDerivedState() [1/2] 8.4.2.2 ~LvlhDerivedState() [2/2] 8.4.3 Member Function Documentation 8.4.3.1 initialize() . 8.4.3.2 operator=() . 8.4.3.3 update() . 8.4.4.5 Friends And Related Function Documentation 8.4.4.1 init_attrjood_LvlhDerivedState 8.4.4.2 InputProcessor 8.4.5 Field Documentation 8.4.5.1 local_dm . 8.4.5.2 lvlh_frame 8.4.5.3 lvlh_state . 8.4.5.5 register_frame sedd:LvlhRelativeDerivedState Class Reference 8.5.1 Detailed Description 8.5.2 Constructor & Destructor Documentation 8.5.2.1 LvlhRelativeDerivedState() [1/2] 8.5.2.2 ~LvlhRelativeDerivedState() 8.5.2.3 LvlhRelativeDerivedState() 8.5.2.3 LvlhRelativeDerivedState() 8.5.3.3 Member Function Documentation 8.5.3.1 convert_circ_to_rect() . 8.5.3.2 convert_rect_to_circ() . 8.5.3.3 do_theta_dot_correction() . 8.5.3.4 initialize() . 8.5.3.5 operator=() .

CONTENTS

	8.5.4	Friends A	And Related Function Documentation	39
		8.5.4.1	init_attrjeodLvlhRelativeDerivedState	39
		8.5.4.2	InputProcessor	39
	8.5.5	Field Do	cumentation	39
		8.5.5.1	lvlh_type	39
		8.5.5.2	use_theta_dot_correction	40
8.6	jeod::N	ledDerived	dState Class Reference	40
	8.6.1	Detailed	Description	41
	8.6.2	Construc	ctor & Destructor Documentation	41
		8.6.2.1	NedDerivedState() [1/2]	41
		8.6.2.2	~NedDerivedState()	41
		8.6.2.3	NedDerivedState() [2/2]	42
	8.6.3	Member	Function Documentation	42
		8.6.3.1	compute_ned_frame()	42
		8.6.3.2	initialize()	42
		8.6.3.3	operator=()	43
		8.6.3.4	set_use_alt_pfix()	43
		8.6.3.5	update()	43
	8.6.4	Friends A	And Related Function Documentation	43
		8.6.4.1	init_attrjeodNedDerivedState	43
		8.6.4.2	InputProcessor	43
	8.6.5	Field Do	cumentation	44
		8.6.5.1	local_dm	44
		8.6.5.2	ned_state	44
		8.6.5.3	pfix_ptr	44
		8.6.5.4	pfix_rel_state	44
		8.6.5.5	planet	45
		8.6.5.6	register_frame	45
		8.6.5.7	use_alt_pfix	45
8.7	jeod::C)rbElemDe	erivedState Class Reference	45

vi

	8.7.1	Detailed	Description	46
	8.7.2	Construc	etor & Destructor Documentation	47
		8.7.2.1	OrbElemDerivedState() [1/2]	47
		8.7.2.2	~OrbElemDerivedState()	47
		8.7.2.3	OrbElemDerivedState() [2/2]	47
	8.7.3	Member	Function Documentation	47
		8.7.3.1	compute_orbital_elements()	47
		8.7.3.2	initialize()	48
		8.7.3.3	operator=()	48
		8.7.3.4	set_use_alt_inertial()	48
		8.7.3.5	update()	49
	8.7.4	Friends A	And Related Function Documentation	49
		8.7.4.1	init_attrjeodOrbElemDerivedState	49
		8.7.4.2	InputProcessor	49
	8.7.5	Field Doo	cumentation	49
		8.7.5.1	elements	49
		8.7.5.2	inertial_ptr	50
		8.7.5.3	planet	50
		8.7.5.4	rel_state	50
		8.7.5.5	use_alt_inertial	50
8.8	jeod::Pl	lanetaryD	erivedState Class Reference	51
	8.8.1	Detailed	Description	52
	8.8.2	Construc	etor & Destructor Documentation	52
		8.8.2.1	PlanetaryDerivedState() [1/2]	52
		8.8.2.2	~PlanetaryDerivedState()	52
		8.8.2.3	PlanetaryDerivedState() [2/2]	52
	8.8.3	Member	Function Documentation	52
		8.8.3.1	initialize()	52
		8.8.3.2	operator=()	53
		8.8.3.3	set_use_alt_pfix()	53

CONTENTS vii

		8.8.3.4	update()	53
	8.8.4	Friends A	And Related Function Documentation	53
		8.8.4.1	init_attrjeodPlanetaryDerivedState	54
		8.8.4.2	InputProcessor	54
	8.8.5	Field Doo	cumentation	54
		8.8.5.1	pfix_ptr	54
		8.8.5.2	planet	54
		8.8.5.3	state	54
		8.8.5.4	use_alt_pfix	55
8.9	jeod::F	RelativeDer	rivedState Class Reference	55
	8.9.1	Detailed	Description	57
	8.9.2	Member	Enumeration Documentation	57
		8.9.2.1	DirectionSense	57
	8.9.3	Construc	tor & Destructor Documentation	57
		8.9.3.1	RelativeDerivedState() [1/2]	57
		8.9.3.2	~RelativeDerivedState()	57
		8.9.3.3	RelativeDerivedState() [2/2]	58
	8.9.4	Member	Function Documentation	58
		8.9.4.1	initialize() [1/2]	58
		8.9.4.2	initialize() [2/2]	58
		8.9.4.3	operator=()	59
		8.9.4.4	set_activation_flag()	59
		8.9.4.5	set_name()	59
		8.9.4.6	set_subject_frame()	59
		8.9.4.7	set_target_frame()	60
		8.9.4.8	update()	60
	8.9.5	Friends A	And Related Function Documentation	60
		8.9.5.1	init_attrjeodRelativeDerivedState	60
		8.9.5.2	InputProcessor	60
	8.9.6	Field Doo	cumentation	61

viii CONTENTS

	8.9.6.1	active	. 61
	8.9.6.2	direction_sense	. 61
	8.9.6.3	name	. 61
	8.9.6.4	rel_state	. 62
	8.9.6.5	subject_frame	. 62
	8.9.6.6	subject_frame_name	. 62
	8.9.6.7	target_frame	. 63
	8.9.6.8	target_frame_name	. 63
8.10 jeod::S	SolarBetaD	DerivedState Class Reference	. 63
8.10.1	Detailed	Description	. 64
8.10.2	Construc	ctor & Destructor Documentation	. 65
	8.10.2.1	SolarBetaDerivedState() [1/2]	. 65
	8.10.2.2	~SolarBetaDerivedState()	. 65
	8.10.2.3	SolarBetaDerivedState() [2/2]	. 65
8.10.3	Member	Function Documentation	. 65
	8.10.3.1	initialize()	. 65
	8.10.3.2	operator=()	. 66
	8.10.3.3	update()	. 66
8.10.4	Friends A	And Related Function Documentation	. 66
	8.10.4.1	init_attrjeodSolarBetaDerivedState	. 66
	8.10.4.2	InputProcessor	. 66
8.10.5	Field Doo	cumentation	. 66
	8.10.5.1	active	. 67
	8.10.5.2	planet	. 67
	8.10.5.3	solar_beta	. 67
	8.10.5.4	sun	. 68
	8.10.5.5	sun_wrt_planet	. 68
	8.10.5.6	veh_wrt_planet	. 68

CONTENTS

9	File I	Documentation	69
	9.1	class_declarations.hh File Reference	69
		9.1.1 Detailed Description	69
	9.2	derived_state.cc File Reference	69
		9.2.1 Detailed Description	70
	9.3	derived_state.hh File Reference	70
		9.3.1 Detailed Description	70
	9.4	derived_state_messages.cc File Reference	70
		9.4.1 Detailed Description	71
		9.4.2 Macro Definition Documentation	71
		9.4.2.1 MAKE_DERIVEDSTATE_MESSAGE_CODE	71
	9.5	derived_state_messages.hh File Reference	71
		9.5.1 Detailed Description	71
	9.6	euler_derived_state.cc File Reference	72
		9.6.1 Detailed Description	72
	9.7	euler_derived_state.hh File Reference	72
		9.7.1 Detailed Description	72
	9.8	lvlh_derived_state.cc File Reference	73
		9.8.1 Detailed Description	73
	9.9	lvlh_derived_state.hh File Reference	73
		9.9.1 Detailed Description	73
	9.10	lvlh_relative_derived_state.cc File Reference	74
		9.10.1 Detailed Description	74
	9.11	lvlh_relative_derived_state.hh File Reference	74
		9.11.1 Detailed Description	75
	9.12	ned_derived_state.cc File Reference	75
		9.12.1 Detailed Description	75
	9.13	ned_derived_state.hh File Reference	75
		9.13.1 Detailed Description	76
	9.14	orb_elem_derived_state.cc File Reference	76

CONTENTS

	9.14.1 Detailed Description	76
9.15	orb_elem_derived_state.hh File Reference	76
	9.15.1 Detailed Description	77
9.16	planetary_derived_state.cc File Reference	77
	9.16.1 Detailed Description	77
9.17	planetary_derived_state.hh File Reference	77
	9.17.1 Detailed Description	78
9.18	relative_derived_state.cc File Reference	78
	9.18.1 Detailed Description	78
9.19	relative_derived_state.hh File Reference	78
	9.19.1 Detailed Description	79
9.20	solar_beta_derived_state.cc File Reference	79
	9.20.1 Detailed Description	79
9.21	solar_beta_derived_state.hh File Reference	80
	9.21.1 Detailed Description	80
Index		81

Module Index

1.1 Modules

Here is a list of all modules:

Models	 11
Dynamics	 . 12
DerivedState	13

2 Module Index

Namespace Index

2.1	Namespace	List

Hei	ere is a list of all flattlespaces with brief descriptions.		
	jeod		

4 Namespace Index

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

jeod::DerivedState	17
jeod::EulerDerivedState	26
jeod::LvlhDerivedState	31
jeod::NedDerivedState	1 0
jeod::OrbElemDerivedState	1 5
jeod::PlanetaryDerivedState	51
jeod::RelativeDerivedState	55
jeod::LvlhRelativeDerivedState	35
jeod::SolarBetaDerivedState	33
ieod::DerivedStateMessages	22

6 Hierarchical Index

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::DerivedState	
The base class used for deriving a state representation of some subject DynBody	17
jeod::DerivedStateMessages	
The class that specifies the message IDs used in the DerivedState model	22
jeod::EulerDerivedState	
The class used for deriving the Euler angle representation of a subject DynBody's attitude	26
jeod::LvlhDerivedState	
The class used for deriving the rectilinear LVLH representations of a subject DynBody's state .	31
jeod::LvlhRelativeDerivedState	
The class used for calculating the LVLH state of a subject DynBody relative to some LVLH	
reference frame	35
jeod::NedDerivedState	
The class used for deriving the North-East-Down representations of a subject DynBody's state	40
jeod::OrbElemDerivedState	
The class used for deriving the orbital elements representation of a subject DynBody's position	45
jeod::PlanetaryDerivedState	
The class used for deriving the planet-fixed representations of a subject DynBody's position	51
jeod::RelativeDerivedState	
The class used for deriving the state of some frame associated with the subject DynBody relative	
to some other target frame	55
jeod::SolarBetaDerivedState	
The class for calculating the solar beta of a vehicle	63

8 Data Structure Index

File Index

5.1 File List

Here is a list of all files with brief descriptions:

class_declarations.hh	
Forward declarations of classes defined in XXX_derived_state.hh files	69
derived_state.cc	
Define methods for the base body initialization class	69
derived_state.hh	
Define the class DerivedState, the base class used for deriving a state representation of some	
subject DynBody	70
derived_state_messages.cc	
Implement the class DerivedStateMessages	70
derived_state_messages.hh	
Define the class DerivedStateMessages, the class that specifies the message IDs used in the	
DerivedState model	71
euler_derived_state.cc	
Define methods for the Euler attitude derived state class	72
euler_derived_state.hh	
Define the class EulerDerivedState, the class used for deriving the Euler angle representation of	
a subject DynBody's attitude	72
lvlh_derived_state.cc	
Define methods for the base body initialization class	73
lvlh_derived_state.hh	
Define the class LvlhDerivedState, the class used for deriving the rectilinear LVLH representa-	
tions of a subject DynBody's state	73
lvlh_relative_derived_state.cc	
Define methods for the LVLH relative state class	74
lvlh_relative_derived_state.hh	
Define the class LvlhRelativeDerivedState, the class used for calculating the LVLH state of a	
subject DynBody relative to some LVLH reference frame	74
ned_derived_state.cc	
Define methods for NedDerivedState	75
ned_derived_state.hh	
Define the class NedDerivedState, the class used for deriving the NED representations of a	
subject DynBody's state	75
orb_elem_derived_state.cc	
Define methods for the orbital elements derived state class	76

10 File Index

orb_elem_derived_state.hh	
Define the class OrbElemDerivedState, the class used for deriving the orbital elements repre-	
sentation of a subject DynBody's position	76
planetary_derived_state.cc	
Define methods for the base body initialization class	77
planetary_derived_state.hh	
Define the class PlanetaryDerivedState, the class used for deriving the planet-fixed representa-	
tions of a subject DynBody's position	77
relative_derived_state.cc	
Define methods for the base body initialization class	78
relative_derived_state.hh	
Define the class RelativeDerivedState, the class used for deriving the state of some frame asso-	
ciated with the subject DynBody relative to some other target frame	78
solar_beta_derived_state.cc	
This function calculates the angle between a spacecraft's orbital plane and the vector from the	
	79
solar_beta_derived_state.hh	
A class for calculating the solar beta of a vehicle	80

Module Documentation

6.1 Models

Modules

- Dynamics
- 6.1.1 Detailed Description

12 Module Documentation

6.2 Dynamics

Modules

DerivedState

6.2.1 Detailed Description

6.3 DerivedState 13

6.3 DerivedState

Files

· file class declarations.hh

Forward declarations of classes defined in XXX_derived_state.hh files.

· file derived state.hh

Define the class DerivedState, the base class used for deriving a state representation of some subject DynBody.

file derived_state_messages.hh

Define the class DerivedStateMessages, the class that specifies the message IDs used in the DerivedState model.

· file euler derived state.hh

Define the class EulerDerivedState, the class used for deriving the Euler angle representation of a subject DynBody's attitude

· file lvlh_derived_state.hh

Define the class LvlhDerivedState, the class used for deriving the rectilinear LVLH representations of a subject Dyn← Body's state.

· file lvlh relative derived state.hh

Define the class LvlhRelativeDerivedState, the class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

· file ned derived state.hh

Define the class NedDerivedState, the class used for deriving the NED representations of a subject DynBody's state.

· file orb elem derived state.hh

Define the class OrbElemDerivedState, the class used for deriving the orbital elements representation of a subject DynBody's position.

file planetary_derived_state.hh

Define the class PlanetaryDerivedState, the class used for deriving the planet-fixed representations of a subject DynBody's position.

• file relative_derived_state.hh

Define the class RelativeDerivedState, the class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame.

· file solar beta derived state.hh

A class for calculating the solar beta of a vehicle.

· file derived state.cc

Define methods for the base body initialization class.

file derived_state_messages.cc

Implement the class DerivedStateMessages.

• file euler_derived_state.cc

Define methods for the Euler attitude derived state class.

• file lvlh_derived_state.cc

Define methods for the base body initialization class.

• file lvlh_relative_derived_state.cc

Define methods for the LVLH relative state class.

file ned_derived_state.cc

Define methods for NedDerivedState.

• file orb_elem_derived_state.cc

Define methods for the orbital elements derived state class.

• file planetary_derived_state.cc

Define methods for the base body initialization class.

• file relative_derived_state.cc

Define methods for the base body initialization class.

file solar_beta_derived_state.cc

This function calculates the angle between a spacecraft's orbital plane and the vector from the relevant planet to the sun.

14 Module Documentation

Namespaces

• jeod

Namespace jeod.

6.3.1 Detailed Description

Namespace Documentation

7.1 jeod Namespace Reference

Namespace jeod.

Data Structures

· class DerivedState

The base class used for deriving a state representation of some subject DynBody.

class DerivedStateMessages

The class that specifies the message IDs used in the DerivedState model.

• class EulerDerivedState

The class used for deriving the Euler angle representation of a subject DynBody's attitude.

· class LvlhDerivedState

The class used for deriving the rectilinear LVLH representations of a subject DynBody's state.

· class LvlhRelativeDerivedState

The class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

• class NedDerivedState

The class used for deriving the North-East-Down representations of a subject DynBody's state.

· class OrbElemDerivedState

The class used for deriving the orbital elements representation of a subject DynBody's position.

class PlanetaryDerivedState

The class used for deriving the planet-fixed representations of a subject DynBody's position.

· class RelativeDerivedState

The class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame

· class SolarBetaDerivedState

The class for calculating the solar beta of a vehicle.

Variables

• static constexpr double epsilon = 0.0000001

7.1.1 Detailed Description

Namespace jeod.

7.1.2 Variable Documentation

7.1.2.1 epsilon

```
constexpr double jeod::epsilon = 0.0000001 [static]
```

Definition at line 53 of file solar_beta_derived_state.cc.

Referenced by jeod::SolarBetaDerivedState::update().

Data Structure Documentation

8.1 jeod::DerivedState Class Reference

The base class used for deriving a state representation of some subject DynBody.

```
#include <derived_state.hh>
```

Inheritance diagram for jeod::DerivedState:



Public Member Functions

- DerivedState ()=default
- virtual ∼DerivedState ()=default
- DerivedState (const DerivedState &)=delete
- DerivedState & operator= (const DerivedState &)=delete
- void set_reference_name (const std::string &new_name)

Set the reference_name to a copy of the supplied value.

• virtual void initialize (DynBody &subject_body, DynManager &dyn_manager)

Begin initialization of a DerivedState.

• virtual void update ()

Update the state.

Data Fields

DynBody * subject {}

The body that is the subject of the derived state.

• std::string reference_name

The name of the object with respect to which the subject state is assessed.

Protected Member Functions

Planet * find_planet (const DynManager &dyn_manager, const std::string &planet_name, const std::string &variable_name)

Find the Planet with the given name, failing if not found.

Protected Attributes

· std::string state identifier

An identifier for this derived state, constructed at initialization time from the class name, the subject body name, and the reference name.

Friends

- · class InputProcessor
- void init_attrjeod__DerivedState ()

8.1.1 Detailed Description

The base class used for deriving a state representation of some subject DynBody.

Definition at line 85 of file derived_state.hh.

8.1.2 Constructor & Destructor Documentation

```
8.1.2.1 DerivedState() [1/2]

jeod::DerivedState::DerivedState ( ) [default]

8.1.2.2 ~DerivedState()

virtual jeod::DerivedState::~DerivedState ( ) [virtual], [default]

8.1.2.3 DerivedState() [2/2]

jeod::DerivedState::DerivedState ( const DerivedState & ) [delete]
```

8.1.3 Member Function Documentation

8.1.3.1 find_planet()

Find the Planet with the given name, failing if not found.

Returns

Found Planet

Parameters

in	dyn_manager	Dynamics manager
in	planet_name	Planet name
in	variable_name	For error reporting

Definition at line 104 of file derived_state.cc.

References jeod::DerivedStateMessages::invalid_name, and state_identifier.

Referenced by jeod::PlanetaryDerivedState::initialize(), jeod::OrbElemDerivedState::initialize(), jeod::NedDerived State::initialize(), and jeod::SolarBetaDerivedState::initialize().

8.1.3.2 initialize()

Begin initialization of a DerivedState.

The initialize method for all subclasses of DerivedState *nust* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Assumptions and Limitations

• g++ is being used as the compiler

Parameters

in,out	subject_body	Subject body	
in,out	dyn_manager	ager Dynamics manager	

Reimplemented in jeod::RelativeDerivedState, jeod::SolarBetaDerivedState, jeod::NedDerivedState, jeod::OrbElemDerivedState, jeod::EulerDerivedState, jeod::LvlhDerivedState, jeod::LvlhRelativeDerivedState.

Definition at line 71 of file derived_state.cc.

References reference_name, state_identifier, and subject.

Referenced by jeod::LvlhDerivedState::initialize(), jeod::PlanetaryDerivedState::initialize(), jeod::EulerDerived \hookrightarrow State::initialize(), jeod::OrbElemDerivedState::initialize(), jeod::NedDerivedState::initialize(), jeod::SolarBeta \hookleftarrow DerivedState::initialize(), and jeod::RelativeDerivedState::initialize().

8.1.3.3 operator=()

8.1.3.4 set_reference_name()

Set the reference_name to a copy of the supplied value.

Parameters

_			
	in	new_name	new name of reference.

Definition at line 55 of file derived_state.cc.

References reference name.

8.1.3.5 update()

```
void jeod::DerivedState::update ( ) [virtual]
```

Update the state.

Reimplemented in jeod::RelativeDerivedState, jeod::SolarBetaDerivedState, jeod::NedDerivedState, jeod::OrbElemDerivedState, jeod::EulerDerivedState, jeod::LvlhDerivedState, j

Definition at line 87 of file derived_state.cc.

Referenced by jeod::EulerDerivedState::update(), and jeod::OrbElemDerivedState::update().

8.1.4 Friends And Related Function Documentation

8.1.4.1 init_attrjeod__DerivedState

```
void init_attrjeod__DerivedState ( ) [friend]
```

8.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 87 of file derived state.hh.

8.1.5 Field Documentation

8.1.5.1 reference_name

```
std::string jeod::DerivedState::reference_name
```

The name of the object with respect to which the subject state is assessed.

trick_units(-)

Definition at line 99 of file derived_state.hh.

Referenced by initialize(), jeod::LvlhDerivedState::initialize(), jeod::PlanetaryDerivedState::initialize(), jeod:: \leftarrow OrbElemDerivedState::initialize(), jeod::NedDerivedState::initialize(), jeod::SolarBetaDerivedState::initialize(), and set_reference_name().

8.1.5.2 state_identifier

```
std::string jeod::DerivedState::state_identifier [protected]
```

An identifier for this derived state, constructed at initialization time from the class name, the subject body name, and the reference name.

This is used for generating error and debug messages.trick_units(-)

Definition at line 107 of file derived_state.hh.

Referenced by find_planet(), initialize(), and jeod::RelativeDerivedState::initialize().

8.1.5.3 subject

```
DynBody* jeod::DerivedState::subject {}
```

The body that is the subject of the derived state.

trick_units(-)

Definition at line 93 of file derived_state.hh.

Referenced by initialize(), jeod::LvlhDerivedState::initialize(), jeod::RelativeDerivedState::initialize(), jeod::← PlanetaryDerivedState::update(), jeod::EulerDerivedState::update(), jeod::OrbElemDerivedState::update(), jeod::NedDerivedState::update(), and jeod::SolarBetaDerivedState::update().

The documentation for this class was generated from the following files:

- · derived_state.hh
- · derived state.cc

8.2 jeod::DerivedStateMessages Class Reference

The class that specifies the message IDs used in the DerivedState model.

```
#include <derived_state_messages.hh>
```

Public Member Functions

- DerivedStateMessages ()=delete
- DerivedStateMessages (const DerivedStateMessages &)=delete
- DerivedStateMessages & operator= (const DerivedStateMessages &)=delete

Static Public Attributes

- static const char * fatal_error = "dynamics/derived_state/" "fatal_error"
 - Issued when performing an action results in an error return from the method performing the action.
- static const char * illegal_value = "dynamics/derived_state/" "illegal_value"
 Issued when a simple type (e.g.
- static const char * invalid name = "dynamics/derived state/" "invalid name"
 - Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).
- static const char * invalid object = "dynamics/derived state/" "invalid object"
 - Issued when a pointer points to an object of the wrong type.
- static const char * null_pointer = "dynamics/derived_state/" "null_pointer"
 - Error issued when a pointer is required but was not provided.
- static const char * trace = "dynamics/derived state/" "trace"
 - Debug message issued to trace DerivedState actions.
- static const char * divide_by_zero = "dynamics/derived_state/" "divide_by_zero"

Fatal message when a divide by zero is encountered.

Friends

- · class InputProcessor
- void init_attrjeod__DerivedStateMessages ()

8.2.1 Detailed Description

The class that specifies the message IDs used in the DerivedState model.

Definition at line 81 of file derived_state_messages.hh.

8.2.2 Constructor & Destructor Documentation

```
8.2.2.1 DerivedStateMessages() [1/2]
```

```
jeod::DerivedStateMessages::DerivedStateMessages ( ) [delete]
```

8.2.2.2 DerivedStateMessages() [2/2]

8.2.3 Member Function Documentation

8.2.3.1 operator=()

8.2.4 Friends And Related Function Documentation

8.2.4.1 init_attrjeod__DerivedStateMessages

```
void init_attrjeod__DerivedStateMessages ( ) [friend]
```

8.2.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 83 of file derived_state_messages.hh.

8.2.5 Field Documentation

8.2.5.1 divide_by_zero

```
 char const * jeod::DerivedStateMessages::divide_by_zero = "dynamics/derived_state/" "divide\_\leftrightarrow by_zero" [static]
```

Fatal message when a divide by zero is encountered.

trick_units(-)

Definition at line 121 of file derived state messages.hh.

Referenced by jeod::SolarBetaDerivedState::update().

8.2.5.2 fatal_error

```
char const * jeod::DerivedStateMessages::fatal_error = "dynamics/derived_state/" "fatal_error"
[static]
```

Issued when performing an action results in an error return from the method performing the action.

trick_units(-)

Definition at line 90 of file derived_state_messages.hh.

8.2.5.3 illegal_value

```
\label{lem:char_const} $$ \text{ jeod::DerivedStateMessages::illegal\_value = "dynamics/derived\_state/" "illegal\_$$ $$ \text{value" [static]} $$
```

Issued when a simple type (e.g.

an enum) has an illegal value.trick_units(-)

Definition at line 95 of file derived_state_messages.hh.

Referenced by jeod::LvlhRelativeDerivedState::convert_circ_to_rect(), jeod::LvlhRelativeDerivedState::convert_circ_to_rect(), jeod::LvlhRelativeDerivedState::update(), and jeod::RelativeDerivedState::update().

8.2.5.4 invalid_name

```
char const * jeod::DerivedStateMessages::invalid_name = "dynamics/derived_state/" "invalid_←
name" [static]
```

Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).

trick_units(-)

Definition at line 101 of file derived_state_messages.hh.

Referenced by jeod::DerivedState::find_planet(), and jeod::RelativeDerivedState::initialize().

8.2.5.5 invalid_object

```
\label{lem:const} char const * jeod::DerivedStateMessages::invalid\_object = "dynamics/derived\_state/" "invalid\_$\ef{lem:const}$ object" [static]
```

Issued when a pointer points to an object of the wrong type.

trick_units(-)

Definition at line 106 of file derived_state_messages.hh.

8.2.5.6 null_pointer

```
char const * jeod::DerivedStateMessages::null_pointer = "dynamics/derived_state/" "null_\leftrightarrow pointer" [static]
```

Error issued when a pointer is required but was not provided.

trick units(-)

Definition at line 111 of file derived state messages.hh.

8.2.5.7 trace

```
char const * jeod::DerivedStateMessages::trace = "dynamics/derived_state/" "trace" [static]
```

Debug message issued to trace DerivedState actions.

trick_units(-)

Definition at line 116 of file derived_state_messages.hh.

The documentation for this class was generated from the following files:


- · derived_state_messages.hh
- derived_state_messages.cc

8.3 jeod::EulerDerivedState Class Reference

The class used for deriving the Euler angle representation of a subject DynBody's attitude.

```
#include <euler_derived_state.hh>
```

Inheritance diagram for jeod::EulerDerivedState:



Public Member Functions

- EulerDerivedState ()=default
- ∼EulerDerivedState () override

Destruct a EulerDerivedState object.

- EulerDerivedState (const EulerDerivedState &)=delete
- EulerDerivedState & operator= (const EulerDerivedState &)=delete
- void initialize (DynBody &subject_body, DynManager &dyn_manager) override

Begin initialization of a EulerDerivedState.

- virtual void initialize (RefFrame &ref_frame, DynBody &subject_body, DynManager &dyn_manager)
 Begin initialization of a EulerDerivedState.
- void update () override

Compute the Euler angles.

Data Fields

• Orientation::EulerSequence sequence {Orientation::Roll Pitch Yaw}

Euler angle sequence specification.

double ref_body_angles [3] {}

Euler angles from reference frame.

• double body_ref_angles [3] {}

Euler angles to reference frame.

• RefFrameState rel_state

The relative state of the body.

Protected Attributes

RefFrame * rel_frame {}

Reference frame from which to compute the Euler angle attitude.

Friends

- class InputProcessor
- void init_attrjeod__EulerDerivedState ()

Additional Inherited Members

8.3.1 Detailed Description

The class used for deriving the Euler angle representation of a subject DynBody's attitude.

Definition at line 88 of file euler_derived_state.hh.

8.3.2 Constructor & Destructor Documentation

```
8.3.2.1 EulerDerivedState() [1/2]

jeod::EulerDerivedState::EulerDerivedState ( ) [default]
```

8.3.2.2 \sim EulerDerivedState()

```
{\tt jeod::EulerDerivedState::} {\sim} {\tt EulerDerivedState} \text{ ( ) } \text{ [override]}
```

Destruct a EulerDerivedState object.

Definition at line 46 of file euler_derived_state.cc.

References rel frame.

8.3.2.3 EulerDerivedState() [2/2]

8.3.3 Member Function Documentation

Begin initialization of a EulerDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body.
in,out	dyn_manager	Dynamics manager.

Reimplemented from jeod::DerivedState.

Definition at line 63 of file euler_derived_state.cc.

References jeod::DerivedState::initialize().

```
8.3.3.2 initialize() [2/2]
```

Begin initialization of a EulerDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in	ref_frame	Reference frame for angles.
in,out	subject_body	Subject body.
in,out	dyn_manager	Dynamics manager.

Definition at line 78 of file euler_derived_state.cc.

References jeod::DerivedState::initialize(), and rel_frame.

8.3.3.3 operator=()

8.3.3.4 update()

```
void jeod::EulerDerivedState::update ( ) [override], [virtual]
```

Compute the Euler angles.

Assumptions and Limitations

• Depends upon the Trick Euler angle math macros and routines.

Reimplemented from jeod::DerivedState.

Definition at line 96 of file euler_derived_state.cc.

References body_ref_angles, ref_body_angles, rel_frame, rel_state, sequence, jeod::DerivedState::subject, and jeod::DerivedState::update().

8.3.4 Friends And Related Function Documentation

8.3.4.1 init_attrjeod__EulerDerivedState

```
void init_attrjeod__EulerDerivedState ( ) [friend]
```

8.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 90 of file euler_derived_state.hh.

8.3.5 Field Documentation

8.3.5.1 body_ref_angles

```
double jeod::EulerDerivedState::body_ref_angles[3] {}
```

Euler angles to reference frame.

trick_units(rad)

Definition at line 106 of file euler_derived_state.hh.

Referenced by update().

8.3.5.2 ref_body_angles

```
double jeod::EulerDerivedState::ref_body_angles[3] {}
```

Euler angles from reference frame.

trick_units(rad)

Definition at line 101 of file euler_derived_state.hh.

Referenced by update().

8.3.5.3 rel_frame

```
RefFrame* jeod::EulerDerivedState::rel_frame {} [protected]
```

Reference frame from which to compute the Euler angle attitude.

If this is NULL then the body's parent frame is used.trick_units(-)

Definition at line 120 of file euler_derived_state.hh.

Referenced by initialize(), update(), and ~EulerDerivedState().

8.3.5.4 rel_state

```
RefFrameState jeod::EulerDerivedState::rel_state
```

The relative state of the body.

This is just a copy of the body's state when the relative frame is the parent frame. This is a computed relative state when the relative frame is not the parent frame.trick_units(-)

Definition at line 113 of file euler_derived_state.hh.

Referenced by update().

8.3.5.5 sequence

```
Orientation::EulerSequence jeod::EulerDerivedState::sequence {Orientation::Roll_Pitch_Yaw}
```

Euler angle sequence specification.

trick units(-)

Definition at line 96 of file euler_derived_state.hh.

Referenced by update().

The documentation for this class was generated from the following files:


- euler_derived_state.hh
- euler_derived_state.cc

8.4 jeod::LvlhDerivedState Class Reference

The class used for deriving the rectilinear LVLH representations of a subject DynBody's state.

```
#include <lvlh_derived_state.hh>
```

Inheritance diagram for jeod::LvIhDerivedState:



Public Member Functions

- LvlhDerivedState ()=default
- ~LvlhDerivedState () override

Destruct a LvlhDerivedState object.

- LvlhDerivedState (const LvlhDerivedState &)=delete
- LvlhDerivedState & operator= (const LvlhDerivedState &)=delete
- void initialize (DynBody &subject_body, DynManager &dyn_manager) override

Begin initialization of a LvlhDerivedState.

• void update () override

Update the state.

Data Fields

• bool register_frame {true}

If set (default), the LVLH frame will be registered with the dynamics manager at initialization time.

· RefFrame lvlh_frame

The LVLH frame of the subject body with respect to the planet specified by the reference name.

· LvlhFrame lvlh state

The LvlhFrame object responsible for maintaining the lvlh_frame.

Protected Attributes

RefFrame * planet_centered_inertial {}

The inertial frame with origin at the center of the specified planet.

DynManager * local_dm {}

Friends

- · class InputProcessor
- void init_attrjeod__LvlhDerivedState ()

Additional Inherited Members

8.4.1 Detailed Description

The class used for deriving the rectilinear LVLH representations of a subject DynBody's state.

Definition at line 84 of file lvlh_derived_state.hh.

8.4.2 Constructor & Destructor Documentation

```
8.4.2.1 LvlhDerivedState() [1/2]

jeod::LvlhDerivedState::LvlhDerivedState ( ) [default]

8.4.2.2 ~LvlhDerivedState()

jeod::LvlhDerivedState::~LvlhDerivedState ( ) [override]
```

Destruct a LvlhDerivedState object.

Definition at line 50 of file lvlh_derived_state.cc.

References local_dm, and lvlh_frame.

```
8.4.2.3 LvlhDerivedState() [2/2]
```

8.4.3 Member Function Documentation

8.4.3.1 initialize()

Begin initialization of a LvlhDerivedState.

The initialize method for all subclasses of DerivedState *nust* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

Reimplemented from jeod::DerivedState.

Definition at line 70 of file lvlh_derived_state.cc.

References jeod::DerivedState::initialize(), local_dm, lvlh_frame, lvlh_state, planet_centered_inertial, jeod::

DerivedState::reference_name, register_frame, and jeod::DerivedState::subject.

8.4.3.2 operator=()

8.4.3.3 update()

```
void jeod::LvlhDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 93 of file lvlh_derived_state.cc.

References IvIh_frame, and IvIh_state.

8.4.4 Friends And Related Function Documentation

8.4.4.1 init_attrjeod_ LvlhDerivedState

```
void init_attrjeod__LvlhDerivedState ( ) [friend]
```

8.4.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file lvlh_derived_state.hh.

8.4.5 Field Documentation

8.4.5.1 | local_dm DynManager* jeod::LvlhDerivedState::local_dm {} [protected] Definition at line 113 of file lvlh_derived_state.hh. Referenced by initialize(), and ~LvlhDerivedState(). 8.4.5.2 lvlh_frame RefFrame jeod::LvlhDerivedState::lvlh_frame The LVLH frame of the subject body with respect to the planet specified by the reference name. trick_units(-) Definition at line 100 of file lvlh_derived_state.hh. Referenced by initialize(), update(), and ~LvlhDerivedState(). 8.4.5.3 lvlh_state LvlhFrame jeod::LvlhDerivedState::lvlh_state The LvIhFrame object responsible for maintaining the lvIh_frame. trick_units(-) Definition at line 105 of file lvlh_derived_state.hh. Referenced by initialize(), and update(). 8.4.5.4 planet_centered_inertial RefFrame* jeod::LvlhDerivedState::planet_centered_inertial {} [protected]

The inertial frame with origin at the center of the specified planet.

Definition at line 111 of file lvlh_derived_state.hh.

trick_units(-)

Referenced by initialize().

8.4.5.5 register_frame

```
bool jeod::LvlhDerivedState::register_frame {true}
```

If set (default), the LVLH frame will be registered with the dynamics manager at initialization time.

This will make the frame accessible through the dynamic manager via its find_ref_frame method.trick_units(-)

Definition at line 94 of file lvlh_derived_state.hh.

Referenced by initialize().

The documentation for this class was generated from the following files:


- · IvIh derived state.hh
- · lvlh_derived_state.cc

8.5 jeod::LvlhRelativeDerivedState Class Reference

The class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

```
#include <lvlh_relative_derived_state.hh>
```

Inheritance diagram for jeod::LvlhRelativeDerivedState:



Public Member Functions

LvlhRelativeDerivedState ()

Default Constructor.

- ~LvlhRelativeDerivedState () override=default
- LvlhRelativeDerivedState (const LvlhRelativeDerivedState &)=delete
- LvlhRelativeDerivedState & operator= (const LvlhRelativeDerivedState &)=delete
- void initialize (DynBody &subject_body, DynManager &dyn_manager) override

Begin initialization of an LvlhRelativeDerivedState.

• void update () override

Update the state.

• void convert_rect_to_circ (const RefFrameState &rect_rel_state)

Convert from rectilinear LVLH coordinates to circular curvilinear.

void convert_circ_to_rect (const RefFrameState &circ_rel_state)

Convert from circular curvilinear LVLH coordinates to rectilinear.

Data Fields

- LvlhType::Type lvlh_type {LvlhType::Rectilinear}
 Indicates type of LVLH coordinates desired.
- bool use_theta_dot_correction {}

Indicates whether or not to correct for changing phase angle in curvilinear coordinates.

Private Member Functions

• void do_theta_dot_correction (double omega[3], const RefFrameState &state, const double r, bool c2r)

Compute thetadot correction to omega.

Friends

- class InputProcessor
- void init_attrjeod__LvlhRelativeDerivedState ()

Additional Inherited Members

8.5.1 Detailed Description

The class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

Definition at line 87 of file lvlh_relative_derived_state.hh.

8.5.2 Constructor & Destructor Documentation

8.5.2.1 LvIhRelativeDerivedState() [1/2]

```
jeod::LvlhRelativeDerivedState::LvlhRelativeDerivedState ( )
```

Default Constructor.

Definition at line 53 of file lvlh_relative_derived_state.cc.

References jeod::RelativeDerivedState::ComputeSubjectStateinTarget, and jeod::RelativeDerivedState::direction ← __sense.

8.5.2.2 ∼LvlhRelativeDerivedState()

```
jeod::LvlhRelativeDerivedState::~LvlhRelativeDerivedState ( ) [override], [default]
```

8.5.2.3 LvlhRelativeDerivedState() [2/2]

8.5.3 Member Function Documentation

8.5.3.1 convert_circ_to_rect()

Convert from circular curvilinear LVLH coordinates to rectilinear.

Parameters

in curvi_rel_state Source state	e
---------------------------------	---

Definition at line 190 of file lvlh_relative_derived_state.cc.

References do_theta_dot_correction(), jeod::DerivedStateMessages::illegal_value, jeod::RelativeDerivedState :::name, jeod::RelativeDerivedState::rel_state, and jeod::RelativeDerivedState::target_frame.

8.5.3.2 convert_rect_to_circ()

Convert from rectilinear LVLH coordinates to circular curvilinear.

Parameters

in	rect_rel_state	Source state

Definition at line 115 of file lvlh_relative_derived_state.cc.

References do_theta_dot_correction(), jeod::DerivedStateMessages::illegal_value, jeod::RelativeDerivedState :::name, jeod::RelativeDerivedState::rel_state, and jeod::RelativeDerivedState::target_frame.

Referenced by update().

8.5.3.3 do_theta_dot_correction()

```
void jeod::LvlhRelativeDerivedState::do_theta_dot_correction ( double omega[3], const RefFrameState & state, const double r, bool c2r) [private]
```

Compute thetadot correction to omega.

Definition at line 266 of file lvlh_relative_derived_state.cc.

References jeod::RelativeDerivedState::target_frame, and use_theta_dot_correction.

Referenced by convert_circ_to_rect(), and convert_rect_to_circ().

8.5.3.4 initialize()

Begin initialization of an LvlhRelativeDerivedState.

The initialize method for all subclasses of DerivedState must pass the initialize call to their immediate parent class.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

 $\label{lem:lemented_red} Reimplemented from \ jeod:: Derived State.$

Definition at line 66 of file lvlh_relative_derived_state.cc.

References jeod::RelativeDerivedState::initialize().

8.5.3.5 operator=()

8.5.3.6 update()

```
void jeod::LvlhRelativeDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 75 of file lvlh_relative_derived_state.cc.

References convert_rect_to_circ(), jeod::DerivedStateMessages::illegal_value, lvlh_type, jeod::RelativeDerived \hookrightarrow State::rel_state, jeod::RelativeDerivedState::subject_frame, and jeod::RelativeDerivedState::target_frame.

8.5.4 Friends And Related Function Documentation

8.5.4.1 init_attrjeod__LvlhRelativeDerivedState

```
void init_attrjeod__LvlhRelativeDerivedState ( ) [friend]
```

8.5.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file lvlh_relative_derived_state.hh.

8.5.5 Field Documentation

8.5.5.1 lvlh_type

```
LvlhType::Type jeod::LvlhRelativeDerivedState::lvlh_type {LvlhType::Rectilinear}
```

Indicates type of LVLH coordinates desired.

Default is rectilinear.trick_units(-)

Definition at line 95 of file lvlh_relative_derived_state.hh.

Referenced by update().

8.5.5.2 use_theta_dot_correction

```
bool jeod::LvlhRelativeDerivedState::use_theta_dot_correction {}
```

Indicates whether or not to correct for changing phase angle in curvilinear coordinates.

Default is false.trick_units(-)

Definition at line 101 of file lvlh_relative_derived_state.hh.

Referenced by do_theta_dot_correction().

The documentation for this class was generated from the following files:


- · IvIh relative derived state.hh
- lvlh_relative_derived_state.cc

8.6 jeod::NedDerivedState Class Reference

The class used for deriving the North-East-Down representations of a subject DynBody's state.

```
#include <ned_derived_state.hh>
```

Inheritance diagram for jeod::NedDerivedState:



Public Member Functions

- NedDerivedState ()=default
- ∼NedDerivedState () override

NedDerivedState destructor.

- NedDerivedState (const NedDerivedState &)=delete
- NedDerivedState & operator= (const NedDerivedState &)=delete
- void set_use_alt_pfix (const bool use_alt_pfix_in)

Setter for use alt pfix.

• void initialize (DynBody &subject_body, DynManager &dyn_manager) override

Begin initialization of a LvlhDerivedState.

• void update () override

Update the state.

Data Fields

bool register_frame {true}

If set (default), the NED frame will be registered with the dynamics manager at initialization time.

NorthEastDown ned_state

The NorthEastDown frame plus spherical/elliptical selector.

Planet * planet {}

The planet, the name of which is specified by the inherited reference_name data member.

Protected Member Functions

void compute_ned_frame (const RefFrameTrans &rel_trans)
 Update the state.

Protected Attributes

bool use alt pfix {}

Use pfix or alt_pfix flag.

EphemerisRefFrame * pfix_ptr {}

Pointer to planet fixed frame to be used, either pfix or alt_pfix.

• RefFrameState pfix_rel_state

Vehicle state relative to the planet-center, planet-fixed frame.

Private Attributes

DynManager * local_dm {}

Friends

- · class InputProcessor
- void init_attrjeod__NedDerivedState ()

8.6.1 Detailed Description

The class used for deriving the North-East-Down representations of a subject DynBody's state.

Definition at line 87 of file ned_derived_state.hh.

8.6.2 Constructor & Destructor Documentation

```
8.6.2.1 NedDerivedState() [1/2]
```

```
jeod::NedDerivedState::NedDerivedState ( ) [default]
```

8.6.2.2 \sim NedDerivedState()

```
jeod::NedDerivedState::~NedDerivedState ( ) [override]
```

NedDerivedState destructor.

Definition at line 51 of file ned_derived_state.cc.

References local_dm, ned_state, and pfix_ptr.

8.6.2.3 NedDerivedState() [2/2]

8.6.3 Member Function Documentation

8.6.3.1 compute_ned_frame()

Update the state.

Parameters

in rel_trans Planet relative st	ate
---------------------------------	-----

Definition at line 139 of file ned_derived_state.cc.

References ned_state.

Referenced by update().

8.6.3.2 initialize()

Begin initialization of a LvlhDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

Reimplemented from jeod::DerivedState.

Definition at line 84 of file ned_derived_state.cc.

References jeod::DerivedState::find_planet(), jeod::DerivedState::initialize(), local_dm, ned_state, pfix_ptr, planet, jeod::DerivedState::reference_name, register_frame, and use_alt_pfix.

8.6.3.3 operator=()

8.6.3.4 set_use_alt_pfix()

Setter for use_alt_pfix.

Definition at line 71 of file ned_derived_state.cc.

References use_alt_pfix.

8.6.3.5 update()

```
void jeod::NedDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 125 of file ned_derived_state.cc.

References compute_ned_frame(), ned_state, pfix_ptr, pfix_rel_state, and jeod::DerivedState::subject.

8.6.4 Friends And Related Function Documentation

8.6.4.1 init_attrjeod__NedDerivedState

```
void init_attrjeod__NedDerivedState ( ) [friend]
```

8.6.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file ned_derived_state.hh.

8.6.5 Field Documentation

8.6.5.1 local_dm DynManager* jeod::NedDerivedState::local_dm {} [private] Definition at line 128 of file ned_derived_state.hh. Referenced by initialize(), and ~NedDerivedState().

8.6.5.2 ned_state

```
NorthEastDown jeod::NedDerivedState::ned_state
```

The NorthEastDown frame plus spherical/elliptical selector.

trick_units(-)

Definition at line 102 of file ned_derived_state.hh.

Referenced by compute_ned_frame(), initialize(), update(), and \sim NedDerivedState().

8.6.5.3 pfix_ptr

```
EphemerisRefFrame* jeod::NedDerivedState::pfix_ptr {} [protected]
```

Pointer to planet fixed frame to be used, either pfix or alt_pfix.

Definition at line 120 of file ned_derived_state.hh.

Referenced by initialize(), update(), and \sim NedDerivedState().

8.6.5.4 pfix_rel_state

```
RefFrameState jeod::NedDerivedState::pfix_rel_state [protected]
```

Vehicle state relative to the planet-center, planet-fixed frame.

trick_units(-)

Definition at line 125 of file ned_derived_state.hh.

Referenced by update().

8.6.5.5 planet

```
Planet* jeod::NedDerivedState::planet {}
```

The planet, the name of which is specified by the inherited reference name data member.

trick_units(-)

Definition at line 108 of file ned_derived_state.hh.

Referenced by initialize().

8.6.5.6 register_frame

```
bool jeod::NedDerivedState::register_frame {true}
```

If set (default), the NED frame will be registered with the dynamics manager at initialization time.

This will make the frame accessible through the dynamic manager via its find_ref_frame method.trick_units(-)

Definition at line 97 of file ned_derived_state.hh.

Referenced by initialize().

8.6.5.7 use_alt_pfix

```
bool jeod::NedDerivedState::use_alt_pfix {} [protected]
```

Use pfix or alt_pfix flag.

Definition at line 114 of file ned derived state.hh.

Referenced by initialize(), and set_use_alt_pfix().

The documentation for this class was generated from the following files:


- ned_derived_state.hh
- ned_derived_state.cc

8.7 jeod::OrbElemDerivedState Class Reference

The class used for deriving the orbital elements representation of a subject DynBody's position.

```
#include <orb_elem_derived_state.hh>
```

Inheritance diagram for jeod::OrbElemDerivedState:



Public Member Functions

- OrbElemDerivedState ()=default
- ~OrbElemDerivedState () override

Destruct a OrbElemDerivedState object.

- OrbElemDerivedState (const OrbElemDerivedState &)=delete
- OrbElemDerivedState & operator= (const OrbElemDerivedState &)=delete
- void set_use_alt_inertial (const bool use_alt_inertial_in)

Setter for use_alt_inertial.

- void initialize (DynBody &subject_body, DynManager &dyn_manager) override
 Begin initialization of a OrbElemDerivedState.
- void update () override

Update the state.

Data Fields

· OrbitalElements elements

The orbital elements of the subject body with respect to the planet specified by the reference name.

Planet * planet {}

The planet, the name of which is specified by the inherited reference_name data member.

Protected Member Functions

• void compute_orbital_elements (const RefFrameTrans &rel_trans)

Compute the orbital elements for the current state.

Protected Attributes

• bool use alt inertial {}

Use inertial or alt_inertial flag.

EphemerisRefFrame * inertial_ptr {}

Pointer to planet inertial frame to be used, either inertial or alt_inertial.

• RefFrameState rel_state

Relative state; only used when the vehicle integration from is not the planet-centered inertial frame.

Friends

- class InputProcessor
- void init attrjeod OrbElemDerivedState ()

8.7.1 Detailed Description

The class used for deriving the orbital elements representation of a subject DynBody's position.

Definition at line 87 of file orb_elem_derived_state.hh.

8.7.2 Constructor & Destructor Documentation

8.7.2.1 OrbElemDerivedState() [1/2]

```
jeod::OrbElemDerivedState::OrbElemDerivedState ( ) [default]
```

8.7.2.2 ∼OrbElemDerivedState()

```
{\tt jeod::OrbElemDerivedState::}{\sim} {\tt OrbElemDerivedState} \ \ (\ ) \quad [override]
```

Destruct a OrbElemDerivedState object.

Definition at line 47 of file orb_elem_derived_state.cc.

References inertial_ptr.

8.7.2.3 OrbElemDerivedState() [2/2]

8.7.3 Member Function Documentation

8.7.3.1 compute_orbital_elements()

Compute the orbital elements for the current state.

Parameters

in	rel trans	Planet relative state.

Definition at line 123 of file orb_elem_derived_state.cc.

References elements, and planet.

Referenced by update().

8.7.3.2 initialize()

Begin initialization of a OrbElemDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

Reimplemented from jeod::DerivedState.

Definition at line 71 of file orb_elem_derived_state.cc.

References elements, jeod::DerivedState::find_planet(), inertial_ptr, jeod::DerivedState::initialize(), planet, jeod::

DerivedState::reference_name, and use_alt_inertial.

8.7.3.3 operator=()

8.7.3.4 set_use_alt_inertial()

Setter for use_alt_inertial.

Definition at line 58 of file orb_elem_derived_state.cc.

References use_alt_inertial.

8.7.3.5 update()

```
void jeod::OrbElemDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 101 of file orb_elem_derived_state.cc.

References compute_orbital_elements(), inertial_ptr, rel_state, jeod::DerivedState::subject, and jeod::Derived← State::update().

8.7.4 Friends And Related Function Documentation

8.7.4.1 init_attrjeod__OrbElemDerivedState

```
void init_attrjeod__OrbElemDerivedState ( ) [friend]
```

8.7.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file orb_elem_derived_state.hh.

8.7.5 Field Documentation

8.7.5.1 elements

```
OrbitalElements jeod::OrbElemDerivedState::elements
```

The orbital elements of the subject body with respect to the planet specified by the reference name.

trick_units(-)

Definition at line 96 of file orb_elem_derived_state.hh.

Referenced by compute_orbital_elements(), and initialize().

8.7.5.2 inertial_ptr

```
EphemerisRefFrame* jeod::OrbElemDerivedState::inertial_ptr {} [protected]
```

Pointer to planet inertial frame to be used, either inertial or alt_inertial.

Definition at line 114 of file orb_elem_derived_state.hh.

Referenced by initialize(), update(), and ~OrbElemDerivedState().

8.7.5.3 planet

```
Planet* jeod::OrbElemDerivedState::planet {}
```

The planet, the name of which is specified by the inherited reference_name data member.

trick units(-)

Definition at line 102 of file orb_elem_derived_state.hh.

Referenced by compute_orbital_elements(), and initialize().

8.7.5.4 rel_state

```
RefFrameState jeod::OrbElemDerivedState::rel_state [protected]
```

Relative state; only used when the vehicle integration from is not the planet-centered inertial frame.

trick_units(-)

Definition at line 120 of file orb_elem_derived_state.hh.

Referenced by update().

8.7.5.5 use_alt_inertial

```
bool jeod::OrbElemDerivedState::use_alt_inertial {} [protected]
```

Use inertial or alt_inertial flag.

Definition at line 108 of file orb_elem_derived_state.hh.

Referenced by initialize(), and set_use_alt_inertial().

The documentation for this class was generated from the following files:


- orb_elem_derived_state.hh
- orb_elem_derived_state.cc

8.8 jeod::PlanetaryDerivedState Class Reference

The class used for deriving the planet-fixed representations of a subject DynBody's position.

```
#include <planetary_derived_state.hh>
```

Inheritance diagram for jeod::PlanetaryDerivedState:



Public Member Functions

- PlanetaryDerivedState ()=default
- ~PlanetaryDerivedState () override

Destruct a PlanetaryDerivedState object.

- PlanetaryDerivedState (const PlanetaryDerivedState &)=delete
- PlanetaryDerivedState & operator= (const PlanetaryDerivedState &)=delete
- void set_use_alt_pfix (const bool use_alt_pfix_in)

Setter for use_alt_pfix.

- void initialize (DynBody &subject_body, DynManager &dyn_manager) override
 Begin initialization of a PlanetaryDerivedState.
- void update () override

Update the state.

Data Fields

• PlanetFixedPosition state

The planet-fixed state of the subject body's composite CoM.

Planet * planet {}

The planet, the name of which is specified by the inherited reference_name data member.

Protected Attributes

bool use_alt_pfix {}

Use pfix or alt_pfix flag.

EphemerisRefFrame * pfix_ptr {}

Pointer to planet fixed frame to be used, either pfix or alt pfix.

Friends

- class InputProcessor
- void init_attrjeod__PlanetaryDerivedState ()

Additional Inherited Members

8.8.1 Detailed Description

The class used for deriving the planet-fixed representations of a subject DynBody's position.

Definition at line 85 of file planetary_derived_state.hh.

8.8.2 Constructor & Destructor Documentation

```
8.8.2.1 PlanetaryDerivedState() [1/2]
```

```
jeod::PlanetaryDerivedState::PlanetaryDerivedState ( ) [default]
```

8.8.2.2 ~PlanetaryDerivedState()

```
jeod::PlanetaryDerivedState::~PlanetaryDerivedState ( ) [override]
```

Destruct a PlanetaryDerivedState object.

Definition at line 46 of file planetary_derived_state.cc.

References pfix ptr.

8.8.2.3 PlanetaryDerivedState() [2/2]

8.8.3 Member Function Documentation

8.8.3.1 initialize()

Begin initialization of a PlanetaryDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

Reimplemented from jeod::DerivedState.

Definition at line 70 of file planetary_derived_state.cc.

References jeod::DerivedState::find_planet(), jeod::DerivedState::initialize(), pfix_ptr, planet, jeod::DerivedState \leftarrow ::reference_name, state, and use_alt_pfix.

8.8.3.2 operator=()

8.8.3.3 set_use_alt_pfix()

Setter for use_alt_pfix.

Definition at line 57 of file planetary_derived_state.cc.

 $References\ use_alt_pfix.$

8.8.3.4 update()

```
void jeod::PlanetaryDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 97 of file planetary_derived_state.cc.

References pfix ptr, state, and jeod::DerivedState::subject.

8.8.4 Friends And Related Function Documentation

8.8.4.1 init_attrjeod__PlanetaryDerivedState

```
void init_attrjeod__PlanetaryDerivedState ( ) [friend]
```

8.8.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 87 of file planetary_derived_state.hh.

8.8.5 Field Documentation

8.8.5.1 pfix_ptr

```
EphemerisRefFrame* jeod::PlanetaryDerivedState::pfix_ptr {} [protected]
```

Pointer to planet fixed frame to be used, either pfix or alt_pfix.

Definition at line 111 of file planetary_derived_state.hh.

Referenced by initialize(), update(), and ~PlanetaryDerivedState().

8.8.5.2 planet

```
Planet* jeod::PlanetaryDerivedState::planet {}
```

The planet, the name of which is specified by the inherited reference_name data member.

trick_units(-)

Definition at line 99 of file planetary_derived_state.hh.

Referenced by initialize().

8.8.5.3 state

```
PlanetFixedPosition jeod::PlanetaryDerivedState::state
```

The planet-fixed state of the subject body's composite CoM.

trick_units(-)

Definition at line 93 of file planetary_derived_state.hh.

Referenced by initialize(), and update().

8.8.5.4 use_alt_pfix

```
bool jeod::PlanetaryDerivedState::use_alt_pfix {} [protected]
```

Use pfix or alt_pfix flag.

Definition at line 105 of file planetary_derived_state.hh.

Referenced by initialize(), and set_use_alt_pfix().

The documentation for this class was generated from the following files:


- planetary_derived_state.hh
- planetary_derived_state.cc

8.9 jeod::RelativeDerivedState Class Reference

The class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame.

```
#include <relative_derived_state.hh>
```

Inheritance diagram for jeod::RelativeDerivedState:



Public Types

enum DirectionSense { undefined = -1, ComputeSubjectStateinTarget = 0, ComputeTargetStateinSubject = 2 }

an enumeration to specify the direction and sense, and frame representation intended for output from the RelativeDerivedState calculations.

Public Member Functions

- RelativeDerivedState ()=default
- ∼RelativeDerivedState () override

Destruct a RelativeDerivedState object.

- RelativeDerivedState (const RelativeDerivedState &)=delete
- RelativeDerivedState & operator= (const RelativeDerivedState &)=delete
- void set_name (std::string name_in)

Setter for the name.

· void set target frame (RefFrame &tf)

Quick shortcut allowing use of conversion routines without requiring initialization.

void set_subject_frame (BodyRefFrame &sf)

Quick shortcut allowing use of conversion routines without requiring initialization.

void initialize (DynBody &subject_body, DynManager &dyn_manager) override

Begin initialization of a RelativeDerivedState.

virtual void initialize (DynManager &dyn_manager)

Initialize a RelativeDerivedState, without a DynBody.

• void update () override

Update the state.

· void set activation flag (bool raf)

Setter for the activation flag to on or off and If off, unsubscribes subject and target frames /param raf RelativeDerivedState activation flag for RelKin manager.

Data Fields

• std::string name {""}

The name of this relative derived state.

std::string subject_frame_name

The name of the frame on the subject vehicle.

std::string target_frame_name

The name of the target reference frame.

DirectionSense direction sense {undefined}

Indicates direction in which relative state is to be computed.

RefFrameState rel_state

Computed relative state.

· bool active {true}

Bool flag used by the RelKin model to turn on/off which Relative Derived State needs to be managed.

Protected Attributes

BodyRefFrame * subject_frame {}

The reference frame corresponding to the user-input subject_frame_name.

RefFrame * target frame {}

The reference frame corresponding to the user-input target_frame_name.

Friends

- class InputProcessor
- void init_attrjeod__RelativeDerivedState ()

Additional Inherited Members

8.9.1 Detailed Description

The class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame.

Definition at line 88 of file relative_derived_state.hh.

8.9.2 Member Enumeration Documentation

8.9.2.1 DirectionSense

```
enum jeod::RelativeDerivedState::DirectionSense
```

an enumeration to specify the direction and sense, and frame representation intended for output from the RelativeDerivedState calculations.

Enumerator

undefined	
ComputeSubjectStateinTarget	
ComputeTargetStateinSubject	

Definition at line 98 of file relative_derived_state.hh.

8.9.3 Constructor & Destructor Documentation

8.9.3.1 RelativeDerivedState() [1/2]

```
jeod::RelativeDerivedState::RelativeDerivedState ( ) [default]
```

8.9.3.2 ~RelativeDerivedState()

```
jeod::RelativeDerivedState::~RelativeDerivedState ( ) [override]
```

Destruct a RelativeDerivedState object.

Definition at line 50 of file relative_derived_state.cc.

References subject_frame, and target_frame.

8.9.3.3 RelativeDerivedState() [2/2]

8.9.4 Member Function Documentation

Begin initialization of a RelativeDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

Reimplemented from jeod::DerivedState.

Definition at line 71 of file relative_derived_state.cc.

References jeod::DerivedState::initialize().

Referenced by jeod::LvIhRelativeDerivedState::initialize().

```
8.9.4.2 initialize() [2/2]
```

Initialize a RelativeDerivedState, without a DynBody.

No pass up the initialization chain is possible for this method, since it is not inherited.

Parameters

in,ou	dyn_manager	Dynamics manager

Definition at line 86 of file relative_derived_state.cc.

References jeod::DerivedStateMessages::invalid_name, jeod::DerivedState::state_identifier, jeod::DerivedState ::subject, subject_frame, subject_frame_name, target_frame, and target_frame_name.

8.9.4.3 operator=()

8.9.4.4 set_activation_flag()

```
void jeod::RelativeDerivedState::set_activation_flag ( bool \ raf \ )
```

Setter for the activation flag to on or off and If off, unsubscribes subject and target frames /param raf RelativeDerivedState activation flag for RelKin manager.

Definition at line 201 of file relative_derived_state.cc.

References active, subject_frame, and target_frame.

8.9.4.5 set_name()

Setter for the name.

Definition at line 172 of file relative_derived_state.hh.

8.9.4.6 set_subject_frame()

```
void jeod::RelativeDerivedState::set_subject_frame ( {\tt BodyRefFrame \ \& \ sf \ ) \quad [inline]}
```

Quick shortcut allowing use of conversion routines without requiring initialization.

Parameters

```
sf New subject frame.
```

Definition at line 192 of file relative_derived_state.hh.

8.9.4.7 set_target_frame()

Quick shortcut allowing use of conversion routines without requiring initialization.

Parameters

```
tf New target frame.
```

Definition at line 182 of file relative_derived_state.hh.

8.9.4.8 update()

```
void jeod::RelativeDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 174 of file relative_derived_state.cc.

References ComputeSubjectStateinTarget, ComputeTargetStateinSubject, direction_sense, jeod::DerivedState
Messages::illegal_value, rel_state, subject_frame, and target_frame.

8.9.5 Friends And Related Function Documentation

8.9.5.1 init_attrjeod_ RelativeDerivedState

```
void init_attrjeod__RelativeDerivedState ( ) [friend]
```

8.9.5.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 90 of file relative_derived_state.hh.

8.9.6 Field Documentation

```
8.9.6.1 active
bool jeod::RelativeDerivedState::active {true}
Bool flag used by the RelKin model to turn on/off which Relative Derived State needs to be managed.
trick_units(-)
Definition at line 147 of file relative_derived_state.hh.
Referenced by set_activation_flag().
8.9.6.2 direction sense
DirectionSense jeod::RelativeDerivedState::direction_sense {undefined}
Indicates direction in which relative state is to be computed.
trick_units(-)
Definition at line 136 of file relative_derived_state.hh.
Referenced \ by \ jeod:: LvIhRelative Derived State:: LvIhRelative Derived State(), \ and \ update().
8.9.6.3 name
std::string jeod::RelativeDerivedState::name {""}
The name of this relative derived state.
trick_units(-)
Definition at line 116 of file relative_derived_state.hh.
```

Referenced by jeod::LvlhRelativeDerivedState::convert_circ_to_rect(), and jeod::LvlhRelativeDerivedState ←

::convert_rect_to_circ().

8.9.6.4 rel_state

RefFrameState jeod::RelativeDerivedState::rel_state

Computed relative state.

trick_units(-)

Definition at line 141 of file relative_derived_state.hh.

Referenced by jeod::LvlhRelativeDerivedState::convert_circ_to_rect(), jeod::LvlhRelativeDerivedState::convert_circ_to_rect(), jeod::LvlhRelativeDerivedState::update(), and update().

8.9.6.5 subject_frame

```
BodyRefFrame* jeod::RelativeDerivedState::subject_frame {} [protected]
```

The reference frame corresponding to the user-input subject_frame_name.

trick_units(-)

Definition at line 153 of file relative_derived_state.hh.

Referenced by initialize(), set_activation_flag(), jeod::LvlhRelativeDerivedState::update(), update(), and $\sim \leftarrow$ RelativeDerivedState().

8.9.6.6 subject_frame_name

```
std::string jeod::RelativeDerivedState::subject_frame_name
```

The name of the frame on the subject vehicle.

This can specify one of the vehicle's three primary reference frames (core body, composite body, or structure) or one of the vehicle's vehicle point frames. The vehicle name can be included in or omitted from the subject frame name. A vehicle name prefix is assumed if it is omitted.trick_units(-)

Definition at line 126 of file relative_derived_state.hh.

Referenced by initialize().

8.9.6.7 target_frame

```
RefFrame* jeod::RelativeDerivedState::target_frame {} [protected]
```

The reference frame corresponding to the user-input target frame name.

trick_units(-)

Definition at line 158 of file relative_derived_state.hh.

Referenced by jeod::LvlhRelativeDerivedState::convert_circ_to_rect(), jeod::LvlhRelativeDerivedState::convert_ \leftarrow rect_to_circ(), jeod::LvlhRelativeDerivedState::do_theta_dot_correction(), initialize(), set_activation_flag(), jeod:: \leftarrow LvlhRelativeDerivedState::update(), update(), and \sim RelativeDerivedState().

8.9.6.8 target_frame_name

```
std::string jeod::RelativeDerivedState::target_frame_name
```

The name of the target reference frame.

trick_units(-)

Definition at line 131 of file relative_derived_state.hh.

Referenced by initialize().

The documentation for this class was generated from the following files:


- · relative_derived_state.hh
- relative_derived_state.cc

8.10 jeod::SolarBetaDerivedState Class Reference

The class for calculating the solar beta of a vehicle.

```
#include <solar_beta_derived_state.hh>
```

 $Inheritance\ diagram\ for\ jeod:: Solar Beta Derived State:$



Public Member Functions

- SolarBetaDerivedState ()=default
- ∼SolarBetaDerivedState () override

Destruct a SolarBetaDerivedState.

- SolarBetaDerivedState (const SolarBetaDerivedState &)=delete
- SolarBetaDerivedState & operator= (const SolarBetaDerivedState &)=delete
- void initialize (DynBody &subject_body, DynManager &dyn_manager) override

Begin initialization of a SolarBetaDerivedState.

· void update () override

Update the state.

Data Fields

Planet * planet {}

The planet, the name of which is specified by the inherited reference_name data member.

Planet * sun {}

The sun, found by looking for the planetary object named "Sun".

• double solar beta {}

The angle between the orbital plane and the sun position vector.

· bool active {true}

Indicates whether the model is "active".

Protected Attributes

• RefFrameState veh_wrt_planet

The state of the vehicle with respect to the planet.

double sun_wrt_planet [3] {}

The position of the sun with respect to the planet.

Friends

- class InputProcessor
- void init_attrjeod__SolarBetaDerivedState ()

Additional Inherited Members

8.10.1 Detailed Description

The class for calculating the solar beta of a vehicle.

Assumptions and Limitations

• The vehicle must be in orbit about the named planet

Definition at line 83 of file solar_beta_derived_state.hh.

8.10.2 Constructor & Destructor Documentation

8.10.2.1 SolarBetaDerivedState() [1/2]

```
jeod::SolarBetaDerivedState::SolarBetaDerivedState ( ) [default]
```

8.10.2.2 ~SolarBetaDerivedState()

```
{\tt jeod::SolarBetaDerivedState::} {\sim} SolarBetaDerivedState \ (\ ) \quad [override]
```

Destruct a SolarBetaDerivedState.

Definition at line 146 of file solar_beta_derived_state.cc.

References planet, and sun.

8.10.2.3 SolarBetaDerivedState() [2/2]

8.10.3 Member Function Documentation

8.10.3.1 initialize()

Begin initialization of a SolarBetaDerivedState.

The initialize method for all subclasses of DerivedState *must* pass the initialize call to their immediate parent class, which in turn must do the same, eventually invoking this method.

Parameters

in,out	subject_body	Subject body
in,out	dyn_manager	Dynamics manager

Reimplemented from jeod::DerivedState.

Definition at line 63 of file solar_beta_derived_state.cc.

References active, jeod::DerivedState::find_planet(), jeod::DerivedState::initialize(), planet, jeod::DerivedState \leftarrow ::reference_name, and sun.

8.10.3.2 operator=()

8.10.3.3 update()

```
void jeod::SolarBetaDerivedState::update ( ) [override], [virtual]
```

Update the state.

Reimplemented from jeod::DerivedState.

Definition at line 88 of file solar_beta_derived_state.cc.

References active, jeod::DerivedStateMessages::divide_by_zero, jeod::epsilon, planet, solar_beta, jeod::Derived← State::subject, sun, sun_wrt_planet, and veh_wrt_planet.

8.10.4 Friends And Related Function Documentation

8.10.4.1 init_attrjeod__SolarBetaDerivedState

```
void init_attrjeod__SolarBetaDerivedState ( ) [friend]
```

8.10.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 85 of file solar_beta_derived_state.hh.

8.10.5 Field Documentation

8.10.5.1 active

```
bool jeod::SolarBetaDerivedState::active {true}
```

Indicates whether the model is "active".

This flag defaults to true. This default value results in

- Initialization-time subscriptions issued against the planet-centered and sun-centered inertial frames to ensure that the planet and the Sun are a part of the active reference frame tree, and
- Run-time calculations of the solar beta angle, updated by calls to SolarBetaDerivedState::update.

Setting the active flag to false prior to the call to SolarBetaDerivedState::initialize permanently disables the model. Setting the active flag to true after having set it to false prior to the call to initialize initially will have no effect; the model is permanently disabled.

If the value of the flag is true at the time of the call to SolarBetaDerivedState::initialize, subsequently setting the flag to false will temporarily disable the model (cause SolarBetaDerivedState::update to immediately return). Updates will once again be performed when the flag is set to true.trick_units(–)

Definition at line 132 of file solar_beta_derived_state.hh.

Referenced by initialize(), and update().

8.10.5.2 planet

```
Planet* jeod::SolarBetaDerivedState::planet {}
```

The planet, the name of which is specified by the inherited reference name data member.

```
trick_units(-)
```

Definition at line 95 of file solar_beta_derived_state.hh.

Referenced by initialize(), update(), and ~SolarBetaDerivedState().

8.10.5.3 solar_beta

```
double jeod::SolarBetaDerivedState::solar_beta {}
```

The angle between the orbital plane and the sun position vector.

Positive solar beta will be on the side of the positive angular momentum vector.trick_units(rad)

Definition at line 107 of file solar beta derived state.hh.

Referenced by update().

```
8.10.5.4 sun
Planet* jeod::SolarBetaDerivedState::sun {}
The sun, found by looking for the planetary object named "Sun".
trick units(-)
Definition at line 100 of file solar_beta_derived_state.hh.
Referenced by initialize(), update(), and ~SolarBetaDerivedState().
8.10.5.5 sun_wrt_planet
double jeod::SolarBetaDerivedState::sun_wrt_planet[3] {} [protected]
The position of the sun with respect to the planet.
trick_units(m)
Definition at line 165 of file solar_beta_derived_state.hh.
Referenced by update().
8.10.5.6 veh_wrt_planet
RefFrameState jeod::SolarBetaDerivedState::veh_wrt_planet [protected]
The state of the vehicle with respect to the planet.
trick_units(-)
Definition at line 160 of file solar_beta_derived_state.hh.
Referenced by update().
```

The documentation for this class was generated from the following files:

- solar_beta_derived_state.hh
- solar_beta_derived_state.cc

Chapter 9

File Documentation

9.1 class_declarations.hh File Reference

Forward declarations of classes defined in XXX_derived_state.hh files.

Namespaces

jeod

Namespace jeod.

9.1.1 Detailed Description

Forward declarations of classes defined in XXX derived state.hh files.

9.2 derived_state.cc File Reference

Define methods for the base body initialization class.

```
#include <array>
#include <cstddef>
#include <typeinfo>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/derived_state.hh"
#include "../include/derived_state_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

9.2.1 Detailed Description

Define methods for the base body initialization class.

9.3 derived_state.hh File Reference

Define the class DerivedState, the base class used for deriving a state representation of some subject DynBody.

```
#include <string>
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "dynamics/dyn_body/include/dyn_body.hh"
```

Data Structures

· class jeod::DerivedState

The base class used for deriving a state representation of some subject DynBody.

Namespaces

jeod

Namespace jeod.

9.3.1 Detailed Description

Define the class DerivedState, the base class used for deriving a state representation of some subject DynBody.

9.4 derived_state_messages.cc File Reference

Implement the class DerivedStateMessages.

```
#include "utils/message/include/make_message_code.hh"
#include "../include/derived_state_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

Macros

9.4.1 Detailed Description

Implement the class DerivedStateMessages.

9.4.2 Macro Definition Documentation

9.4.2.1 MAKE_DERIVEDSTATE_MESSAGE_CODE

```
 \begin{tabular}{ll} \# define $MAKE\_DERIVEDSTATE\_MESSAGE\_CODE($ id.) $ JEOD\_MAKE\_MESSAGE\_CODE(DerivedStateMessages, "dynamics/derived\_state/", id.) $ Id. $ Id.
```

Definition at line 37 of file derived_state_messages.cc.

9.5 derived_state_messages.hh File Reference

Define the class DerivedStateMessages, the class that specifies the message IDs used in the DerivedState model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::DerivedStateMessages

The class that specifies the message IDs used in the DerivedState model.

Namespaces

• jeod

Namespace jeod.

9.5.1 Detailed Description

Define the class DerivedStateMessages, the class that specifies the message IDs used in the DerivedState model.

9.6 euler_derived_state.cc File Reference

Define methods for the Euler attitude derived state class.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "utils/math/include/matrix3x3.hh"
#include "utils/orientation/include/orientation.hh"
#include "../include/euler_derived_state.hh"
```

Namespaces

• jeod

Namespace jeod.

9.6.1 Detailed Description

Define methods for the Euler attitude derived state class.

9.7 euler_derived_state.hh File Reference

Define the class EulerDerivedState, the class used for deriving the Euler angle representation of a subject Dyn← Body's attitude.

```
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "utils/orientation/include/orientation.hh"
#include "utils/ref_frames/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "derived_state.hh"
```

Data Structures

· class jeod::EulerDerivedState

The class used for deriving the Euler angle representation of a subject DynBody's attitude.

Namespaces

• jeod

Namespace jeod.

9.7.1 Detailed Description

Define the class EulerDerivedState, the class used for deriving the Euler angle representation of a subject Dyn← Body's attitude.

9.8 lvlh_derived_state.cc File Reference

Define methods for the base body initialization class.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/planet.hh"
#include "utils/math/include/vector3.hh"
#include "../include/lvlh_derived_state.hh"
```

Namespaces

• jeod

Namespace jeod.

9.8.1 Detailed Description

Define methods for the base body initialization class.

9.9 lvlh_derived_state.hh File Reference

Define the class LvlhDerivedState, the class used for deriving the rectilinear LVLH representations of a subject DynBody's state.

```
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "utils/lvlh_frame/include/lvlh_frame.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "derived_state.hh"
```

Data Structures

· class jeod::LvlhDerivedState

The class used for deriving the rectilinear LVLH representations of a subject DynBody's state.

Namespaces

· jeod

Namespace jeod.

9.9.1 Detailed Description

Define the class LvlhDerivedState, the class used for deriving the rectilinear LVLH representations of a subject DynBody's state.

9.10 Ivlh relative derived state.cc File Reference

Define methods for the LVLH relative state class.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/math/include/matrix3x3.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/derived_state_messages.hh"
#include "../include/lvlh_relative_derived_state.hh"
```

Namespaces

jeod

Namespace jeod.

9.10.1 Detailed Description

Define methods for the LVLH relative state class.

9.11 lvlh_relative_derived_state.hh File Reference

Define the class LvlhRelativeDerivedState, the class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

```
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/base_planet.hh"
#include "utils/lvlh_frame/include/lvlh_type.hh"
#include "utils/ref_frames/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "relative_derived_state.hh"
```

Data Structures

· class jeod::LvlhRelativeDerivedState

The class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

Namespaces

jeod

Namespace jeod.

9.11.1 Detailed Description

Define the class LvlhRelativeDerivedState, the class used for calculating the LVLH state of a subject DynBody relative to some LVLH reference frame.

9.12 ned_derived_state.cc File Reference

Define methods for NedDerivedState.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/planet.hh"
#include "utils/planet_fixed/north_east_down/include/north_east_down.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "../include/ned_derived_state.hh"
```

Namespaces

jeod

Namespace jeod.

9.12.1 Detailed Description

Define methods for NedDerivedState.

9.13 ned_derived_state.hh File Reference

Define the class NedDerivedState, the class used for deriving the NED representations of a subject DynBody's state.

```
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/ephemerides/ephem_interface/include/ephem_ref_frame.
hh"
#include "utils/planet_fixed/north_east_down/include/north_east_down.hh"
#include "utils/ref_frames/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "derived_state.hh"
```

Data Structures

class jeod::NedDerivedState

The class used for deriving the North-East-Down representations of a subject DynBody's state.

Namespaces

· jeod

Namespace jeod.

9.13.1 Detailed Description

Define the class NedDerivedState, the class used for deriving the NED representations of a subject DynBody's state.

9.14 orb_elem_derived_state.cc File Reference

Define methods for the orbital elements derived state class.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "environment/planet/include/planet.hh"
#include "utils/orbital_elements/include/orbital_elements.hh"
#include "../include/orb_elem_derived_state.hh"
```

Namespaces

• jeod

Namespace jeod.

9.14.1 Detailed Description

Define methods for the orbital elements derived state class.

9.15 orb elem derived state.hh File Reference

Define the class OrbElemDerivedState, the class used for deriving the orbital elements representation of a subject DynBody's position.

```
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/ephemerides/ephem_interface/include/ephem_ref_frame.
hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/orbital_elements/include/orbital_elements.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "derived_state.hh"
#include "environment/planet/include/planet.hh"
```

Data Structures

class jeod::OrbElemDerivedState

The class used for deriving the orbital elements representation of a subject DynBody's position.

Namespaces

jeod

Namespace jeod.

9.15.1 Detailed Description

Define the class OrbElemDerivedState, the class used for deriving the orbital elements representation of a subject DynBody's position.

9.16 planetary_derived_state.cc File Reference

Define methods for the base body initialization class.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "environment/planet/include/planet.hh"
#include "../include/planetary_derived_state.hh"
```

Namespaces

• jeod

Namespace jeod.

9.16.1 Detailed Description

Define methods for the base body initialization class.

9.17 planetary_derived_state.hh File Reference

Define the class PlanetaryDerivedState, the class used for deriving the planet-fixed representations of a subject DynBody's position.

```
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/planet_fixed/planet_fixed_posn/include/planet_fixed_posn.\to
hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "derived_state.hh"
```

Data Structures

· class jeod::PlanetaryDerivedState

The class used for deriving the planet-fixed representations of a subject DynBody's position.

Namespaces

· jeod

Namespace jeod.

9.17.1 Detailed Description

Define the class PlanetaryDerivedState, the class used for deriving the planet-fixed representations of a subject DynBody's position.

9.18 relative_derived_state.cc File Reference

Define methods for the base body initialization class.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/ref_frames/include/ref_frame.hh"
#include "../include/derived_state_messages.hh"
#include "../include/relative_derived_state.hh"
```

Namespaces

· jeod

Namespace jeod.

9.18.1 Detailed Description

Define methods for the base body initialization class.

9.19 relative derived state.hh File Reference

Define the class RelativeDerivedState, the class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame.

```
#include "derived_state.hh"
#include "dynamics/dyn_body/include/class_declarations.hh"
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "utils/ref_frames/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include <string>
#include <utility>
```

Data Structures

· class jeod::RelativeDerivedState

The class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame.

Namespaces

jeod

Namespace jeod.

9.19.1 Detailed Description

Define the class RelativeDerivedState, the class used for deriving the state of some frame associated with the subject DynBody relative to some other target frame.

9.20 solar_beta_derived_state.cc File Reference

This function calculates the angle between a spacecraft's orbital plane and the vector from the relevant planet to the sun.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/planet.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/derived_state_messages.hh"
#include "../include/solar_beta_derived_state.hh"
```

Namespaces

jeod

Namespace jeod.

Variables

• static constexpr double jeod::epsilon = 0.0000001

9.20.1 Detailed Description

This function calculates the angle between a spacecraft's orbital plane and the vector from the relevant planet to the sun.

9.21 solar_beta_derived_state.hh File Reference

A class for calculating the solar beta of a vehicle.

```
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "derived_state.hh"
#include "environment/planet/include/planet.hh"
```

Data Structures

· class jeod::SolarBetaDerivedState

The class for calculating the solar beta of a vehicle.

Namespaces

• jeod

Namespace jeod.

9.21.1 Detailed Description

A class for calculating the solar beta of a vehicle.

Index

\sim DerivedState	jeod::DerivedStateMessages, 24
jeod::DerivedState, 18	do_theta_dot_correction
\sim EulerDerivedState	jeod::LvlhRelativeDerivedState, 37
jeod::EulerDerivedState, 27	Dynamics, 12
\sim LvlhDerivedState	
jeod::LvlhDerivedState, 32	elements
\sim LvlhRelativeDerivedState	jeod::OrbElemDerivedState, 49
jeod::LvlhRelativeDerivedState, 36	epsilon
\sim NedDerivedState	jeod, 16
jeod::NedDerivedState, 41	euler_derived_state.cc, 72
\sim OrbElemDerivedState	euler_derived_state.hh, 72
jeod::OrbElemDerivedState, 47	EulerDerivedState
\sim PlanetaryDerivedState	jeod::EulerDerivedState, 27
jeod::PlanetaryDerivedState, 52	
\sim RelativeDerivedState	fatal_error
jeod::RelativeDerivedState, 57	jeod::DerivedStateMessages, 24
\sim SolarBetaDerivedState	find_planet
jeod::SolarBetaDerivedState, 65	jeod::DerivedState, 19
active	illegal_value
jeod::RelativeDerivedState, 61	jeod::DerivedStateMessages, 24
jeod::SolarBetaDerivedState, 66	inertial_ptr
journous and a surface and a s	jeod::OrbElemDerivedState, 49
body ref angles	init_attrjeodDerivedState
jeod::EulerDerivedState, 29	jeod::DerivedState, 21
J	init_attrjeodDerivedStateMessages
class_declarations.hh, 69	jeod::DerivedStateMessages, 23
compute_ned_frame	init_attrjeodEulerDerivedState
jeod::NedDerivedState, 42	jeod::EulerDerivedState, 29
compute_orbital_elements	init_attrjeodLvlhDerivedState
jeod::OrbElemDerivedState, 47	jeod::LvlhDerivedState, 33
convert_circ_to_rect	init_attrjeodLvlhRelativeDerivedState
jeod::LvlhRelativeDerivedState, 37	jeod::LvlhRelativeDerivedState, 39
convert_rect_to_circ	init attrjeod NedDerivedState
jeod::LvlhRelativeDerivedState, 37	jeod::NedDerivedState, 43
joodnii maanoi omaaaa, or	init_attrjeodOrbElemDerivedState
derived_state.cc, 69	jeod::OrbElemDerivedState, 49
derived_state.hh, 70	init_attrjeodPlanetaryDerivedState
derived_state_messages.cc, 70	jeod::PlanetaryDerivedState, 53
MAKE_DERIVEDSTATE_MESSAGE_CODE, 71	init attrjeod RelativeDerivedState
derived_state_messages.hh, 71	jeod::RelativeDerivedState, 60
DerivedState, 13	init_attrjeodSolarBetaDerivedState
jeod::DerivedState, 18	jeod::SolarBetaDerivedState, 66
DerivedStateMessages	initialize
jeod::DerivedStateMessages, 23	jeod::DerivedState, 19
direction_sense	jeod::EulerDerivedState, 27, 28
jeod::RelativeDerivedState, 61	jeod::LvlhDerivedState, 32
DirectionSense	jeod::LvlhRelativeDerivedState, 38
jeod::RelativeDerivedState, 57	jeod::NedDerivedState, 42
divide_by_zero	jeod::NedDerivedState, 42 jeod::OrbElemDerivedState, 48
divido_by_2610	jedaOrbelellibelivedolale, 40

82 INDEX

jeod::PlanetaryDerivedState, 52 jeod::RelativeDerivedState, 58 jeod::SolarBetaDerivedState, 65	jeod::LvlhDerivedState, 31 ∼LvlhDerivedState, 32 init_attrjeodLvlhDerivedState, 33
InputProcessor	initialize, 32
jeod::DerivedState, 21	InputProcessor, 33
jeod::DerivedStateMessages, 23	local_dm, 34
jeod::EulerDerivedState, 29	lvlh_frame, 34
jeod::LvlhDerivedState, 33	lvlh_state, 34
jeod::LvlhRelativeDerivedState, 39	LvlhDerivedState, 32
jeod::NedDerivedState, 43	operator=, 33
jeod::OrbElemDerivedState, 49	planet_centered_inertial, 34
jeod::PlanetaryDerivedState, 54	register_frame, 34
jeod::RelativeDerivedState, 60	update, 33
jeod::SolarBetaDerivedState, 66	jeod::LvlhRelativeDerivedState, 35
invalid_name	\sim LvlhRelativeDerivedState, 36
jeod::DerivedStateMessages, 24	convert_circ_to_rect, 37
invalid_object	convert_rect_to_circ, 37
jeod::DerivedStateMessages, 25	do_theta_dot_correction, 37
jeod, 15	<pre>init_attrjeodLvlhRelativeDerivedState, 39 initialize, 38</pre>
epsilon, 16	InputProcessor, 39
jeod::DerivedState, 17	lvlh_type, 39
\sim DerivedState, 18	LvlhRelativeDerivedState, 36
DerivedState, 18	operator=, 38
find_planet, 19	update, 38
init_attrjeodDerivedState, 21	use_theta_dot_correction, 39
initialize, 19	jeod::NedDerivedState, 40
InputProcessor, 21	~NedDerivedState, 41
operator=, 20	compute_ned_frame, 42
reference_name, 21	init_attrjeodNedDerivedState, 43
set_reference_name, 20	initialize, 42
state_identifier, 21	InputProcessor, 43
subject, 21	local_dm, 44
update, 20	ned_state, 44
jeod::DerivedStateMessages, 22	NedDerivedState, 41
DerivedStateMessages, 23	operator=, 43
divide_by_zero, 24	pfix_ptr, 44
fatal_error, 24	pfix_rel_state, 44
illegal_value, 24 init_attrjeodDerivedStateMessages, 23	planet, 44
InputProcessor, 23	register_frame, 45
invalid_name, 24	set_use_alt_pfix, 43
invalid_object, 25	update, 43
null_pointer, 25	use_alt_pfix, 45
operator=, 23	jeod::OrbElemDerivedState, 45
trace, 25	~OrbElemDerivedState, 47
jeod::EulerDerivedState, 26	compute_orbital_elements, 47
~EulerDerivedState, 27	elements, 49
body ref angles, 29	inertial_ptr, 49
EulerDerivedState, 27	init_attrjeodOrbElemDerivedState, 49
init_attrjeodEulerDerivedState, 29	initialize, 48
initialize, 27, 28	InputProcessor, 49
InputProcessor, 29	operator=, 48
operator=, 28	OrbElemDerivedState, 47
ref_body_angles, 29	planet, 50
rel_frame, 30	rel_state, 50
rel_state, 30	set_use_alt_inertial, 48
sequence, 30	update, 48
update, 28	use_alt_inertial, 50

INDEX 83

icad::PlaneteryDerivedState_E1	icadul ylhDariyadStata 24
jeod::PlanetaryDerivedState, 51	jeod::LvlhDerivedState, 34
~PlanetaryDerivedState, 52	lvlh_type
init_attrjeodPlanetaryDerivedState, 53	jeod::LvlhRelativeDerivedState, 39
initialize, 52	LvlhDerivedState
InputProcessor, 54	jeod::LvlhDerivedState, 32
operator=, 53	LvlhRelativeDerivedState
pfix_ptr, 54	jeod::LvlhRelativeDerivedState, 36
planet, 54	MAKE DEDIVEDOTATE MESSAGE CODE
PlanetaryDerivedState, 52	MAKE_DERIVEDSTATE_MESSAGE_CODE
set_use_alt_pfix, 53	derived_state_messages.cc, 71
state, 54	Models, 11
update, 53	
use_alt_pfix, 54	name
jeod::RelativeDerivedState, 55	jeod::RelativeDerivedState, 61
\sim RelativeDerivedState, 57	ned_derived_state.cc, 75
active, 61	ned_derived_state.hh, 75
direction_sense, 61	ned_state
DirectionSense, 57	jeod::NedDerivedState, 44
init_attrjeodRelativeDerivedState, 60	NedDerivedState
initialize, 58	jeod::NedDerivedState, 41
InputProcessor, 60	null_pointer
name, 61	jeod::DerivedStateMessages, 25
operator=, 59	•
rel_state, 61	operator=
RelativeDerivedState, 57	jeod::DerivedState, 20
set_activation_flag, 59	jeod::DerivedStateMessages, 23
set_name, 59	jeod::EulerDerivedState, 28
set_subject_frame, 59	jeod::LvlhDerivedState, 33
set_target_frame, 60	jeod::LvlhRelativeDerivedState, 38
subject_frame, 62	jeod::NedDerivedState, 43
subject_frame_name, 62	jeod::OrbElemDerivedState, 48
target_frame, 62	jeod::PlanetaryDerivedState, 53
- -	jeod::RelativeDerivedState, 59
target_frame_name, 63	jeod::SolarBetaDerivedState, 66
update, 60	orb_elem_derived_state.cc, 76
jeod::SolarBetaDerivedState, 63	orb_elem_derived_state.hh, 76
~SolarBetaDerivedState, 65	OrbElemDerivedState
active, 66	jeod::OrbElemDerivedState, 47
init_attrjeodSolarBetaDerivedState, 66	jeodOrbElembenvedState, 47
initialize, 65	pfix_ptr
InputProcessor, 66	jeod::NedDerivedState, 44
operator=, 66	jeod::PlanetaryDerivedState, 54
planet, 67	pfix_rel_state
solar_beta, 67	• — —
SolarBetaDerivedState, 65	jeod::NedDerivedState, 44
sun, 67	planet
sun_wrt_planet, 68	jeod::NedDerivedState, 44
update, 66	jeod::OrbElemDerivedState, 50
veh_wrt_planet, 68	jeod::PlanetaryDerivedState, 54
	jeod::SolarBetaDerivedState, 67
local_dm	planet_centered_inertial
jeod::LvlhDerivedState, 34	jeod::LvlhDerivedState, 34
jeod::NedDerivedState, 44	planetary_derived_state.cc, 77
lvlh_derived_state.cc, 73	planetary_derived_state.hh, 77
lvlh_derived_state.hh, 73	PlanetaryDerivedState
lvlh_frame	jeod::PlanetaryDerivedState, 52
jeod::LvlhDerivedState, 34	
lvlh_relative_derived_state.cc, 74	ref_body_angles
lvlh_relative_derived_state.hh, 74	jeod::EulerDerivedState, 29
lvlh_state	reference_name

84 INDEX

jeod::DerivedState, 21 register_frame jeod::LvlhDerivedState, 34 jeod::NedDerivedState, 45 rel_frame jeod::EulerDerivedState, 30 rel_state jeod::EulerDerivedState, 30 jeod::OrbElemDerivedState, 50 jeod::RelativeDerivedState, 61 relative_derived_state.cc, 78 relative_derived_state.hh, 78 RelativeDerivedState jeod::RelativeDerivedState, 57	update jeod::DerivedState, 20 jeod::EulerDerivedState, 28 jeod::LvlhDerivedState, 33 jeod::LvlhRelativeDerivedState, 38 jeod::NedDerivedState, 43 jeod::OrbElemDerivedState, 48 jeod::PlanetaryDerivedState, 53 jeod::RelativeDerivedState, 60 jeod::SolarBetaDerivedState, 66 use_alt_inertial jeod::OrbElemDerivedState, 50 use_alt_pfix jeod::NedDerivedState, 45 jeod::PlanetaryDerivedState, 54
sequence jeod::EulerDerivedState, 30	use_theta_dot_correction jeod::LvlhRelativeDerivedState, 39
set_activation_flag jeod::RelativeDerivedState, 59 set_name jeod::RelativeDerivedState, 59 set_reference_name	veh_wrt_planet jeod::SolarBetaDerivedState, 68
jeod::DerivedState, 20 set_subject_frame jeod::RelativeDerivedState, 59	
set_target_frame jeod::RelativeDerivedState, 60	
set_use_alt_inertial jeod::OrbElemDerivedState, 48	
set_use_alt_pfix jeod::NedDerivedState, 43 jeod::PlanetaryDerivedState, 53	
solar_beta jeod::SolarBetaDerivedState, 67 solar_beta_derived_state.cc, 79	
solar_beta_derived_state.hh, 80 SolarBetaDerivedState jeod::SolarBetaDerivedState, 65	
state jeod::PlanetaryDerivedState, 54 state identifier	
jeod::DerivedState, 21 subject	
jeod::DerivedState, 21 subject_frame jeod::RelativeDerivedState, 62	
subject_frame_name jeod::RelativeDerivedState, 62 sun	
jeod::SolarBetaDerivedState, 67 sun_wrt_planet jeod::SolarBetaDerivedState, 68	
target_frame jeod::RelativeDerivedState, 62 target_frame_name jeod::RelativeDerivedState, 63	
trace ieod::DerivedStateMessages, 25	