ContactModel

5.3

Generated by Doxygen 1.8.14

Contents

1	Mod	lule Index	1
	1.1	Modules	1
2	Nam	nespace Index	3
	2.1	Namespace List	3
3	Hier	rarchical Index	5
	3.1	Class Hierarchy	5
4	Data	a Structure Index	7
	4.1	Data Structures	7
5	File	Index	9
	5.1	File List	9
6	Mod	Jule Documentation	11
	6.1	Models	11
		6.1.1 Detailed Description	11
	6.2	Interactions	12
		6.2.1 Detailed Description	12
	6.3	Contact	13
		6.3.1 Detailed Description	14
7	Nam	nespace Documentation	15
	7.1	jeod Namespace Reference	15
		7.1.1 Detailed Description	16

ii CONTENTS

8	Data	Structi	ire Documen	tation	17
	8.1	jeod::C	ontact Class F	Reference	17
		8.1.1	Detailed Des	cription	18
		8.1.2	Constructor 8	& Destructor Documentation	18
			8.1.2.1 Co	ontact() [1/2]	18
			8.1.2.2 ~0	Contact()	19
			8.1.2.3 Co	ontact() [2/2]	19
		8.1.3	Member Fun	ction Documentation	19
			8.1.3.1 ch	eck_contact()	19
			8.1.3.2 fine	d_interaction()	19
			8.1.3.3 init	tialize_contact()	20
			8.1.3.4 op	erator=()	20
			8.1.3.5 reg	gister_contact() [1/4]	20
			8.1.3.6 reg	gister_contact() [2/4]	21
			8.1.3.7 reg	gister_contact() [3/4]	21
			8.1.3.8 reg	gister_contact() [4/4]	21
			8.1.3.9 reg	gister_interaction()	22
			8.1.3.10 un	ique_pair()	22
		8.1.4	Friends And	Related Function Documentation	22
			8.1.4.1 init	t_attrjeodContact	23
			8.1.4.2 Inp	putProcessor	23
		8.1.5	Field Docum	entation	23
			8.1.5.1 ac	tive	23
			8.1.5.2 co	ntact_limit_factor	23
			8.1.5.3 co	ntact_pairs	24
			8.1.5.4 dy	n_manager	24
			8.1.5.5 pa	ir_interactions	24
	8.2	jeod::C	ontactFacet C	lass Reference	25
		8.2.1	Detailed Des	cription	26
		8.2.2	Constructor 8	& Destructor Documentation	26

CONTENTS

		8.2.2.1	ContactFacet() [1/2]	26
		8.2.2.2	~ContactFacet()	26
		8.2.2.3	ContactFacet() [2/2]	26
	8.2.3	Member	Function Documentation	26
		8.2.3.1	calculate_torque()	27
		8.2.3.2	create_pair() [1/2]	27
		8.2.3.3	create_pair() [2/2]	27
		8.2.3.4	create_vehicle_point()	28
		8.2.3.5	get_name()	28
		8.2.3.6	operator=()	28
		8.2.3.7	set_max_dimension()	28
	8.2.4	Friends A	And Related Function Documentation	29
		8.2.4.1	init_attrjeodContactFacet	29
		8.2.4.2	InputProcessor	29
	8.2.5	Field Do	cumentation	29
		8.2.5.1	active	29
		8.2.5.2	max_dimension	29
		8.2.5.3	normal	30
		8.2.5.4	position	30
		8.2.5.5	surface_type	30
		8.2.5.6	vehicle_body	30
		8.2.5.7	vehicle_point	31
8.3	jeod::C	ontactMe	ssages Class Reference	31
	8.3.1	Detailed	Description	32
	8.3.2	Construc	ctor & Destructor Documentation	32
		8.3.2.1	ContactMessages() [1/2]	32
		8.3.2.2	ContactMessages() [2/2]	32
	8.3.3	Member	Function Documentation	32
		8.3.3.1	operator=()	32
	8.3.4	Friends A	And Related Function Documentation	32

iv CONTENTS

		8.3.4.1	init_attrjeodContactMessages	 	32
		8.3.4.2	InputProcessor	 	32
	8.3.5	Field Doo	cumentation	 	33
		8.3.5.1	initialization_error	 	33
		8.3.5.2	initialization_warns	 	33
		8.3.5.3	pre_initialization_error	 	33
		8.3.5.4	runtime_error	 	34
		8.3.5.5	runtime_inform	 	34
		8.3.5.6	runtime_warns	 	34
8.4	jeod::C	ContactPair	r Class Reference	 	34
	8.4.1	Detailed	Description	 	36
	8.4.2	Construc	ctor & Destructor Documentation	 	36
		8.4.2.1	ContactPair() [1/2]	 	36
		8.4.2.2	~ContactPair()	 	36
		8.4.2.3	ContactPair() [2/2]	 	36
	8.4.3	Member	Function Documentation	 	36
		8.4.3.1	check_tree()	 	36
		8.4.3.2	get_subject()	 	37
		8.4.3.3	get_target()	 	37
		8.4.3.4	in_contact()	 	37
		8.4.3.5	in_range()	 	37
		8.4.3.6	initialize_pair()	 	37
		8.4.3.7	initialize_relstate()	 	38
		8.4.3.8	is_active()	 	38
		8.4.3.9	is_complete()	 	39
		8.4.3.10	operator=()	 	39
	8.4.4	Friends A	And Related Function Documentation	 	39
		8.4.4.1	init_attrjeodContactPair	 	39
		8.4.4.2	InputProcessor	 	39
	8.4.5	Field Doo	cumentation	 	39

CONTENTS

		8.4.5.1	interaction	40
		8.4.5.2	interaction_distance	40
		8.4.5.3	rel_state	40
		8.4.5.4	subject	40
		8.4.5.5	target	41
8.5	jeod::C	ContactPar	rams Class Reference	41
	8.5.1	Detailed	Description	41
	8.5.2	Construc	ctor & Destructor Documentation	42
		8.5.2.1	ContactParams() [1/2]	42
		8.5.2.2	~ContactParams()	42
		8.5.2.3	ContactParams() [2/2]	42
	8.5.3	Member	Function Documentation	42
		8.5.3.1	operator=()	42
	8.5.4	Friends /	And Related Function Documentation	42
		8.5.4.1	init_attrjeodContactParams	42
		8.5.4.2	InputProcessor	43
8.6	jeod::C	ContactSur	face Class Reference	43
	8.6.1	Detailed	Description	44
	8.6.2	Construc	ctor & Destructor Documentation	44
		8.6.2.1	ContactSurface() [1/2]	44
		8.6.2.2	~ContactSurface()	44
		8.6.2.3	ContactSurface() [2/2]	44
	8.6.3	Member	Function Documentation	44
		8.6.3.1	allocate_array()	44
		8.6.3.2	allocate_interaction_facet()	45
		8.6.3.3	collect_forces_torques()	45
		8.6.3.4	operator=()	45
	8.6.4	Friends /	And Related Function Documentation	46
	8.6.4	8.6.4.1	And Related Function Documentation	46 46

vi

	8.6.5	Field Doo	cumentation	'	46
		8.6.5.1	contact_facets		46
		8.6.5.2	contact_force		46
		8.6.5.3	contact_torque		47
		8.6.5.4	facets_size	4	47
8.7	jeod::C	ContactSurf	faceFactory Class Reference	4	47
	8.7.1	Detailed	Description	4	48
	8.7.2	Construc	ctor & Destructor Documentation	'	48
		8.7.2.1	ContactSurfaceFactory() [1/2]	'	48
		8.7.2.2	~ContactSurfaceFactory()	4	49
		8.7.2.3	ContactSurfaceFactory() [2/2]	4	49
	8.7.3	Member	Function Documentation	'	49
		8.7.3.1	add_facet_params()	4	49
		8.7.3.2	create_surface()	4	49
		8.7.3.3	operator=()	!	50
	8.7.4	Friends A	And Related Function Documentation	!	50
		8.7.4.1	init_attrjeodContactSurfaceFactory	!	50
		8.7.4.2	InputProcessor	!	50
	8.7.5	Field Doo	cumentation	!	50
		8.7.5.1	line_contact_facet_factory	!	50
		8.7.5.2	point_contact_facet_factory	!	51
8.8	jeod::C	ContactUtils	s Class Reference	!	51
	8.8.1	Detailed	Description	!	51
	8.8.2	Member	Function Documentation	!	51
		8.8.2.1	create_relstate_name()	!	51
		8.8.2.2	dist_line_segments()	!	52
8.9	jeod::L	ineContac	etFacet Class Reference	!	53
	8.9.1	Detailed	Description	!	54
	8.9.2	Construc	ctor & Destructor Documentation	!	54
		8.9.2.1	LineContactFacet() [1/2]	!	54

CONTENTS vii

		8.9.2.2	~LineContactFacet()	54
		8.9.2.3	LineContactFacet() [2/2]	54
	8.9.3	Member	Function Documentation	54
		8.9.3.1	calculate_contact_point()	54
		8.9.3.2	calculate_torque()	55
		8.9.3.3	create_pair() [1/2]	55
		8.9.3.4	create_pair() [2/2]	56
		8.9.3.5	operator=()	56
		8.9.3.6	set_max_dimension()	56
	8.9.4	Friends A	And Related Function Documentation	57
		8.9.4.1	init_attrjeodLineContactFacet	57
		8.9.4.2	InputProcessor	57
	8.9.5	Field Doo	cumentation	57
		8.9.5.1	length	57
8.10	jeod::Li	neContact	tFacetFactory Class Reference	57
	8.10.1	Detailed	Description	58
	8.10.2	Construc	tor & Destructor Documentation	58
		8.10.2.1	LineContactFacetFactory() [1/2]	58
		8.10.2.2	~LineContactFacetFactory()	58
		8.10.2.3	LineContactFacetFactory() [2/2]	58
	8.10.3	Member	Function Documentation	59
		8.10.3.1	create_facet()	59
		8.10.3.2	is_correct_factory()	59
		8.10.3.3	operator=()	60
	8.10.4	Friends A	And Related Function Documentation	60
		8.10.4.1	init_attrjeodLineContactFacetFactory	60
		8.10.4.2	InputProcessor	60
8.11	jeod::Li	neContac	tPair Class Reference	60
	8.11.1	Detailed	Description	61
	8.11.2	Construc	tor & Destructor Documentation	61

viii CONTENTS

		8.11.2.1 LineContactPair() [1/2]	61
		8.11.2.2 ~LineContactPair()	61
		8.11.2.3 LineContactPair() [2/2]	62
	8.11.3	Member Function Documentation	62
		8.11.3.1 in_contact()	62
		8.11.3.2 initialize_pair()	62
		8.11.3.3 operator=()	63
	8.11.4	Friends And Related Function Documentation	63
		8.11.4.1 init_attrjeodLineContactPair	63
		8.11.4.2 InputProcessor	63
	8.11.5	Field Documentation	63
		8.11.5.1 line_subject	63
		8.11.5.2 line_target	63
8.12	jeod::Li	nePointContactPair Class Reference	64
	8.12.1	Detailed Description	64
	8.12.2	Constructor & Destructor Documentation	64
		8.12.2.1 LinePointContactPair() [1/2]	65
		8.12.2.2 ~LinePointContactPair()	65
		8.12.2.3 LinePointContactPair() [2/2]	65
	8.12.3	Member Function Documentation	65
		8.12.3.1 in_contact()	65
		8.12.3.2 initialize_pair()	65
		8.12.3.3 operator=()	66
	8.12.4	Friends And Related Function Documentation	66
		8.12.4.1 init_attrjeodLinePointContactPair	66
		8.12.4.2 InputProcessor	66
	8.12.5	Field Documentation	66
		8.12.5.1 line_subject	67
		8.12.5.2 point_target	67
8.13	jeod::Pa	irInteraction Class Reference	67

CONTENTS

	8.13.1	Detailed Description	68
	8.13.2	Constructor & Destructor Documentation	68
		8.13.2.1 PairInteraction() [1/2]	68
		8.13.2.2 ~PairInteraction()	68
		8.13.2.3 PairInteraction() [2/2]	69
	8.13.3	Member Function Documentation	69
		8.13.3.1 calculate_forces()	69
		8.13.3.2 is_correct_interaction()	69
		8.13.3.3 operator=()	70
	8.13.4	Friends And Related Function Documentation	70
		8.13.4.1 init_attrjeodPairInteraction	70
		8.13.4.2 InputProcessor	70
	8.13.5	Field Documentation	70
		8.13.5.1 friction_mag	70
		8.13.5.2 params_1	71
		8.13.5.3 params_2	71
8.14	jeod::P	ointContactFacet Class Reference	71
	8.14.1	Detailed Description	72
	8.14.2	Constructor & Destructor Documentation	72
		8.14.2.1 PointContactFacet() [1/2]	73
		8.14.2.2 ~PointContactFacet()	73
		8.14.2.3 PointContactFacet() [2/2]	73
	8.14.3	Member Function Documentation	73
		8.14.3.1 calculate_contact_point()	73
		8.14.3.2 calculate_torque()	74
		8.14.3.3 create_pair() [1/2]	74
		8.14.3.4 create_pair() [2/2]	74
		8.14.3.5 operator=()	75
		8.14.3.6 set_max_dimension()	75
	8.14.4	Friends And Related Function Documentation	75

CONTENTS

		8.14.4.1 init_attrjeodPointContactFacet	75
		8.14.4.2 InputProcessor	76
	8.14.5	Field Documentation	76
		8.14.5.1 contact_point	76
		8.14.5.2 radius	76
8.15	jeod::P	pintContactFacetFactory Class Reference	77
	8.15.1	Detailed Description	77
	8.15.2	Constructor & Destructor Documentation	77
		8.15.2.1 PointContactFacetFactory() [1/2]	77
		8.15.2.2 ~PointContactFacetFactory()	78
		8.15.2.3 PointContactFacetFactory() [2/2]	78
	8.15.3	Member Function Documentation	78
		8.15.3.1 create_facet()	78
		8.15.3.2 is_correct_factory()	78
		8.15.3.3 operator=()	79
	8.15.4	Friends And Related Function Documentation	79
		8.15.4.1 init_attrjeodPointContactFacetFactory	79
		8.15.4.2 InputProcessor	79
8.16	jeod::P	pintContactPair Class Reference	79
	8.16.1	Detailed Description	80
	8.16.2	Constructor & Destructor Documentation	80
		8.16.2.1 PointContactPair() [1/2]	80
		8.16.2.2 ~PointContactPair()	80
		8.16.2.3 PointContactPair() [2/2]	81
	8.16.3	Member Function Documentation	81
		8.16.3.1 in_contact()	81
		8.16.3.2 initialize_pair()	81
		8.16.3.3 operator=()	82
	8.16.4	Friends And Related Function Documentation	82
		8.16.4.1 init_attrjeodPointContactPair	82

CONTENTS xi

		8.16.4.2 I	nputProcessor	 	 	 	82
	8.16.5	Field Docu	nentation	 	 	 	82
		8.16.5.1 p	oint_subject	 	 	 	82
		8.16.5.2 p	oint_target	 	 	 	82
8.17	jeod::S	pringPairInte	raction Class Reference	 	 	 	83
	8.17.1	Detailed De	scription	 	 	 	83
	8.17.2	Constructo	& Destructor Documentation	 	 	 	83
		8.17.2.1	pringPairInteraction() [1/2]	 	 	 	84
		8.17.2.2	SpringPairInteraction()	 	 	 	84
		8.17.2.3	pringPairInteraction() [2/2]	 	 	 	84
	8.17.3	Member Fu	nction Documentation	 	 	 	84
		8.17.3.1	alculate_forces()	 	 	 	84
		8.17.3.2	perator=()	 	 	 	85
	8.17.4	Friends An	Related Function Documentation	 	 	 	85
		8.17.4.1 i	nit_attrjeodSpringPairInteraction	 	 	 	85
		8.17.4.2 I	nputProcessor	 	 	 	85
	8.17.5	Field Docu	nentation	 	 	 	85
		8.17.5.1	amping_b	 	 	 	85
		8.17.5.2 r	nu	 	 	 	85
		8.17.5.3	pring_k	 	 	 	86

xii CONTENTS

9	File I	Documentation	87
	9.1	class_declarations.hh File Reference	87
		9.1.1 Detailed Description	87
	9.2	contact.cc File Reference	87
		9.2.1 Detailed Description	88
	9.3	contact.hh File Reference	88
		9.3.1 Detailed Description	88
	9.4	contact_facet.cc File Reference	88
		9.4.1 Detailed Description	89
	9.5	contact_facet.hh File Reference	89
		9.5.1 Detailed Description	89
	9.6	contact_messages.cc File Reference	89
		9.6.1 Detailed Description	90
		9.6.2 Macro Definition Documentation	90
		9.6.2.1 MAKE_CONTACT_MESSAGE_CODE	90
	9.7	contact_messages.hh File Reference	90
		9.7.1 Detailed Description	91
	9.8	contact_pair.cc File Reference	91
		9.8.1 Detailed Description	91
	9.9	contact_pair.hh File Reference	91
		9.9.1 Detailed Description	92
	9.10	contact_params.cc File Reference	92
		9.10.1 Detailed Description	92
	9.11	contact_params.hh File Reference	92
		9.11.1 Detailed Description	92
	9.12	contact_surface.cc File Reference	93
		9.12.1 Detailed Description	93
	9.13	contact_surface.hh File Reference	93
		9.13.1 Detailed Description	94
	9.14	contact_surface_factory.cc File Reference	94

CONTENTS xiii

	9.14.1 Detailed Description	94
9.15	contact_surface_factory.hh File Reference	94
	9.15.1 Detailed Description	95
9.16	contact_utils.hh File Reference	95
	9.16.1 Detailed Description	95
9.17	contact_utils_inline.hh File Reference	95
	9.17.1 Detailed Description	96
9.18	line_contact_facet.cc File Reference	96
	9.18.1 Detailed Description	96
9.19	line_contact_facet.hh File Reference	96
	9.19.1 Detailed Description	97
9.20	line_contact_facet_factory.cc File Reference	97
	9.20.1 Detailed Description	97
9.21	line_contact_facet_factory.hh File Reference	97
	9.21.1 Detailed Description	98
9.22	line_contact_pair.cc File Reference	98
	9.22.1 Detailed Description	98
9.23	line_contact_pair.hh File Reference	98
	9.23.1 Detailed Description	99
9.24	line_point_contact_pair.cc File Reference	99
	9.24.1 Detailed Description	99
9.25	line_point_contact_pair.hh File Reference	99
	9.25.1 Detailed Description	100
9.26	pair_interaction.cc File Reference	100
	9.26.1 Detailed Description	100
9.27	pair_interaction.hh File Reference	100
	9.27.1 Detailed Description	101
9.28	point_contact_facet.cc File Reference	101
	9.28.1 Detailed Description	101
9.29	point_contact_facet.hh File Reference	102
	9.29.1 Detailed Description	102
9.30	point_contact_facet_factory.cc File Reference	102
	9.30.1 Detailed Description	103
9.31	point_contact_facet_factory.hh File Reference	103
	9.31.1 Detailed Description	103
9.32	point_contact_pair.cc File Reference	103
	9.32.1 Detailed Description	104
9.33	point_contact_pair.hh File Reference	104
	9.33.1 Detailed Description	104
9.34	spring_pair_interaction.cc File Reference	104
	9.34.1 Detailed Description	105
9.35	spring_pair_interaction.hh File Reference	105
	9.35.1 Detailed Description	105

•	
	CONTENTS
ΧΪV	CONTENTS

Index 107

Module Index

1.1 Modules

Here is a list of all modules:

Models				 					 											 		11
Interactions																						12
Contact			 																 			13

2 Module Index

Namespace Index

2.1	Namespace	List

riere is a list of all flamespaces with brief t	descriptions.	
jeod		

4 Namespace Index

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

eod::Contact	17
eod::ContactMessages	3
eod::ContactPair	34
jeod::LineContactPair	60
jeod::LinePointContactPair	64
jeod::PointContactPair	79
eod::ContactUtils	5
acetParams	
jeod::ContactParams	4
nteractionFacet	
jeod::ContactFacet	2
jeod::PointContactFacet	7
jeod::LineContactFacet	50
nteractionFacetFactory	
jeod::LineContactFacetFactory	57
jeod::PointContactFacetFactory	7
nteractionSurface	
jeod::ContactSurface	43
nteractionSurfaceFactory	
jeod::ContactSurfaceFactory	
eod::PairInteraction	67
jeod::SpringPairInteraction	83

6 Hierarchical Index

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::Contact	
An base contact class for use in the surface model	17
jeod::ContactFacet	
An contact interaction specific facet for use in the surface model	25
jeod::ContactMessages	
Messages associated with use of the contact model	31
jeod::ContactPair	
An base contact pair class for use in the contact model	34
jeod::ContactParams	
A base class for all contact parameters used in the surface model	41
jeod::ContactSurface	
The contact specific interaction surface, for use with the surface model	43
jeod::ContactSurfaceFactory	
The surface factory that creates an contact specific surface from a general surface	47
jeod::ContactUtils	
Utility string and math functions for the contact model	51
jeod::LineContactFacet	
The contact facet based on the distance to a single point, specifically the vehicle point	53
jeod::LineContactFacetFactory	
Creates a PointContactFacet from an InteractionFacet	57
jeod::LineContactPair	
An point to point contact pair for use in the contact model	60
jeod::LinePointContactPair	
An point to point contact pair for use in the contact model	64
jeod::PairInteraction	
Simple spring contact parameters	67
jeod::PointContactFacet	_
The contact facet based on the distance to a single point, specifically the vehicle point	71
jeod::PointContactFacetFactory	
Creates a PointContactFacet from an InteractionFacet	77
jeod::PointContactPair	
An point to point contact pair for use in the contact model	79
jeod::SpringPairInteraction	
Simple enring contact parameters	Q.

8 Data Structure Index

File Index

5.1 File List

Here is a list of all files with brief descriptions:

class_declarations.hh	
Forward declaration of classes defined in the contact model	87
contact.cc	
Base Contact for use with contact interaction model	87
contact.hh	
(Base class to for the contact manager for use with contact interaction model)	88
contact_facet.cc	
Define ContactFacet::create_vehicle_point	88
contact_facet.hh	
Individual facets for use with contact interaction models	89
contact_messages.cc	
Implement contact_messages	89
contact_messages.hh	
Contact message for message handling	90
contact_pair.cc	
ContactPair class for use with contact interaction model	91
contact_pair.hh	91
Base class for pair of contact facets for use with contact interaction model	9
Contact_parameters for use in the surface model	92
contact_params.hh	32
A class for contact facet parameters, used to create interaction facets for contact in the	
InteractionSurfaceFactorys	92
contact_surface.cc	-
Vehicle surface model for the contact interaction models	93
contact_surface.hh	
Vehicle surface model for contact	93
contact surface factory.cc	
Factory that creates an contact surface, from a surface model	94
contact_surface_factory.hh	
Factory that creates an contact interaction surface from a surface model	94
contact_utils.hh	
This Model is used for utility rotines	95
contact_utils_inline.hh	
Define ContactUtils::create_relstate_name, ContactUtils::copy_const_char_to_char	95

10 File Index

line_contact_facet.cc	
Define LineContactFacet functions	96
line_contact_facet.hh	
The contact facet based on the distance to a line segment centered on the vehicle point	96
line_contact_facet_factory.cc	
Factory that creates a LineContactFacetFactory from a Cylinder facet and a ContactParams	
object	97
line_contact_facet_factory.hh	
Creates a line contact facet from an cylinder facet	97
line_contact_pair.cc	
LineContactPair class for use with contact interaction model	98
line_contact_pair.hh	
Class for a pair of line contact facets for use with contact interaction model	98
line_point_contact_pair.cc	
LinePointContactPair class for use with contact interaction model	99
line_point_contact_pair.hh	
Class for a pair of a line contact facet and a point contact facet for use with contact interaction	
model	99
pair_interaction.cc	
A class to define the interaction type for a pair of contact facets	100
pair_interaction.hh	
A class to define the interaction type for a pair of contact facets	100
point_contact_facet.cc	
Define PointContactFacet functions	101
point_contact_facet.hh	
The contact facet based on the distance to a single point, specifically the vehicle point	102
point_contact_facet_factory.cc	
Factory that creates a PointContactFacet from a FlatPlateCircular facet and a ContactParams	
object	102
point_contact_facet_factory.hh	
Creates a point contact facet from an circular flat plate facet	103
point_contact_pair.cc	
ContactPair class for use with contact interaction model	103
point_contact_pair.hh	
Class for a pair of point contact facets for use with contact interaction model	104
spring_pair_interaction.cc	
Spring pair interaction for use in the contact model	104
spring_pair_interaction.hh	
A class for pair interactions based on a simple spring	105

Module Documentation

6.1 Models

Modules

Interactions

6.1.1 Detailed Description

12 Module Documentation

6.2 Interactions

Modules

Contact

6.2.1 Detailed Description

6.3 Contact 13

6.3 Contact

Files

· file class declarations.hh

Forward declaration of classes defined in the contact model.

· file contact.hh

(Base class to for the contact manager for use with contact interaction model)

· file contact facet.hh

Individual facets for use with contact interaction models.

· file contact_messages.hh

Contact message for message handling.

· file contact pair.hh

Base class for pair of contact facets for use with contact interaction model.

file contact_params.hh

A class for contact facet parameters, used to create interaction facets for contact in the InteractionSurfaceFactorys.

file contact_surface.hh

Vehicle surface model for contact.

· file contact_surface_factory.hh

Factory that creates an contact interaction surface from a surface model.

· file contact utils.hh

This Model is used for utility rotines.

· file contact utils inline.hh

Define ContactUtils::create_relstate_name, ContactUtils::copy_const_char_to_char.

file line_contact_facet.hh

The contact facet based on the distance to a line segment centered on the vehicle point.

file line_contact_facet_factory.hh

Creates a line contact facet from an cylinder facet.

• file line_contact_pair.hh

Class for a pair of line contact facets for use with contact interaction model.

file line_point_contact_pair.hh

Class for a pair of a line contact facet and a point contact facet for use with contact interaction model.

• file pair_interaction.hh

A class to define the interaction type for a pair of contact facets.

file point_contact_facet.hh

The contact facet based on the distance to a single point, specifically the vehicle point.

· file point contact facet factory.hh

Creates a point contact facet from an circular flat plate facet.

• file point_contact_pair.hh

Class for a pair of point contact facets for use with contact interaction model.

file spring_pair_interaction.hh

A class for pair interactions based on a simple spring.

file contact.cc

Base Contact for use with contact interaction model.

• file contact_facet.cc

Define ContactFacet::create_vehicle_point.

file contact_messages.cc

Implement contact_messages.

file contact_pair.cc

ContactPair class for use with contact interaction model.

14 Module Documentation

· file contact_params.cc

contact parameters for use in the surface model

· file contact surface.cc

Vehicle surface model for the contact interaction models.

• file contact_surface_factory.cc

Factory that creates an contact surface, from a surface model.

• file line_contact_facet.cc

Define LineContactFacet functions.

• file line_contact_facet_factory.cc

Factory that creates a LineContactFacetFactory from a Cylinder facet and a ContactParams object.

• file line_contact_pair.cc

LineContactPair class for use with contact interaction model.

• file line_point_contact_pair.cc

LinePointContactPair class for use with contact interaction model.

• file pair_interaction.cc

A class to define the interaction type for a pair of contact facets.

• file point_contact_facet.cc

Define PointContactFacet functions.

• file point_contact_facet_factory.cc

Factory that creates a PointContactFacet from a FlatPlateCircular facet and a ContactParams object.

• file point_contact_pair.cc

ContactPair class for use with contact interaction model.

• file spring_pair_interaction.cc

spring pair interaction for use in the contact model

Namespaces

· jeod

Namespace jeod.

6.3.1 Detailed Description

Namespace Documentation

7.1 jeod Namespace Reference

Namespace jeod.

Data Structures

· class Contact

An base contact class for use in the surface model.

class ContactFacet

An contact interaction specific facet for use in the surface model.

class ContactMessages

Messages associated with use of the contact model.

class ContactPair

An base contact pair class for use in the contact model.

· class ContactParams

A base class for all contact parameters used in the surface model.

· class ContactSurface

The contact specific interaction surface, for use with the surface model.

· class ContactSurfaceFactory

The surface factory that creates an contact specific surface from a general surface.

· class ContactUtils

Utility string and math functions for the contact model.

class LineContactFacet

The contact facet based on the distance to a single point, specifically the vehicle point.

class LineContactFacetFactory

Creates a PointContactFacet from an InteractionFacet.

· class LineContactPair

An point to point contact pair for use in the contact model.

· class LinePointContactPair

An point to point contact pair for use in the contact model.

class PairInteraction

Simple spring contact parameters.

· class PointContactFacet

The contact facet based on the distance to a single point, specifically the vehicle point.

• class PointContactFacetFactory

Creates a PointContactFacet from an InteractionFacet.

• class PointContactPair

An point to point contact pair for use in the contact model.

• class SpringPairInteraction

Simple spring contact parameters.

7.1.1 Detailed Description

Namespace jeod.

Data Structure Documentation

8.1 jeod::Contact Class Reference

An base contact class for use in the surface model.

```
#include <contact.hh>
```

Public Member Functions

· Contact ()

Default Constructor.

virtual ∼Contact ()

Destructor.

- Contact & operator= (const Contact &)=delete
- Contact (const Contact &)=delete
- void register_contact (ContactFacet *facet)

Register one ContactFacet with all inclusive interactions with other registered ContactFacets.

void register_contact (ContactFacet **facets, unsigned int n_facets)

Register an array of ContactFacets with all inclusive interactions with other registered ContactFacets.

void register_contact (ContactFacet *facet1, ContactFacet *facet2)

Register two facets as a pair.

void register_contact (ContactFacet **facets1, unsigned int n_facets1, ContactFacet **facets2, unsigned int n_facets2)

Regiser to arrays of facets and create specific pairs between all of them.

• void register_interaction (PairInteraction *interaction)

Register a pair interaction.

virtual PairInteraction * find_interaction (ContactParams *params_1, ContactParams *params_2)

find a PairInteraction baced on a set of ContactParams.

void initialize_contact (DynManager *manager)

Initialize ContactFacets and the mananger by cleaning up the pair list.

• bool unique_pair (const ContactFacet *facet_1, const ContactFacet *facet_2)

Check to see if a pair of facets already exists.

void check_contact ()

iterate through contact pairs list then call the appropriate contact resolution functions

Data Fields

• bool active {true}

toggles contact on and off, true=on false=off

double contact_limit_factor {}

factor determines if contact is limited by a muliple of the maximum dimensions of the facets in a pair.

Protected Attributes

DynManager * dyn_manager {}

Pointer to the dyn_manager so relstates and be successfully initialized.

JeodPointerList< ContactPair >::type contact_pairs

list of all possible pairings of contact facets registered with this contact class or derived class

JeodPointerList< PairInteraction >::type pair interactions

list of all possible pair interaction types

Friends

- · class InputProcessor
- void init_attrjeod__Contact ()

8.1.1 Detailed Description

An base contact class for use in the surface model.

Definition at line 91 of file contact.hh.

8.1.2 Constructor & Destructor Documentation

```
8.1.2.1 Contact() [1/2] jeod::Contact::Contact ( )
```

Default Constructor.

Definition at line 50 of file contact.cc.

References contact pairs, and pair interactions.

8.1.2.2 \sim Contact()

```
jeod::Contact::~Contact ( ) [virtual]
```

Destructor.

Definition at line 62 of file contact.cc.

References contact_pairs, and pair_interactions.

8.1.2.3 Contact() [2/2]

8.1.3 Member Function Documentation

8.1.3.1 check_contact()

```
void jeod::Contact::check_contact ( )
```

iterate through contact pairs list then call the appropriate contact resolution functions

Definition at line 86 of file contact.cc.

References active, and contact_pairs.

8.1.3.2 find_interaction()

find a PairInteraction baced on a set of ContactParams.

Returns

pointer to a PairInteraction

Parameters

in	params⊷	ContactParams from a ContactFacet
	_1	
in	params⇔	ContactParams from a ContactFacet
Generat	ed by Doxygen	

Definition at line 251 of file contact.cc.

References pair_interactions.

Referenced by jeod::LineContactFacet::create_pair(), and jeod::PointContactFacet::create_pair().

8.1.3.3 initialize_contact()

Initialize ContactFacets and the mananger by cleaning up the pair list.

Parameters

in,out	manager	Dynamics Manager
--------	---------	------------------

Definition at line 106 of file contact.cc.

References contact_pairs, jeod::ContactFacet::create_pair(), dyn_manager, jeod::ContactPair::get_subject(), jeod::ContactPair::initialize_relstate(), and unique_pair().

8.1.3.4 operator=()

8.1.3.5 register_contact() [1/4]

Register one ContactFacet with all inclusive interactions with other registered ContactFacets.

Parameters

```
in, out facet ContactFacet
```

Definition at line 167 of file contact.cc.

References contact pairs, and jeod::ContactFacet::create pair().

Referenced by register_contact().

Register an array of ContactFacets with all inclusive interactions with other registered ContactFacets.

Parameters

in,out	facets	array of ContactFacets
in	nFacets	number of ContactFacets in array

unsigned int nFacets)

Definition at line 184 of file contact.cc.

References register_contact().

```
8.1.3.7 register_contact() [3/4]
```

Register two facets as a pair.

Parameters

in,out	facet1	Contact Facet 1
in,out	facet2	Contact Facet 2

Definition at line 197 of file contact.cc.

References contact_pairs, jeod::ContactFacet::create_pair(), and dyn_manager.

```
8.1.3.8 register_contact() [4/4]
```

Regiser to arrays of facets and create specific pairs between all of them.

Parameters

in,out	facets1	array of ContactFacets
in	nFacets1	number of ContactFacets in array
Generated by Do	tacets2	array of ContactFacets
in	nFacets2	number of ContactFacets in array

Definition at line 220 of file contact.cc.

References register_contact().

8.1.3.9 register_interaction()

Register a pair interaction.

Parameters

in	interaction	PairInteraction to add to list
----	-------------	--------------------------------

Definition at line 240 of file contact.cc.

References pair_interactions.

8.1.3.10 unique_pair()

Check to see if a pair of facets already exists.

Returns

bool

Parameters

in,out	facet←	ContactFacet
	_1	
in,out	facet←	ContactFacet
	_2	

Definition at line 146 of file contact.cc.

References contact_pairs.

Referenced by initialize_contact().

8.1.4 Friends And Related Function Documentation

```
8.1.4.1 init_attrjeod__Contact
```

```
void init_attrjeod__Contact ( ) [friend]
```

8.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 93 of file contact.hh.

8.1.5 Field Documentation

8.1.5.1 active

```
bool jeod::Contact::active {true}
```

toggles contact on and off, true=on false=off

trick_units(-)

Definition at line 97 of file contact.hh.

Referenced by check_contact().

8.1.5.2 contact_limit_factor

```
double jeod::Contact::contact_limit_factor {}
```

factor determines if contact is limited by a muliple of the maximum dimensions of the facets in a pair.

trick_units(-)

Definition at line 103 of file contact.hh.

Referenced by jeod::LineContactFacet::create_pair(), and jeod::PointContactFacet::create_pair().

8.1.5.3 contact_pairs

```
JeodPointerList<ContactPair>::type jeod::Contact::contact_pairs [protected]
```

list of all possible pairings of contact facets registered with this contact class or derived class

```
trick_io(**)
```

Definition at line 158 of file contact.hh.

Referenced by check_contact(), Contact(), initialize_contact(), register_contact(), unique_pair(), and ~Contact().

8.1.5.4 dyn_manager

```
DynManager* jeod::Contact::dyn_manager {} [protected]
```

Pointer to the dyn_manager so relstates and be successfully initialized.

```
trick_units(-)
```

Definition at line 152 of file contact.hh.

Referenced by initialize_contact(), and register_contact().

8.1.5.5 pair_interactions

```
JeodPointerList<PairInteraction>::type jeod::Contact::pair_interactions [protected]
```

list of all possible pair interaction types

```
trick_io(**)
```

Definition at line 163 of file contact.hh.

Referenced by Contact(), find_interaction(), register_interaction(), and ~Contact().

The documentation for this class was generated from the following files:


- · contact.hh
- contact.cc

8.2 jeod::ContactFacet Class Reference

An contact interaction specific facet for use in the surface model.

```
#include <contact_facet.hh>
```

Inheritance diagram for jeod::ContactFacet:



Public Member Functions

- ContactFacet ()=default
- ContactFacet () override=default
- ContactFacet & operator= (const ContactFacet &)=delete
- ContactFacet (const ContactFacet &)=delete
- void create_vehicle_point ()

Create a vehicle point to track the state information of the contact facet.

• virtual void set max dimension ()=0

Calculate the max dimension of the facet for range limit determination.

• std::string get_name () const

Accessor for name.

virtual void calculate_torque (double *tmp_force)=0

Calculate the torque acting on the facet in the vehicle structural frame.

virtual ContactPair * create_pair ()=0

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

• virtual ContactPair * create_pair (ContactFacet *target, Contact *contact)=0

Overloaded functions that creates a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

Data Fields

bool active {true}

toggles this contact facet on and off, true=on false=off

ContactParams * surface type {}

Stores the name of surface material that the facet is constructed of.

DynBody * vehicle_body {}

DynBody associated with this facet for structural frame information.

double max_dimension {}

maximum dimension of the contact facet for use in limiting pair in_contact calls

• double position [3] {}

position of the facet in vehicle structural frame.

double normal [3] {}

normal of the facet relative to the vehicle structural frame.

const BodyRefFrame * vehicle_point {}

Vehicle point for relstate calculations.

Friends

- · class InputProcessor
- void init_attrjeod__ContactFacet ()

8.2.1 Detailed Description

An contact interaction specific facet for use in the surface model.

Definition at line 85 of file contact_facet.hh.

8.2.2 Constructor & Destructor Documentation

8.2.3 Member Function Documentation

8.2.3.1 calculate_torque()

Calculate the torque acting on the facet in the vehicle structural frame.

In: N force from one contact interaction.

Implemented in jeod::PointContactFacet, and jeod::LineContactFacet.

Referenced by jeod::SpringPairInteraction::calculate_forces().

```
8.2.3.2 create_pair() [1/2]
virtual ContactPair* jeod::ContactFacet::create_pair ( ) [pure virtual]
```

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

This function is called to create a pair that only contains a subject. Return: - ContactPair that was created

 $Implemented\ in\ jeod:: Point Contact Facet,\ and\ jeod:: Line Contact Facet.$

Referenced by jeod::Contact::initialize_contact(), and jeod::Contact::register_contact().

```
8.2.3.3 create_pair() [2/2]
```

Overloaded functions that creates a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

This function is called when a subject and target are known. Return: — ContactPair that was created InOut: — target ContactFacet In: — Contact object used to find the pair interaction

Implemented in jeod::PointContactFacet, and jeod::LineContactFacet.

8.2.3.4 create_vehicle_point()

```
void jeod::ContactFacet::create_vehicle_point ( )
```

Create a vehicle point to track the state information of the contact facet.

Create a vehicle point from the base facet position and orientation and store the created vehicle point in the contact facet.

Definition at line 50 of file contact_facet.cc.

References get_name(), normal, position, vehicle_body, and vehicle_point.

Referenced by jeod::LineContactFacetFactory::create_facet(), and jeod::PointContactFacetFactory::create_facet().

8.2.3.5 get_name()

```
std::string jeod::ContactFacet::get_name ( ) const [inline]
```

Accessor for name.

Returns

Point name

Definition at line 173 of file contact_facet.hh.

Referenced by create_vehicle_point().

8.2.3.6 operator=()

8.2.3.7 set_max_dimension()

```
virtual void jeod::ContactFacet::set_max_dimension ( ) [pure virtual]
```

Calculate the max dimension of the facet for range limit determination.

Implemented in jeod::PointContactFacet, and jeod::LineContactFacet.

8.2.4 Friends And Related Function Documentation

8.2.4.1 init_attrjeod__ContactFacet

```
void init_attrjeod__ContactFacet ( ) [friend]
```

8.2.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 87 of file contact_facet.hh.

8.2.5 Field Documentation

8.2.5.1 active

```
bool jeod::ContactFacet::active {true}
```

toggles this contact facet on and off, true=on false=off

trick_units(-)

Definition at line 91 of file contact_facet.hh.

Referenced by jeod::ContactPair::is_active().

8.2.5.2 max_dimension

```
double jeod::ContactFacet::max_dimension {}
```

maximum dimension of the contact facet for use in limiting pair in_contact calls

trick_units(m)

Definition at line 108 of file contact_facet.hh.

Referenced by jeod::LineContactFacet::create_pair(), jeod::PointContactFacet::create_pair(), jeod::LineContact Facet::set_max_dimension(), and jeod::PointContactFacet::set_max_dimension().

8.2.5.3 normal

```
double jeod::ContactFacet::normal[3] {}
```

normal of the facet relative to the vehicle structural frame.

trick_units(-)

Definition at line 118 of file contact_facet.hh.

Referenced by jeod::LineContactFacetFactory::create_facet(), jeod::PointContactFacetFactory::create_facet(), and create_vehicle_point().

8.2.5.4 position

```
double jeod::ContactFacet::position[3] {}
```

position of the facet in vehicle structural frame.

trick units(m)

Definition at line 113 of file contact facet.hh.

Referenced by jeod::LineContactFacetFactory::create_facet(), jeod::PointContactFacetFactory::create_facet(), and create vehicle point().

8.2.5.5 surface_type

```
ContactParams* jeod::ContactFacet::surface_type {}
```

Stores the name of surface material that the facet is constructed of.

This information is used to deturmine the contact parameters used when pairs are constructed.trick_units(-)

Definition at line 98 of file contact facet.hh.

8.2.5.6 vehicle_body

```
DynBody* jeod::ContactFacet::vehicle_body {}
```

DynBody associated with this facet for structural frame information.

trick_units(-)

Definition at line 103 of file contact_facet.hh.

Referenced by jeod::SpringPairInteraction::calculate_forces(), jeod::LineContactFacet::calculate_torque(), jeod::PointContactFacet::calculate_torque(), jeod::LineContactFacetFactory::create_facet(), jeod::PointContactFacet Factory::create_facet(), create_vehicle_point(), and jeod::ContactPair::initialize_relstate().

8.2.5.7 vehicle_point

```
const BodyRefFrame* jeod::ContactFacet::vehicle_point {}
```

Vehicle point for relstate calculations.

```
trick_units(-)
```

Definition at line 123 of file contact_facet.hh.

Referenced by jeod::SpringPairInteraction::calculate_forces(), jeod::LineContactFacet::calculate_torque(), jeod::⇔ PointContactFacet::calculate_torque(), create_vehicle_point(), jeod::PointContactPair::initialize_pair(), jeod::Line⇔ ContactPair::initialize_pair(), and jeod::LinePointContactPair::initialize_pair().

The documentation for this class was generated from the following files:

- · contact_facet.hh
- · contact_facet.cc

8.3 jeod::ContactMessages Class Reference

Messages associated with use of the contact model.

```
#include <contact messages.hh>
```

Public Member Functions

- ContactMessages ()=delete
- ContactMessages (const ContactMessages &rhs)=delete
- ContactMessages & operator= (const ContactMessages &rhs)=delete

Static Public Attributes

- static const char * initialization_error = "interactions/contact" "initialization_error"
 Associated with errors during initialization of the contact model.
- static const char * runtime_error = "interactions/contact" "runtime_error"

Associated with errors during the runtime of the contact model.

• static const char * pre_initialization_error = "interactions/contact" "pre_initialization_error"

Associated with errors during the setup of the system, before runtime.

• static const char * initialization_warns = "interactions/contact" "initialization_warns"

Associated with warning during initialization of the contact model.

static const char * runtime_warns = "interactions/contact" "runtime_warns"

Associated with warnings given at runtime.

• static const char * runtime_inform = "interactions/contact" "runtime_inform"

Associated with information given at runtime.

Friends

- class InputProcessor
- void init_attrjeod__ContactMessages ()

8.3.1 Detailed Description

Messages associated with use of the contact model.

Definition at line 85 of file contact_messages.hh.

8.3.2 Constructor & Destructor Documentation

8.3.3 Member Function Documentation

8.3.3.1 operator=()

8.3.4 Friends And Related Function Documentation

8.3.4.1 init_attrjeod__ContactMessages

```
\label{lem:contactMessages} \mbox{ ( ) } \mbox{ [friend]}
```

8.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 87 of file contact_messages.hh.

8.3.5 Field Documentation

8.3.5.1 initialization_error

```
char const * jeod::ContactMessages::initialization_error = "interactions/contact" "initialization←
_error" [static]
```

Associated with errors during initialization of the contact model.

trick_units(-)

Definition at line 95 of file contact_messages.hh.

Referenced by jeod::ContactSurface::allocate_array(), jeod::ContactSurface::allocate_interaction_facet(), jeod::ContactSurface::allocate_interaction_facet(), jeod::ContactFacetFactory::create_facet(), and jeod::Contact SurfaceFactory::create_surface().

8.3.5.2 initialization_warns

```
char const * jeod::ContactMessages::initialization_warns = "interactions/contact" "initialization
_warns" [static]
```

Associated with warning during initialization of the contact model.

trick_units(-)

Definition at line 110 of file contact_messages.hh.

Referenced by jeod::LineContactFacet::create_pair(), and jeod::PointContactFacet::create_pair().

8.3.5.3 pre_initialization_error

Associated with errors during the setup of the system, before runtime.

trick_units(-)

Definition at line 103 of file contact_messages.hh.

Referenced by jeod::ContactSurfaceFactory::add_facet_params().

8.3.5.4 runtime_error

char const * jeod::ContactMessages::runtime_error = "interactions/contact" "runtime_error"
[static]

Associated with errors during the runtime of the contact model.

trick_units(-)

Definition at line 99 of file contact messages.hh.

8.3.5.5 runtime_inform

char const * jeod::ContactMessages::runtime_inform = "interactions/contact" "runtime_inform"
[static]

Associated with information given at runtime.

trick_units(-)

Definition at line 121 of file contact_messages.hh.

8.3.5.6 runtime_warns

```
char const * jeod::ContactMessages::runtime_warns = "interactions/contact" "runtime_warns"
[static]
```

Associated with warnings given at runtime.

trick_units(-)

Definition at line 114 of file contact_messages.hh.

The documentation for this class was generated from the following files:


- contact_messages.hh
- contact_messages.cc

8.4 jeod::ContactPair Class Reference

An base contact pair class for use in the contact model.

```
#include <contact_pair.hh>
```

Inheritance diagram for jeod::ContactPair:



Public Member Functions

- ContactPair ()=default
- virtual ∼ContactPair ()=default
- ContactPair & operator= (const ContactPair &)=delete
- ContactPair (const ContactPair &)=delete
- bool in_range ()

test whether the pair is in range for interaction

• bool is active ()

Determine if contact can occur between the two facets.

• bool is_complete ()

Determine if the pair has a target facet.

ContactFacet * get_subject ()

Determine if the pair has a target facet.

ContactFacet * get_target ()

Determine if the pair has a target facet.

• virtual void in_contact ()=0

Virtual funtion to determine if the pair is in contact.

- virtual void initialize_pair (ContactFacet *subject_facet, ContactFacet *target_facet)=0
 Initialize the contact pair by setting the subject, target, and creating the relstate if possible.
- virtual void initialize_relstate (DynManager *dyn_manager)

Initialize the relative state between the facets and register with the dynamics manager.

virtual bool check_tree ()

Make sure the two contact facets are not on the same mass tree.

Data Fields

PairInteraction * interaction {}

Parameters that define the force calculation function between the subjec and target.

double interaction_distance {}

rel_state distance at which in_contact should be called

Protected Attributes

• RelativeDerivedState rel_state

Current relative state between the subject and the target in the subject frame.

ContactFacet * subject {}

pointer to the contact facet that is the subject of the associated relative states.

ContactFacet * target {}

pointer to the contact facet that is the target of the associated relative states.

Friends

- · class InputProcessor
- void init_attrjeod__ContactPair ()

8.4.1 Detailed Description

An base contact pair class for use in the contact model.

Definition at line 84 of file contact_pair.hh.

8.4.2 Constructor & Destructor Documentation

8.4.3 Member Function Documentation

```
8.4.3.1 check_tree()
```

```
bool jeod::ContactPair::check_tree ( ) [virtual]
```

Make sure the two contact facets are not on the same mass tree.

Returns

bool

Definition at line 108 of file contact_pair.cc.

References subject, and target.

Referenced by is_active().

```
8.4.3.2 get_subject()
ContactFacet * jeod::ContactPair::get_subject ( )
Determine if the pair has a target facet.
Returns
      subject ContactFacet
Definition at line 90 of file contact_pair.cc.
References subject.
Referenced by jeod::Contact::initialize_contact().
8.4.3.3 get_target()
ContactFacet * jeod::ContactPair::get_target ( )
Determine if the pair has a target facet.
Returns
      target ContactFacet
Definition at line 99 of file contact_pair.cc.
References target.
8.4.3.4 in_contact()
virtual void jeod::ContactPair::in_contact ( ) [pure virtual]
Virtual funtion to determine if the pair is in contact.
Contact depends on specific geometry so implementation has to wait for a derived class.
Implemented in jeod::LinePointContactPair, jeod::LineContactPair, and jeod::PointContactPair.
8.4.3.5 in_range()
bool jeod::ContactPair::in_range ( )
test whether the pair is in range for interaction
Returns
      hool
Definition at line 49 of file contact pair.cc.
References interaction_distance, and rel_state.
```

```
8.4.3.6 initialize_pair()
```

Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Parameters

in,out	subject_facet	subject ContactFacet
in,out	target_facet	target ContactFacet

 $Implemented\ in\ jeod::Line Point Contact Pair,\ jeod::Line Contact Pair,\ and\ jeod::Point Contact Pair.$

8.4.3.7 initialize_relstate()

Initialize the relative state between the facets and register with the dynamics manager.

Initialize the relstate using the DynManager provided by Contact class.

Parameters

in <i>dy</i>	n_manager	dynamics manager
--------------	-----------	------------------

Definition at line 129 of file contact_pair.cc.

References rel_state, subject, and jeod::ContactFacet::vehicle_body.

Referenced by jeod::Contact::initialize_contact().

8.4.3.8 is_active()

```
bool jeod::ContactPair::is_active ( )
```

Determine if contact can occur between the two facets.

Returns

bool

Definition at line 64 of file contact_pair.cc.

References jeod::ContactFacet::active, check_tree(), subject, and target.

```
8.4.3.9 is_complete()
```

```
bool jeod::ContactPair::is_complete ( )
```

Determine if the pair has a target facet.

Returns

bool

Definition at line 77 of file contact_pair.cc.

References target.

8.4.3.10 operator=()

8.4.4 Friends And Related Function Documentation

8.4.4.1 init_attrjeod__ContactPair

```
void init_attrjeod__ContactPair ( ) [friend]
```

8.4.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file contact_pair.hh.

8.4.5 Field Documentation

8.4.5.1 interaction

```
PairInteraction* jeod::ContactPair::interaction {}
```

Parameters that define the force calculation function between the subjec and target.

trick_units(-)

Definition at line 90 of file contact_pair.hh.

Referenced by jeod::LineContactFacet::create_pair(), jeod::PointContactFacet::create_pair(), jeod::LineContact Pair::in_contact(), jeod::PointContactPair::in_contact().

8.4.5.2 interaction_distance

```
double jeod::ContactPair::interaction_distance {}
```

rel_state distance at which in_contact should be called

trick_units(m)

Definition at line 95 of file contact_pair.hh.

Referenced by jeod::LineContactFacet::create_pair(), jeod::PointContactFacet::create_pair(), and in_range().

8.4.5.3 rel_state

```
RelativeDerivedState jeod::ContactPair::rel_state [protected]
```

Current relative state between the subject and the target in the subject frame.

trick_units(-)

Definition at line 145 of file contact_pair.hh.

Referenced by jeod::LineContactPair::in_contact(), jeod::PointContactPair::in_contact(), jeod::LinePointContact Pair::in_contact(), jeod::LineContactPair::initialize_pair(), jeod::PointContactPair::initialize_pair(), jeod::LinePointContactPair::initialize_pair(), jeod::LinePointContactPair::initialize_pair(), and initialize_relstate().

8.4.5.4 subject

```
ContactFacet* jeod::ContactPair::subject {} [protected]
```

pointer to the contact facet that is the subject of the associated relative states.

trick_units(-)

Definition at line 150 of file contact_pair.hh.

Referenced by check_tree(), get_subject(), jeod::LineContactPair::initialize_pair(), jeod::PointContactPair::initialize_pair(), jeod::LinePointContactPair::initialize_pair(), initialize_relstate(), and is_active().

8.4.5.5 target

```
ContactFacet* jeod::ContactPair::target {} [protected]
```

pointer to the contact facet that is the target of the associated relative states.

trick_units(-)

Definition at line 155 of file contact_pair.hh.

Referenced by check_tree(), get_target(), jeod::LineContactPair::initialize_pair(), jeod::PointContactPair::initialize \rightarrow _pair(), jeod::LinePointContactPair::initialize_pair(), is_active(), and is_complete().

The documentation for this class was generated from the following files:


- · contact_pair.hh
- · contact_pair.cc

8.5 jeod::ContactParams Class Reference

A base class for all contact parameters used in the surface model.

```
#include <contact_params.hh>
```

Inheritance diagram for jeod::ContactParams:



Public Member Functions

- · ContactParams ()
 - Default Constructor.
- ContactParams () override=default
- ContactParams & operator= (const ContactParams &)=delete
- ContactParams (const ContactParams &)=delete

Friends

- class InputProcessor
- void init_attrjeod__ContactParams ()

8.5.1 Detailed Description

A base class for all contact parameters used in the surface model.

Definition at line 81 of file contact_params.hh.

8.5.2 Constructor & Destructor Documentation

8.5.3 Member Function Documentation

8.5.3.1 operator=()

8.5.4 Friends And Related Function Documentation

8.5.4.1 init_attrjeod__ContactParams

```
void init_attrjeod__ContactParams ( ) [friend]
```

8.5.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 83 of file contact_params.hh.

The documentation for this class was generated from the following files:


- · contact_params.hh
- · contact_params.cc

8.6 jeod::ContactSurface Class Reference

The contact specific interaction surface, for use with the surface model.

```
#include <contact_surface.hh>
```

Inheritance diagram for jeod::ContactSurface:



Public Member Functions

· ContactSurface ()

Default Constructor.

∼ContactSurface () override

Destructor

- ContactSurface & operator= (const ContactSurface &)=delete
- ContactSurface (const ContactSurface &)=delete
- void allocate_array (unsigned int size) override

Allocates an array of ContactFacet pointers, of the size indicated by the input variable.

• void allocate_interaction_facet (Facet *facet, InteractionFacetFactory *factory, FacetParams *params, unsigned int index) override

Creates an interaction facet or more accurately a contact facet from a basic facet and set of parameters.

virtual void collect_forces_torques ()

collect the forces and torques from all the facets in this contact surface

Data Fields

ContactFacet ** contact_facets {}

An array of pointers to contact interaction facets.

unsigned int facets_size {}

Size of the contact_facets array.

• double contact_force [3] {}

Total Force due to contact, resulting from all plates combined.

double contact_torque [3] {}

Total Torque due to contact, resulting from all plates combined.

Friends

- · class InputProcessor
- void init_attrjeod__ContactSurface ()

8.6.1 Detailed Description

The contact specific interaction surface, for use with the surface model.

Definition at line 84 of file contact_surface.hh.

8.6.2 Constructor & Destructor Documentation

```
8.6.2.1 ContactSurface() [1/2]
jeod::ContactSurface::ContactSurface ( )
```

Default Constructor.

Definition at line 56 of file contact_surface.cc.

```
8.6.2.2 ∼ContactSurface()
```

```
jeod::ContactSurface::~ContactSurface ( ) [override]
```

Destructor.

Definition at line 64 of file contact_surface.cc.

References contact_facets, and facets_size.

8.6.2.3 ContactSurface() [2/2]

8.6.3 Member Function Documentation

8.6.3.1 allocate_array()

Allocates an array of ContactFacet pointers, of the size indicated by the input variable.

Parameters

in	size	The size of the needed array	
		Units: cnt:	

Definition at line 75 of file contact_surface.cc.

 $References\ contact_facets,\ facets_size,\ and\ jeod::ContactMessages::initialization_error.$

8.6.3.2 allocate_interaction_facet()

Creates an interaction facet or more accurately a contact facet from a basic facet and set of parameters.

Parameters

in	facet	The basic facet used to create the interaction facet	
in	factory	The factory used to create the interaction facet	
in	params	The contact params used to create the interaction facet	
in	index	Where the new interaction facet will be placed in the contact_facets array	
		Units: cnt	

Definition at line 108 of file contact_surface.cc.

References contact_facets, facets_size, and jeod::ContactMessages::initialization_error.

8.6.3.3 collect_forces_torques()

```
void jeod::ContactSurface::collect_forces_torques ( ) [virtual]
```

collect the forces and torques from all the facets in this contact surface

Definition at line 177 of file contact_surface.cc.

 $References\ contact_facets,\ contact_force,\ contact_torque,\ and\ facets_size.$

8.6.3.4 operator=()

8.6.4 Friends And Related Function Documentation

8.6.4.1 init_attrjeod__ContactSurface

```
void init_attrjeod__ContactSurface ( ) [friend]
```

8.6.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file contact surface.hh.

8.6.5 Field Documentation

8.6.5.1 contact_facets

```
ContactFacet** jeod::ContactSurface::contact_facets {}
```

An array of pointers to contact interaction facets.

trick_units(-)

Definition at line 95 of file contact_surface.hh.

 $Referenced \ by \ allocate_array(), \ allocate_interaction_facet(), \ collect_forces_torques(), \ and \ \sim ContactSurface().$

8.6.5.2 contact_force

```
double jeod::ContactSurface::contact_force[3] {}
```

Total Force due to contact, resulting from all plates combined.

 $trick_units(N)$

Definition at line 105 of file contact_surface.hh.

Referenced by collect_forces_torques().

8.6.5.3 contact_torque

```
double jeod::ContactSurface::contact_torque[3] {}
```

Total Torque due to contact, resulting from all plates combined.

trick units(N/m)

Definition at line 110 of file contact_surface.hh.

Referenced by collect_forces_torques().

8.6.5.4 facets_size

```
unsigned int jeod::ContactSurface::facets_size {}
```

Size of the contact_facets array.

trick_units(count)

Definition at line 100 of file contact surface.hh.

Referenced by allocate array(), allocate interaction facet(), collect forces torques(), and ~ContactSurface().

The documentation for this class was generated from the following files:


- · contact_surface.hh
- contact_surface.cc

8.7 jeod::ContactSurfaceFactory Class Reference

The surface factory that creates an contact specific surface from a general surface.

```
#include <contact_surface_factory.hh>
```

Inheritance diagram for jeod::ContactSurfaceFactory:



Public Member Functions

ContactSurfaceFactory ()

Default Constructor.

- ~ContactSurfaceFactory () override=default
- ContactSurfaceFactory & operator= (const ContactSurfaceFactory &)=delete
- ContactSurfaceFactory (const ContactSurfaceFactory &)=delete
- void create_surface (SurfaceModel *surface, InteractionSurface *inter_surface) override

Creates an interaction surface, in the inter_surface parameter, from the given SurfaceModel.

void add_facet_params (FacetParams *to_add) override

Add a named set of facet params to the surface factory.

Protected Attributes

PointContactFacetFactory point_contact_facet_factory

A factory that can create a point contact facet from a circular flat plate.

LineContactFacetFactory line_contact_facet_factory

A factory that can create a line contact facet from a cylinder.

Friends

- · class InputProcessor
- void init_attrjeod__ContactSurfaceFactory ()

8.7.1 Detailed Description

The surface factory that creates an contact specific surface from a general surface.

Used with the surface model.

Definition at line 86 of file contact_surface_factory.hh.

8.7.2 Constructor & Destructor Documentation

8.7.2.1 ContactSurfaceFactory() [1/2]

 ${\tt jeod::} ContactSurfaceFactory:: ContactSurfaceFactory \ (\)$

Default Constructor.

Definition at line 48 of file contact_surface_factory.cc.

References line contact facet factory, and point contact facet factory.

8.7.2.2 ∼ContactSurfaceFactory()

```
jeod::ContactSurfaceFactory::~ContactSurfaceFactory ( ) [override], [default]
```

8.7.2.3 ContactSurfaceFactory() [2/2]

8.7.3 Member Function Documentation

8.7.3.1 add_facet_params()

Add a named set of facet params to the surface factory.

Intended to be used when an contact specific surface is created, to convert a basic facet to an contact interaction facet. This MUST be a parameter inheriting from ContactParam, or the function will fail and send a failure message

Parameters

in	to_add	The facet parameters to add

Definition at line 176 of file contact_surface_factory.cc.

References jeod::ContactMessages::pre_initialization_error.

8.7.3.2 create_surface()

Creates an interaction surface, in the inter_surface parameter, from the given SurfaceModel.

The InteractionSurfaceFactory should contain all necessary InteractionFacetFactories and FacetParams already

Parameters

	in	surface	The surface model used to create the interaction surface
ĺ	out	inter_surface	Where the interaction surface will be produced

Definition at line 65 of file contact_surface_factory.cc.

 $References\ jeod:: Contact Messages:: initialization_error.$

8.7.3.3 operator=()

8.7.4 Friends And Related Function Documentation

8.7.4.1 init_attrjeod__ContactSurfaceFactory

```
void init_attrjeod__ContactSurfaceFactory ( ) [friend]
```

8.7.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 88 of file contact_surface_factory.hh.

8.7.5 Field Documentation

8.7.5.1 line_contact_facet_factory

```
LineContactFacetFactory jeod::ContactSurfaceFactory::line_contact_facet_factory [protected]
```

A factory that can create a line contact facet from a cylinder.

```
trick_units(-)
```

Definition at line 115 of file contact_surface_factory.hh.

Referenced by ContactSurfaceFactory().

8.7.5.2 point_contact_facet_factory

```
PointContactFacetFactory jeod::ContactSurfaceFactory::point_contact_facet_factory [protected]
```

A factory that can create a point contact facet from a circular flat plate.

```
trick_units(-)
```

Definition at line 110 of file contact_surface_factory.hh.

Referenced by ContactSurfaceFactory().

The documentation for this class was generated from the following files:

- · contact_surface_factory.hh
- · contact_surface_factory.cc

8.8 jeod::ContactUtils Class Reference

Utility string and math functions for the contact model.

```
#include <contact_utils.hh>
```

Static Public Member Functions

- static int create_relstate_name (char *name1, char *name2, char **out_str)

 create a name for a relstate out of two facet names
- static int dist_line_segments (double p1[3], double p2[3], double p3[3], double p4[3], double *pa, double *pb) calculate the closest points between two line segments

8.8.1 Detailed Description

Utility string and math functions for the contact model.

Definition at line 72 of file contact_utils.hh.

8.8.2 Member Function Documentation

8.8.2.1 create_relstate_name()

create a name for a relstate out of two facet names

Returns

char**

Parameters

in	name1	name of first contact facet
in	name2	name of second contact facet
in,out	out_str	output name for the relstate

Definition at line 93 of file contact_utils_inline.hh.

8.8.2.2 dist_line_segments()

calculate the closest points between two line segments

Returns

success

Parameters

in	p1	vector to one point of the first line seg Units: M	
in	p2	vector to one point of the first line seg Units: M	
in	рЗ	vector to one point of the second line seg Units: M	
in	p4	vector to one point of the second line seg Units: M	
out	ра	vector to close_point on line 1 Units: M	
out	pb	vector to close_point on line 2 Units: M	

Definition at line 122 of file contact_utils_inline.hh.

 $Referenced \ by \ jeod::LineContactPair::in_contact(), \ and \ jeod::LinePointContactPair::in_contact().$

The documentation for this class was generated from the following files:


- · contact_utils.hh
- · contact_utils_inline.hh

8.9 jeod::LineContactFacet Class Reference

The contact facet based on the distance to a single point, specifically the vehicle point.

```
#include <line_contact_facet.hh>
```

Inheritance diagram for jeod::LineContactFacet:



Public Member Functions

· LineContactFacet ()

Default constructor.

- ~LineContactFacet () override=default
- LineContactFacet & operator= (const LineContactFacet &)=delete
- LineContactFacet (const LineContactFacet &)=delete
- ContactPair * create_pair () override

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

• ContactPair * create_pair (ContactFacet *target, Contact *contact) override

Overloaded functions that creates a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

void set_max_dimension () override

calculate the max dimension of the facet for range limit determination.

• void calculate_torque (double *tmp_force) override

Calculate the torque generated on the vehicle by the facet.

void calculate_contact_point (double nvec[3]) override

Find the point on the surface that coorisponds to the closest point on line segments using the radius value.

Data Fields

double length {}

length of the line along the vehicle point x axis.

Friends

- · class InputProcessor
- void init_attrjeod__LineContactFacet ()

8.9.1 Detailed Description

The contact facet based on the distance to a single point, specifically the vehicle point.

In effect this represents a sphere.

Definition at line 87 of file line contact facet.hh.

8.9.2 Constructor & Destructor Documentation

```
8.9.2.1 LineContactFacet() [1/2]
jeod::LineContactFacet::LineContactFacet ( )
```

Default constructor.

Definition at line 52 of file line_contact_facet.cc.

8.9.2.2 ~LineContactFacet()

```
\verb|jeod::LineContactFacet:: \sim LineContactFacet ( ) [override], [default]|
```

8.9.2.3 LineContactFacet() [2/2]

8.9.3 Member Function Documentation

8.9.3.1 calculate_contact_point()

Find the point on the surface that coorisponds to the closest point on line segments using the radius value.

Parameters

nvec vector between line points	in n
---------------------------------	------

Reimplemented from jeod::PointContactFacet.

Definition at line 159 of file line_contact_facet.cc.

References jeod::PointContactFacet::contact_point, length, and jeod::PointContactFacet::radius.

Referenced by jeod::LineContactPair::in_contact(), and jeod::LinePointContactPair::in_contact().

8.9.3.2 calculate_torque()

Calculate the torque generated on the vehicle by the facet.

Assumes that the force is in the vehicle structural frame, but that close_point is not.

Parameters

in	tmp_force	force from one contact interaction.
		Units: N

Implements jeod::ContactFacet.

Definition at line 212 of file line_contact_facet.cc.

```
8.9.3.3 create_pair() [1/2]
```

```
ContactPair * jeod::LineContactFacet::create_pair ( ) [override], [virtual]
```

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

This function is called to create a pair that only contains a subject.

Returns

ContactPair that was created

Implements jeod::ContactFacet.

Definition at line 64 of file line_contact_facet.cc.

References jeod::LineContactPair::initialize_pair().

8.9.3.4 create_pair() [2/2]

Overloaded functions that creates a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

This function is called when a subject and target are known.

Returns

ContactPair that was created

Parameters

in,out	target	target ContactFacet
in	contact	Contact object used to find the pair interaction

Implements jeod::ContactFacet.

Definition at line 83 of file line_contact_facet.cc.

References jeod::Contact::contact_limit_factor, jeod::Contact::find_interaction(), jeod::ContactMessages :::initialization_warns, jeod::LineContactPair::initialize_pair(), jeod::LinePointContactPair::initialize_pair(), jeod::ContactPair::initialize_pair(), jeod::ContactPair::interaction_distance, jeod::ContactFacet::max_dimension, and jeod::ContactFacet::surface_type.

8.9.3.5 operator=()

8.9.3.6 set_max_dimension()

```
void jeod::LineContactFacet::set_max_dimension ( ) [override], [virtual]
```

calculate the max dimension of the facet for range limit determination.

Implements jeod::ContactFacet.

Definition at line 202 of file line_contact_facet.cc.

References length, jeod::ContactFacet::max_dimension, and jeod::PointContactFacet::radius.

Referenced by jeod::LineContactFacetFactory::create_facet().

8.9.4 Friends And Related Function Documentation

8.9.4.1 init_attrjeod__LineContactFacet

```
void init_attrjeod__LineContactFacet ( ) [friend]
```

8.9.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file line_contact_facet.hh.

8.9.5 Field Documentation

8.9.5.1 length

```
double jeod::LineContactFacet::length {}
```

length of the line along the vehicle point x axis.

trick_units(m)

Definition at line 93 of file line_contact_facet.hh.

Referenced by calculate_contact_point(), $jeod::LineContactFacetFactory::create_facet()$, $jeod::LineContactPaircin_contact()$, $jeod::LineContactPaircin_contact()$, $jeod::LineContactPaircin_contact()$, and $set_max_dimension()$.

The documentation for this class was generated from the following files:


- · line_contact_facet.hh
- line_contact_facet.cc

8.10 jeod::LineContactFacetFactory Class Reference

Creates a PointContactFacet from an InteractionFacet.

```
#include <line_contact_facet_factory.hh>
```

Inheritance diagram for jeod::LineContactFacetFactory:



Public Member Functions

LineContactFacetFactory ()

Default Constructor.

- ~LineContactFacetFactory () override=default
- LineContactFacetFactory & operator= (const LineContactFacetFactory &)=delete
- LineContactFacetFactory (const LineContactFacetFactory &)=delete
- InteractionFacet * create_facet (Facet *facet, FacetParams *params) override

Create a PointContactFacet from a CircularFlatPlate facet and a ContactParams object.

bool is_correct_factory (Facet *facet) override

PointContactFacetFactory specific implementation of this function.

Friends

- · class InputProcessor
- void init_attrjeod__LineContactFacetFactory ()

8.10.1 Detailed Description

Creates a PointContactFacet from an InteractionFacet.

Definition at line 86 of file line_contact_facet_factory.hh.

8.10.2 Constructor & Destructor Documentation

```
8.10.2.1 LineContactFacetFactory() [1/2]
jeod::LineContactFacetFactory::LineContactFacetFactory ( )
```

Default Constructor.

Definition at line 52 of file line_contact_facet_factory.cc.

```
8.10.2.2 ~LineContactFacetFactory()
```

```
\verb|jeod::LineContactFacetFactory::\sim LineContactFacetFactory () [override], [default]|
```

8.10.2.3 LineContactFacetFactory() [2/2]

8.10.3 Member Function Documentation

8.10.3.1 create_facet()

Create a PointContactFacet from a CircularFlatPlate facet and a ContactParams object.

Returns

The new EllipsoidContactFacet. Note that this is allocated and YOU are responsible for destroying it at the end!

Parameters

in	facet	The CircularFlatPlate. This MUST be a circular flat plate or the algorithm will send a failure message
in	params	ContactParams

Definition at line 65 of file line_contact_facet_factory.cc.

References jeod::ContactFacet::create_vehicle_point(), jeod::ContactMessages::initialization_error, jeod::Line \leftarrow ContactFacet::length, jeod::ContactFacet::normal, jeod::ContactFacet::position, jeod::PointContactFacet::radius, jeod::LineContactFacet::set_max_dimension(), jeod::ContactFacet::surface_type, and jeod::ContactFacet \leftarrow ::vehicle body.

8.10.3.2 is_correct_factory()

PointContactFacetFactory specific implementation of this function.

If the Facet is of type CircularFlatPlate, returns true. False otherwise

Returns

true if facet is a FlatPlateCircular, false otherwise

Parameters

ı			
	in	facet	The facet to check

Definition at line 135 of file line_contact_facet_factory.cc.

8.10.3.3 operator=()

8.10.4 Friends And Related Function Documentation

8.10.4.1 init_attrjeod__LineContactFacetFactory

```
void init_attrjeod__LineContactFacetFactory ( ) [friend]
```

8.10.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 88 of file line_contact_facet_factory.hh.

The documentation for this class was generated from the following files:


- · line_contact_facet_factory.hh
- line_contact_facet_factory.cc

8.11 jeod::LineContactPair Class Reference

An point to point contact pair for use in the contact model.

```
#include <line_contact_pair.hh>
```

Inheritance diagram for jeod::LineContactPair:



Public Member Functions

- LineContactPair ()=default
- ~LineContactPair () override=default
- LineContactPair & operator= (const LineContactPair &)=delete
- LineContactPair (const LineContactPair &)=delete
- void in_contact () override

Determine if contact has occurred between the facets of the pair.

void initialize_pair (ContactFacet *subject_facet, ContactFacet *target_facet) override
 Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Data Fields

- LineContactFacet * line_subject {}
 pointer to the contact facet that is the subject of the associated relative states.
- LineContactFacet * line_target {}
 pointer to the contact facet that is the target of the associated relative states.

Friends

- · class InputProcessor
- void init_attrjeod__LineContactPair ()

Additional Inherited Members

8.11.1 Detailed Description

An point to point contact pair for use in the contact model.

Definition at line 84 of file line_contact_pair.hh.

8.11.2 Constructor & Destructor Documentation

```
8.11.2.1 LineContactPair() [1/2]

jeod::LineContactPair::LineContactPair ( ) [default]

8.11.2.2 ~LineContactPair()

jeod::LineContactPair::~LineContactPair ( ) [override], [default]
```

8.11.2.3 LineContactPair() [2/2]

8.11.3 Member Function Documentation

8.11.3.1 in_contact()

```
void jeod::LineContactPair::in_contact ( ) [override], [virtual]
```

Determine if contact has occurred between the facets of the pair.

Implements jeod::ContactPair.

Definition at line 48 of file line_contact_pair.cc.

References jeod::LineContactFacet::calculate_contact_point(), jeod::PairInteraction::calculate_forces(), jeod::

PointContactFacet::contact_point, jeod::ContactUtils::dist_line_segments(), jeod::ContactPair::interaction, jeod::

LineContactFacet::length, line_subject, line_target, and jeod::ContactPair::rel_state.

8.11.3.2 initialize_pair()

Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Parameters

in,out	subject_facet	subject ContactFacet
in,out	target_facet	target ContactFacet

Implements jeod::ContactPair.

Definition at line 138 of file line_contact_pair.cc.

References line_subject, line_target, jeod::ContactPair::rel_state, jeod::ContactPair::subject, jeod::ContactPair::subject, jeod::ContactPair::target, and jeod::ContactFacet::vehicle_point.

Referenced by jeod::LineContactFacet::create_pair().

8.11.3.3 operator=()

8.11.4 Friends And Related Function Documentation

8.11.4.1 init_attrjeod__LineContactPair

```
void init_attrjeod__LineContactPair ( ) [friend]
```

8.11.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file line_contact_pair.hh.

8.11.5 Field Documentation

8.11.5.1 line_subject

```
LineContactFacet* jeod::LineContactPair::line_subject {}
```

pointer to the contact facet that is the subject of the associated relative states.

```
trick_units(-)
```

Definition at line 90 of file line_contact_pair.hh.

Referenced by in_contact(), and initialize_pair().

8.11.5.2 line_target

```
LineContactFacet* jeod::LineContactPair::line_target {}
```

pointer to the contact facet that is the target of the associated relative states.

```
trick_units(-)
```

Definition at line 95 of file line_contact_pair.hh.

Referenced by in_contact(), and initialize_pair().

The documentation for this class was generated from the following files:


- line_contact_pair.hh
- line_contact_pair.cc

8.12 jeod::LinePointContactPair Class Reference

An point to point contact pair for use in the contact model.

```
#include <line_point_contact_pair.hh>
```

Inheritance diagram for jeod::LinePointContactPair:



Public Member Functions

- LinePointContactPair ()=default
- ~LinePointContactPair () override=default
- LinePointContactPair & operator= (const LineContactPair &)=delete
- LinePointContactPair (const LineContactPair &)=delete
- void in_contact () override

Determine if contact has occurred between the facets of the pair.

void initialize_pair (ContactFacet *subject_facet, ContactFacet *target_facet) override
 Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Data Fields

- LineContactFacet * line_subject {}
 pointer to the contact facet that is the subject of the associated relative states.
- PointContactFacet * point_target {}
 pointer to the contact facet that is the target of the associated relative states.

Friends

- class InputProcessor
- void init_attrjeod__LinePointContactPair ()

Additional Inherited Members

8.12.1 Detailed Description

An point to point contact pair for use in the contact model.

Definition at line 85 of file line point contact pair.hh.

8.12.2 Constructor & Destructor Documentation

8.12.2.1 LinePointContactPair() [1/2]

```
jeod::LinePointContactPair::LinePointContactPair ( ) [default]
```

8.12.2.2 ~LinePointContactPair()

```
jeod::LinePointContactPair::~LinePointContactPair ( ) [override], [default]
```

8.12.2.3 LinePointContactPair() [2/2]

8.12.3 Member Function Documentation

8.12.3.1 in_contact()

```
void jeod::LinePointContactPair::in_contact ( ) [override], [virtual]
```

Determine if contact has occurred between the facets of the pair.

Implements jeod::ContactPair.

Definition at line 49 of file line_point_contact_pair.cc.

References jeod::LineContactFacet::calculate_contact_point(), jeod::PointContactFacet::calculate_contact_point(), jeod::PointContactFacet::calculate_contact_point(), jeod::PointContactFacet::contact_point, jeod::ContactUtils::dist_line_contactFacet::length, line_subject, point_target, and jeod::ContactPair::rel_state.

8.12.3.2 initialize_pair()

Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Parameters

in,out	subject_facet	subject ContactFacet
in,out	target_facet	target ContactFacet

Implements jeod::ContactPair.

Definition at line 132 of file line_point_contact_pair.cc.

References line_subject, point_target, jeod::ContactPair::rel_state, jeod::ContactPair::subject, jeod::ContactPair::contactPair::subject, jeod::ContactPair::contactPa

Referenced by jeod::LineContactFacet::create_pair().

8.12.3.3 operator=()

8.12.4 Friends And Related Function Documentation

8.12.4.1 init_attrjeod_LinePointContactPair

```
\label{local_point} \mbox{void init\_attrjeod\_\_LinePointContactPair ()} \quad [\mbox{friend}]
```

8.12.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 87 of file line point contact pair.hh.

8.12.5 Field Documentation

8.12.5.1 line_subject

```
LineContactFacet* jeod::LinePointContactPair::line_subject {}
```

pointer to the contact facet that is the subject of the associated relative states.

```
trick units(-)
```

Definition at line 91 of file line_point_contact_pair.hh.

Referenced by in_contact(), and initialize_pair().

8.12.5.2 point_target

```
PointContactFacet* jeod::LinePointContactPair::point_target {}
```

pointer to the contact facet that is the target of the associated relative states.

```
trick_units(-)
```

Definition at line 96 of file line_point_contact_pair.hh.

Referenced by in contact(), and initialize pair().

The documentation for this class was generated from the following files:


- line_point_contact_pair.hh
- line_point_contact_pair.cc

8.13 jeod::PairInteraction Class Reference

Simple spring contact parameters.

```
#include <pair_interaction.hh>
```

Inheritance diagram for jeod::PairInteraction:



Public Member Functions

- PairInteraction ()=default
- virtual ∼PairInteraction ()=default
- PairInteraction & operator= (const PairInteraction &)=delete
- PairInteraction (const PairInteraction &)=delete
- bool is_correct_interaction (ContactParams *subject_params, ContactParams *target_params)

Check a pair of contact params for a match to the ones defined for this pair_interaction.

• virtual void calculate_forces (ContactFacet *subject, ContactFacet *target, RelativeDerivedState *rel_state, double *penetration_vector, double *rel_velocity)=0

Pure virtual function that is defined to calculate forces on facets in contact.

Data Fields

- std::string params_1
 contact param type that defines this pair interaction.
- std::string params_2

contact param type that defines this pair interaction.

double friction_mag {}

magnitude of the friction force on the contact surfaces.

Friends

- · class InputProcessor
- void init_attrjeod__PairInteraction ()

8.13.1 Detailed Description

Simple spring contact parameters.

Definition at line 89 of file pair_interaction.hh.

8.13.2 Constructor & Destructor Documentation

```
8.13.2.1 PairInteraction() [1/2]

jeod::PairInteraction::PairInteraction ( ) [default]

8.13.2.2 ~PairInteraction()

virtual jeod::PairInteraction::~PairInteraction ( ) [virtual], [default]
```

8.13.2.3 PairInteraction() [2/2]

8.13.3 Member Function Documentation

8.13.3.1 calculate_forces()

Pure virtual function that is defined to calculate forces on facets in contact.

Parameters

in,out	subject	subject of the relative state
in, out	n, out target target of the relative state	
in	rel_state	relative state between subject and target in subject frame
in	penetration_vector	vector that characterises the interpenetration of the subject and the target
in	rel_velocity	relative velocity of the subject and the target in the subject frame

Implemented in jeod::SpringPairInteraction.

Referenced by jeod::LineContactPair::in_contact(), jeod::PointContactPair::in_contact(), and jeod::LinePoint \leftarrow ContactPair::in_contact().

8.13.3.2 is_correct_interaction()

Check a pair of contact params for a match to the ones defined for this pair_interaction.

Returns

bool

Parameters

in	subject_params	parameters of the subject
in	target_params	parameters of the target

Definition at line 50 of file pair_interaction.cc.

References params_1, and params_2.

8.13.3.3 operator=()

8.13.4 Friends And Related Function Documentation

8.13.4.1 init_attrjeod__PairInteraction

```
void init_attrjeod__PairInteraction ( ) [friend]
```

8.13.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 91 of file pair_interaction.hh.

8.13.5 Field Documentation

8.13.5.1 friction_mag

```
double jeod::PairInteraction::friction_mag {}
```

magnitude of the friction force on the contact surfaces.

trick_units(N)

Definition at line 105 of file pair_interaction.hh.

Referenced by jeod::SpringPairInteraction::calculate_forces().

8.13.5.2 params_1

```
std::string jeod::PairInteraction::params_1
```

contact param type that defines this pair interaction.

trick_units(-)

Definition at line 95 of file pair_interaction.hh.

Referenced by is_correct_interaction().

8.13.5.3 params_2

```
std::string jeod::PairInteraction::params_2
```

contact param type that defines this pair interaction.

trick units(-)

Definition at line 100 of file pair_interaction.hh.

Referenced by is_correct_interaction().

The documentation for this class was generated from the following files:


- · pair_interaction.hh
- pair_interaction.cc

8.14 jeod::PointContactFacet Class Reference

The contact facet based on the distance to a single point, specifically the vehicle point.

```
#include <point_contact_facet.hh>
```

Inheritance diagram for jeod::PointContactFacet:



Public Member Functions

PointContactFacet ()

Default constructor.

- ~PointContactFacet () override=default
- PointContactFacet & operator= (const PointContactFacet &)=delete
- PointContactFacet (const PointContactFacet &)=delete
- ContactPair * create_pair () override

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

ContactPair * create pair (ContactFacet *target, Contact *contact) override

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

• void set_max_dimension () override

calculate the max dimension of the facet for range limit determination.

virtual void calculate_contact_point (double nvec[3])

Use the relstate and radius of contact to calculate a contact point on this facet.

void calculate_torque (double *tmp_force) override

Calculate the torque generated on the vehicle by the facet.

Data Fields

· double radius {}

radius from the point at which contact takes place.

double contact_point [3] {}

Contact point given in facet vehicle point frame, representing point on the point on the surface of a sphere of radius "radius" where contact has occured.

Friends

- class InputProcessor
- void init_attrjeod__PointContactFacet ()

8.14.1 Detailed Description

The contact facet based on the distance to a single point, specifically the vehicle point.

In effect this represents a sphere.

Definition at line 87 of file point contact facet.hh.

8.14.2 Constructor & Destructor Documentation

```
8.14.2.1 PointContactFacet() [1/2]
```

```
jeod::PointContactFacet::PointContactFacet ( )
```

Default constructor.

Definition at line 50 of file point contact facet.cc.

8.14.2.2 ~PointContactFacet()

```
jeod::PointContactFacet::~PointContactFacet ( ) [override], [default]
```

8.14.2.3 PointContactFacet() [2/2]

8.14.3 Member Function Documentation

8.14.3.1 calculate_contact_point()

Use the relstate and radius of contact to calculate a contact point on this facet.

Parameters

in	nvec	direction vector between the two facets
----	------	---

Reimplemented in jeod::LineContactFacet.

Definition at line 119 of file point_contact_facet.cc.

References contact_point, and radius.

Referenced by jeod::PointContactPair::in_contact(), and jeod::LinePointContactPair::in_contact().

8.14.3.2 calculate_torque()

Calculate the torque generated on the vehicle by the facet.

Assumes that the force is in the vehicle structural frame, but that close point is not.

Parameters

in	tmp_force	force from one contact interaction.
		Units: N

Implements jeod::ContactFacet.

Definition at line 141 of file point_contact_facet.cc.

References contact_point, jeod::ContactFacet::vehicle_body, and jeod::ContactFacet::vehicle_point.

```
8.14.3.3 create_pair() [1/2]
ContactPair * jeod::PointContactFacet::create_pair ( ) [override], [virtual]
```

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

This function is called to create a pair that only contains a subject.

Returns

ContactPair that was created

Implements jeod::ContactFacet.

Definition at line 61 of file point_contact_facet.cc.

References jeod::PointContactPair::initialize_pair().

```
8.14.3.4 create_pair() [2/2]
```

Overloaded functions that create a ContactPair and pass the address of it to the Contact class for addition to the list of pairs.

This function is called when a subject and target are known.

Returns

ContactPair that was created

Parameters

in,out	target	target ContactFacet
in	contact	Contact object used to find the pair interaction

Implements jeod::ContactFacet.

Definition at line 80 of file point_contact_facet.cc.

References jeod::Contact::contact_limit_factor, jeod::Contact::find_interaction(), jeod::ContactMessages ::initialization_warns, jeod::PointContactPair::initialize_pair(), jeod::ContactPair::interaction, jeod::ContactPair::interaction_distance, jeod::ContactFacet::max_dimension, and jeod::ContactFacet::surface_type.

8.14.3.5 operator=()

8.14.3.6 set_max_dimension()

```
void jeod::PointContactFacet::set_max_dimension ( ) [override], [virtual]
```

calculate the max dimension of the facet for range limit determination.

Implements jeod::ContactFacet.

Definition at line 131 of file point_contact_facet.cc.

References jeod::ContactFacet::max_dimension, and radius.

 $Referenced\ by\ jeod::PointContactFacetFactory::create_facet().$

8.14.4 Friends And Related Function Documentation

8.14.4.1 init_attrjeod_PointContactFacet

```
void init_attrjeod__PointContactFacet ( ) [friend]
```

8.14.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file point_contact_facet.hh.

8.14.5 Field Documentation

8.14.5.1 contact_point

```
double jeod::PointContactFacet::contact_point[3] {}
```

Contact point given in facet vehicle point frame, representing point on the point on the surface of a sphere of radius "radius" where contact has occured.

trick units(m)

Definition at line 100 of file point_contact_facet.hh.

Referenced by jeod::LineContactFacet::calculate_contact_point(), calculate_contact_point(), jeod::LineContact \leftarrow Facet::calculate_torque(), calculate_torque(), jeod::LineContactPair::in_contact(), jeod::PointContactPair::in_ \leftarrow contact(), and jeod::LinePointContactPair::in_contact().

8.14.5.2 radius

```
double jeod::PointContactFacet::radius {}
```

radius from the point at which contact takes place.

trick_units(m)

Definition at line 93 of file point_contact_facet.hh.

Referenced by jeod::LineContactFacet::calculate_contact_point(), calculate_contact_point(), jeod::PointContact \leftarrow FacetFactory::create_facet(), jeod::LineContactFacetFactory::create_facet(), jeod::PointContactPair::in_contact(), jeod::LineContactFacet::set_max_dimension(), and set_max_dimension().

The documentation for this class was generated from the following files:


- · point contact facet.hh
- point_contact_facet.cc

8.15 jeod::PointContactFacetFactory Class Reference

Creates a PointContactFacet from an InteractionFacet.

```
#include <point_contact_facet_factory.hh>
```

Inheritance diagram for jeod::PointContactFacetFactory:



Public Member Functions

· PointContactFacetFactory ()

Default Constructor.

- ~PointContactFacetFactory () override=default
- PointContactFacetFactory & operator= (const PointContactFacetFactory &)=delete
- PointContactFacetFactory (const PointContactFacetFactory &)=delete
- $\bullet \ \ \text{InteractionFacet} * \textit{create_facet} \ (\text{Facet} * \textit{facet}, \, \text{FacetParams} * \textit{params}) \ \textit{override} \\$

Create a PointContactFacet from a CircularFlatPlate facet and a ContactParams object.

bool is_correct_factory (Facet *facet) override

PointContactFacetFactory specific implementation of this function.

Friends

- · class InputProcessor
- void init_attrjeod__PointContactFacetFactory ()

8.15.1 Detailed Description

Creates a PointContactFacet from an InteractionFacet.

Definition at line 86 of file point_contact_facet_factory.hh.

8.15.2 Constructor & Destructor Documentation

8.15.2.1 PointContactFacetFactory() [1/2]

```
\verb|jeod::PointContactFacetFactory::PointContactFacetFactory ( )|\\
```

Default Constructor.

Definition at line 51 of file point_contact_facet_factory.cc.

8.15.2.2 ∼PointContactFacetFactory()

```
jeod::PointContactFacetFactory::~PointContactFacetFactory ( ) [override], [default]
```

8.15.2.3 PointContactFacetFactory() [2/2]

8.15.3 Member Function Documentation

8.15.3.1 create_facet()

Create a PointContactFacet from a CircularFlatPlate facet and a ContactParams object.

Returns

The new EllipsoidContactFacet. Note that this is allocated and YOU are responsible for destroying it at the end!

Parameters

in	facet	The CircularFlatPlate. This MUST be a circular flat plate or the algorithm will send a failure
		message
in	params	ContactParams

Definition at line 64 of file point_contact_facet_factory.cc.

References jeod::ContactFacet::create_vehicle_point(), jeod::ContactMessages::initialization_error, jeod:: \leftarrow ContactFacet::normal, jeod::ContactFacet::position, jeod::PointContactFacet::radius, jeod::PointContactFacet::vehicle_body.

8.15.3.2 is_correct_factory()

PointContactFacetFactory specific implementation of this function.

If the Facet is of type CircularFlatPlate, returns true. False otherwise

Returns

true if facet is a FlatPlateCircular, false otherwise

Parameters

in fa	acet TI	ne facet to check
-------	---------	-------------------

Definition at line 133 of file point_contact_facet_factory.cc.

8.15.3.3 operator=()

8.15.4 Friends And Related Function Documentation

8.15.4.1 init_attrjeod__PointContactFacetFactory

```
void init_attrjeod__PointContactFacetFactory ( ) [friend]
```

8.15.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 88 of file point_contact_facet_factory.hh.

The documentation for this class was generated from the following files:

- point_contact_facet_factory.hh
- point_contact_facet_factory.cc

8.16 jeod::PointContactPair Class Reference

An point to point contact pair for use in the contact model.

```
#include <point_contact_pair.hh>
```

Inheritance diagram for jeod::PointContactPair:



Public Member Functions

- PointContactPair ()=default
- ~PointContactPair () override=default
- PointContactPair & operator= (const PointContactPair &)=delete
- PointContactPair (const PointContactPair &)=delete
- void in_contact () override

Determine if contact has occurred between the facets of the pair.

void initialize_pair (ContactFacet *subject_facet, ContactFacet *target_facet) override
 Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Data Fields

- PointContactFacet * point_subject {}
 pointer to the point contact facet that is the subject of the associated relative states.
- PointContactFacet * point_target {}
 pointer to the point contact facet that is the target of the associated relative states.

Friends

- · class InputProcessor
- void init_attrjeod__PointContactPair ()

Additional Inherited Members

8.16.1 Detailed Description

An point to point contact pair for use in the contact model.

Definition at line 84 of file point_contact_pair.hh.

8.16.2 Constructor & Destructor Documentation

```
8.16.2.1 PointContactPair() [1/2]

jeod::PointContactPair::PointContactPair ( ) [default]

8.16.2.2 ~PointContactPair()

jeod::PointContactPair::~PointContactPair ( ) [override], [default]
```

8.16.2.3 PointContactPair() [2/2]

8.16.3 Member Function Documentation

8.16.3.1 in_contact()

```
void jeod::PointContactPair::in_contact ( ) [override], [virtual]
```

Determine if contact has occurred between the facets of the pair.

Implements jeod::ContactPair.

Definition at line 47 of file point_contact_pair.cc.

References jeod::PointContactFacet::calculate_contact_point(), jeod::PairInteraction::calculate_forces(), jeod::

PointContactFacet::contact_point, jeod::ContactPair::interaction, point_subject, point_target, jeod::PointContact
Facet::radius, and jeod::ContactPair::rel_state.

8.16.3.2 initialize_pair()

Initialize the contact pair by setting the subject, target, and creating the relstate if possible.

Parameters

in,out	subject_facet	subject ContactFacet
in,out	target_facet	target ContactFacet

Implements jeod::ContactPair.

Definition at line 96 of file point_contact_pair.cc.

References point_subject, point_target, jeod::ContactPair::rel_state, jeod::ContactPair::subject, jeod::ContactPair::rel_state, jeod::ContactPair::subject, jeod::ContactPair::rel_state, jeod::ContactPair::subject, jeod::ContactPair::ContactPair::subject

Referenced by jeod::PointContactFacet::create_pair().

8.16.3.3 operator=()

8.16.4 Friends And Related Function Documentation

8.16.4.1 init_attrjeod__PointContactPair

```
void init_attrjeod__PointContactPair ( ) [friend]
```

8.16.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file point_contact_pair.hh.

8.16.5 Field Documentation

8.16.5.1 point_subject

```
PointContactFacet* jeod::PointContactPair::point_subject {}
```

pointer to the point contact facet that is the subject of the associated relative states.

```
trick_units(-)
```

Definition at line 90 of file point_contact_pair.hh.

Referenced by in_contact(), and initialize_pair().

8.16.5.2 point_target

```
PointContactFacet* jeod::PointContactPair::point_target {}
```

pointer to the point contact facet that is the target of the associated relative states.

```
trick_units(-)
```

Definition at line 95 of file point_contact_pair.hh.

Referenced by in_contact(), and initialize_pair().

The documentation for this class was generated from the following files:


- point_contact_pair.hh
- point_contact_pair.cc

8.17 jeod::SpringPairInteraction Class Reference

Simple spring contact parameters.

```
#include <spring_pair_interaction.hh>
```

Inheritance diagram for jeod::SpringPairInteraction:



Public Member Functions

- SpringPairInteraction ()=default
- ~SpringPairInteraction () override=default
- SpringPairInteraction & operator= (const SpringPairInteraction &)=delete
- SpringPairInteraction (const SpringPairInteraction &)=delete
- void calculate_forces (ContactFacet *subject, ContactFacet *target, RelativeDerivedState *rel_state, double *penetration_vector, double *rel_velocity) override

force calculation for a simple spring based contact dynamics model, takes in geometry information from the appropriate ContactFacet::calculate_forces but doesn't know about specific type of ContactFacet

Data Fields

- double spring_k {}
 - Spring stiffness constant.
- double damping_b {}
 - Spring damping constant.
- double mu {}

Coefficent of friction.

Friends

- · class InputProcessor
- void init_attrjeod__SpringPairInteraction ()

8.17.1 Detailed Description

Simple spring contact parameters.

Definition at line 83 of file spring_pair_interaction.hh.

8.17.2 Constructor & Destructor Documentation

8.17.2.1 SpringPairInteraction() [1/2]

```
jeod::SpringPairInteraction::SpringPairInteraction ( ) [default]
```

8.17.2.2 ~SpringPairInteraction()

```
jeod::SpringPairInteraction::~SpringPairInteraction ( ) [override], [default]
```

8.17.2.3 SpringPairInteraction() [2/2]

8.17.3 Member Function Documentation

8.17.3.1 calculate_forces()

force calculation for a simple spring based contact dynamics model, takes in geometry information from the appropriate ContactFacet::calculate_forces but doesn't know about specific type of ContactFacet

Parameters

in, out	subject	subject frame of the relative state
in,out	target	target frame of the relative state
in	rel_state	relative state between subject and target in subject frame
in	penetration_vector	vector that characterises the interpenetration of the subject and the target
in	rel_velocity	relative velocity of the subject and the target in the subject frame

Implements jeod::PairInteraction.

Definition at line 57 of file spring_pair_interaction.cc.

References jeod::ContactFacet::calculate_torque(), damping_b, jeod::PairInteraction::friction_mag, mu, spring_k, jeod::ContactFacet::vehicle_body, and jeod::ContactFacet::vehicle_point.

```
8.17.3.2 operator=()
```

8.17.4 Friends And Related Function Documentation

8.17.4.1 init_attrjeod__SpringPairInteraction

```
void init_attrjeod__SpringPairInteraction ( ) [friend]
```

8.17.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 85 of file spring_pair_interaction.hh.

8.17.5 Field Documentation

8.17.5.1 damping_b

```
double jeod::SpringPairInteraction::damping_b {}
```

Spring damping constant.

trick_units(N*s/m)

Definition at line 94 of file spring_pair_interaction.hh.

Referenced by calculate_forces().

8.17.5.2 mu

```
double jeod::SpringPairInteraction::mu {}
```

Coefficent of friction.

trick_units(-)

Definition at line 99 of file spring_pair_interaction.hh.

Referenced by calculate_forces().

```
8.17.5.3 spring_k
double jeod::SpringPairInteraction::spring_k {}
Spring stiffness constant.
trick_units(N/m)
```

Definition at line 89 of file spring_pair_interaction.hh.

Referenced by calculate_forces().

The documentation for this class was generated from the following files:

- spring_pair_interaction.hh
- spring_pair_interaction.cc

Chapter 9

File Documentation

9.1 class_declarations.hh File Reference

Forward declaration of classes defined in the contact model.

Namespaces

• jeod

Namespace jeod.

9.1.1 Detailed Description

Forward declaration of classes defined in the contact model.

9.2 contact.cc File Reference

Base Contact for use with contact interaction model.

```
#include "dynamics/mass/include/mass.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/surface_model/include/facet.hh"
#include "../include/contact.hh"
#include "../include/contact_facet.hh"
#include "../include/contact_pair.hh"
#include "../include/pair_interaction.hh"
```

Namespaces

• jeod

Namespace jeod.

88 File Documentation

9.2.1 Detailed Description

Base Contact for use with contact interaction model.

9.3 contact.hh File Reference

(Base class to for the contact manager for use with contact interaction model)

```
#include <list>
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "utils/container/include/pointer_list.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "contact_facet.hh"
#include "contact_pair.hh"
#include "pair_interaction.hh"
```

Data Structures

· class jeod::Contact

An base contact class for use in the surface model.

Namespaces

• jeod

Namespace jeod.

9.3.1 Detailed Description

(Base class to for the contact manager for use with contact interaction model)

9.4 contact_facet.cc File Reference

Define ContactFacet::create_vehicle_point.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "dynamics/mass/include/mass_point_init.hh"
#include "utils/math/include/numerical.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/surface_model/include/facet.hh"
#include "../include/contact_facet.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_utils.hh"
```

Namespaces

• jeod

Namespace jeod.

9.4.1 Detailed Description

Define ContactFacet::create_vehicle_point.

9.5 contact_facet.hh File Reference

Individual facets for use with contact interaction models.

```
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/facet.hh"
#include "utils/surface_model/include/interaction_facet.hh"
#include "class_declarations.hh"
```

Data Structures

· class jeod::ContactFacet

An contact interaction specific facet for use in the surface model.

Namespaces

• jeod

Namespace jeod.

9.5.1 Detailed Description

Individual facets for use with contact interaction models.

9.6 contact_messages.cc File Reference

Implement contact_messages.

```
#include "utils/message/include/make_message_code.hh"
#include "../include/contact_messages.hh"
```

90 File Documentation

Namespaces

• jeod

Namespace jeod.

Macros

#define MAKE_CONTACT_MESSAGE_CODE(id) JEOD_MAKE_MESSAGE_CODE(ContactMessages, "interactions/contact", id)

9.6.1 Detailed Description

Implement contact_messages.

9.6.2 Macro Definition Documentation

9.6.2.1 MAKE_CONTACT_MESSAGE_CODE

Definition at line 43 of file contact_messages.cc.

9.7 contact_messages.hh File Reference

Contact message for message handling.

```
#include "utils/message/include/message_handler.hh"
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::ContactMessages

Messages associated with use of the contact model.

Namespaces

• jeod

Namespace jeod.

9.7.1 Detailed Description

Contact message for message handling.

9.8 contact_pair.cc File Reference

ContactPair class for use with contact interaction model.

```
#include <cmath>
#include "dynamics/mass/include/mass.hh"
#include "utils/math/include/vector3.hh"
#include "../include/contact_pair.hh"
```

Namespaces

· jeod

Namespace jeod.

9.8.1 Detailed Description

ContactPair class for use with contact interaction model.

9.9 contact_pair.hh File Reference

Base class for pair of contact facets for use with contact interaction model.

```
#include "dynamics/derived_state/include/relative_derived_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "contact_facet.hh"
```

Data Structures

class jeod::ContactPair

An base contact pair class for use in the contact model.

Namespaces

• jeod

Namespace jeod.

92 File Documentation

9.9.1 Detailed Description

Base class for pair of contact facets for use with contact interaction model.

9.10 contact_params.cc File Reference

contact parameters for use in the surface model

```
#include "utils/memory/include/jeod_alloc.hh"
#include "../include/contact_params.hh"
```

Namespaces

• jeod

Namespace jeod.

9.10.1 Detailed Description

contact parameters for use in the surface model

9.11 contact_params.hh File Reference

A class for contact facet parameters, used to create interaction facets for contact in the InteractionSurfaceFactorys.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/facet_params.hh"
```

Data Structures

· class jeod::ContactParams

A base class for all contact parameters used in the surface model.

Namespaces

• jeod

Namespace jeod.

9.11.1 Detailed Description

A class for contact facet parameters, used to create interaction facets for contact in the InteractionSurfaceFactorys.

9.12 contact surface.cc File Reference

Vehicle surface model for the contact interaction models.

```
#include <cstddef>
#include <typeinfo>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/surface_model/include/facet.hh"
#include "utils/surface_model/include/interaction_facet_factory.hh"
#include "../include/contact_facet.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_surface.hh"
```

Namespaces

jeod

Namespace jeod.

9.12.1 Detailed Description

Vehicle surface model for the contact interaction models.

9.13 contact surface.hh File Reference

Vehicle surface model for contact.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/class_declarations.hh"
#include "utils/surface_model/include/interaction_surface.hh"
#include "contact_facet.hh"
```

Data Structures

· class jeod::ContactSurface

The contact specific interaction surface, for use with the surface model.

Namespaces

• jeod

9.13.1 Detailed Description

Vehicle surface model for contact.

9.14 contact_surface_factory.cc File Reference

Factory that creates an contact surface, from a surface model.

```
#include <cstddef>
#include <cstring>
#include "dynamics/mass/include/mass.hh"
#include "utils/surface_model/include/facet.hh"
#include "utils/surface_model/include/facet_params.hh"
#include "utils/surface_model/include/interaction_surface.hh"
#include "utils/surface_model/include/surface_model.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_params.hh"
#include "../include/contact_surface_factory.hh"
```

Namespaces

jeod

Namespace jeod.

9.14.1 Detailed Description

Factory that creates an contact surface, from a surface model.

9.15 contact_surface_factory.hh File Reference

Factory that creates an contact interaction surface from a surface model.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/class_declarations.hh"
#include "utils/surface_model/include/interaction_surface_factory.hh"
#include "line_contact_facet_factory.hh"
#include "point_contact_facet_factory.hh"
```

Data Structures

· class jeod::ContactSurfaceFactory

The surface factory that creates an contact specific surface from a general surface.

Namespaces

· jeod

Namespace jeod.

9.15.1 Detailed Description

Factory that creates an contact interaction surface from a surface model.

9.16 contact_utils.hh File Reference

This Model is used for utility rotines.

```
#include "contact_utils_inline.hh"
```

Data Structures

class jeod::ContactUtils

Utility string and math functions for the contact model.

Namespaces

• jeod

Namespace jeod.

9.16.1 Detailed Description

This Model is used for utility rotines.

9.17 contact_utils_inline.hh File Reference

 $Define\ Contact Utils::create_relstate_name,\ Contact Utils::copy_const_char_to_char.$

```
#include <cstring>
#include "utils/math/include/vector3.hh"
#include "contact_messages.hh"
#include "contact_utils.hh"
```

Namespaces

• jeod

9.17.1 Detailed Description

Define ContactUtils::create_relstate_name, ContactUtils::copy_const_char_to_char.

9.18 line contact facet.cc File Reference

Define LineContactFacet functions.

```
#include <cmath>
#include "utils/math/include/matrix3x3.hh"
#include "utils/math/include/numerical.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "../include/contact.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_params.hh"
#include "../include/contact_utils.hh"
#include "../include/line_contact_facet.hh"
#include "../include/line_contact_pair.hh"
#include "../include/line_contact_pair.hh"
```

Namespaces

• jeod

Namespace jeod.

9.18.1 Detailed Description

Define LineContactFacet functions.

9.19 line contact facet.hh File Reference

The contact facet based on the distance to a line segment centered on the vehicle point.

```
#include "dynamics/derived_state/include/relative_derived_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "point_contact_facet.hh"
#include "line_contact_pair.hh"
#include "line_point_contact_pair.hh"
```

Data Structures

· class jeod::LineContactFacet

The contact facet based on the distance to a single point, specifically the vehicle point.

Namespaces

· jeod

Namespace jeod.

9.19.1 Detailed Description

The contact facet based on the distance to a line segment centered on the vehicle point.

In effect this represents a cylinder with spherical ends.

9.20 line_contact_facet_factory.cc File Reference

Factory that creates a LineContactFacetFactory from a Cylinder facet and a ContactParams object.

```
#include <cstddef>
#include dynamics/dyn_body/include/dyn_body.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/surface_model/include/cylinder.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_params.hh"
#include "../include/line_contact_facet.hh"
#include "../include/line_contact_facet_factory.hh"
```

Namespaces

• jeod

Namespace jeod.

9.20.1 Detailed Description

Factory that creates a LineContactFacetFactory from a Cylinder facet and a ContactParams object.

9.21 line_contact_facet_factory.hh File Reference

Creates a line contact facet from an cylinder facet.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/class_declarations.hh"
#include "utils/surface_model/include/interaction_facet.hh"
#include "utils/surface_model/include/interaction_facet_factory.hh"
#include "class_declarations.hh"
#include "line_contact_facet.hh"
```

Data Structures

class jeod::LineContactFacetFactory
 Creates a PointContactFacet from an InteractionFacet.

Namespaces

· jeod

Namespace jeod.

9.21.1 Detailed Description

Creates a line contact facet from an cylinder facet.

9.22 line_contact_pair.cc File Reference

LineContactPair class for use with contact interaction model.

```
#include "dynamics/mass/include/mass.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/contact_utils.hh"
#include "../include/line_contact_facet.hh"
#include "../include/line_contact_pair.hh"
#include "../include/pair_interaction.hh"
```

Namespaces

· jeod

Namespace jeod.

9.22.1 Detailed Description

LineContactPair class for use with contact interaction model.

9.23 line_contact_pair.hh File Reference

Class for a pair of line contact facets for use with contact interaction model.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "contact_pair.hh"
```

Data Structures

· class jeod::LineContactPair

An point to point contact pair for use in the contact model.

Namespaces

jeod

Namespace jeod.

9.23.1 Detailed Description

Class for a pair of line contact facets for use with contact interaction model.

9.24 line_point_contact_pair.cc File Reference

LinePointContactPair class for use with contact interaction model.

```
#include "dynamics/mass/include/mass.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/contact_utils.hh"
#include "../include/line_contact_facet.hh"
#include "../include/line_point_contact_pair.hh"
#include "../include/pair_interaction.hh"
#include "../include/point_contact_facet.hh"
```

Namespaces

jeod

Namespace jeod.

9.24.1 Detailed Description

LinePointContactPair class for use with contact interaction model.

9.25 line_point_contact_pair.hh File Reference

Class for a pair of a line contact facet and a point contact facet for use with contact interaction model.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "contact_pair.hh"
```

Data Structures

· class jeod::LinePointContactPair

An point to point contact pair for use in the contact model.

Namespaces

jeod

Namespace jeod.

9.25.1 Detailed Description

Class for a pair of a line contact facet and a point contact facet for use with contact interaction model.

9.26 pair_interaction.cc File Reference

A class to define the interaction type for a pair of contact facets.

```
#include <cstring>
#include "../include/contact_facet.hh"
#include "../include/contact_params.hh"
#include "../include/pair_interaction.hh"
```

Namespaces

• jeod

Namespace jeod.

9.26.1 Detailed Description

A class to define the interaction type for a pair of contact facets.

This is a base class and derived classes define the force generation function when contact between facets occurs.

9.27 pair_interaction.hh File Reference

A class to define the interaction type for a pair of contact facets.

```
#include <string>
#include "dynamics/derived_state/include/class_declarations.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "../include/class_declarations.hh"
```

Data Structures

· class jeod::PairInteraction

Simple spring contact parameters.

Namespaces

· jeod

Namespace jeod.

9.27.1 Detailed Description

A class to define the interaction type for a pair of contact facets.

This is a base class and derived classes define the force generation function when contact between facets occurs.

9.28 point_contact_facet.cc File Reference

Define PointContactFacet functions.

```
#include <cmath>
#include "utils/math/include/matrix3x3.hh"
#include "utils/math/include/numerical.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "../include/contact.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_params.hh"
#include "../include/contact_utils.hh"
#include "../include/point_contact_facet.hh"
#include "../include/point_contact_pair.hh"
```

Namespaces

· jeod

Namespace jeod.

9.28.1 Detailed Description

Define PointContactFacet functions.

9.29 point_contact_facet.hh File Reference

The contact facet based on the distance to a single point, specifically the vehicle point.

```
#include "dynamics/derived_state/include/relative_derived_state.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "contact_facet.hh"
#include "point_contact_pair.hh"
```

Data Structures

· class jeod::PointContactFacet

The contact facet based on the distance to a single point, specifically the vehicle point.

Namespaces

jeod

Namespace jeod.

9.29.1 Detailed Description

The contact facet based on the distance to a single point, specifically the vehicle point.

In effect this represents a sphere.

9.30 point_contact_facet_factory.cc File Reference

Factory that creates a PointContactFacet from a FlatPlateCircular facet and a ContactParams object.

```
#include <cstddef>
#include <typeinfo>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/surface_model/include/flat_plate_circular.hh"
#include "../include/contact_messages.hh"
#include "../include/contact_params.hh"
#include "../include/point_contact_facet.hh"
#include "../include/point_contact_facet_factory.hh"
```

Namespaces

jeod

9.30.1 Detailed Description

Factory that creates a PointContactFacet from a FlatPlateCircular facet and a ContactParams object.

9.31 point_contact_facet_factory.hh File Reference

Creates a point contact facet from an circular flat plate facet.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/class_declarations.hh"
#include "utils/surface_model/include/interaction_facet.hh"
#include "utils/surface_model/include/interaction_facet_factory.hh"
#include "class_declarations.hh"
#include "point_contact_facet.hh"
```

Data Structures

class jeod::PointContactFacetFactory
 Creates a PointContactFacet from an InteractionFacet.

Namespaces

jeod

Namespace jeod.

9.31.1 Detailed Description

Creates a point contact facet from an circular flat plate facet.

9.32 point_contact_pair.cc File Reference

ContactPair class for use with contact interaction model.

```
#include "utils/named_item/include/named_item.hh"
#include "../include/contact_utils.hh"
#include "../include/pair_interaction.hh"
#include "../include/point_contact_facet.hh"
#include "../include/point_contact_pair.hh"
```

Namespaces

jeod

9.32.1 Detailed Description

ContactPair class for use with contact interaction model.

9.33 point_contact_pair.hh File Reference

Class for a pair of point contact facets for use with contact interaction model.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "class_declarations.hh"
#include "contact_pair.hh"
```

Data Structures

· class jeod::PointContactPair

An point to point contact pair for use in the contact model.

Namespaces

· jeod

Namespace jeod.

9.33.1 Detailed Description

Class for a pair of point contact facets for use with contact interaction model.

9.34 spring_pair_interaction.cc File Reference

spring pair interaction for use in the contact model

```
#include <cmath>
#include "dynamics/derived_state/include/relative_derived_state.hh"
#include "dynamics/dyn_body/include/body_ref_frame.hh"
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "utils/math/include/vector3.hh"
#include "../include/contact_facet.hh"
#include "../include/spring_pair_interaction.hh"
```

Namespaces

• jeod

9.34.1 Detailed Description

spring pair interaction for use in the contact model

9.35 spring_pair_interaction.hh File Reference

A class for pair interactions based on a simple spring.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "pair_interaction.hh"
```

Data Structures

class jeod::SpringPairInteraction
 Simple spring contact parameters.

Namespaces

jeod

Namespace jeod.

9.35.1 Detailed Description

A class for pair interactions based on a simple spring.

Index

~Contact	jeod::PointContactFacet, 73
jeod::Contact, 18	check_contact
~ContactFacet	jeod::Contact, 19
jeod::ContactFacet, 26	check tree
~ContactPair	jeod::ContactPair, 36
jeod::ContactPair, 36	class_declarations.hh, 87
~ContactParams	collect_forces_torques
jeod::ContactParams, 42	jeod::ContactSurface, 45
~ContactSurface	Contact, 13
jeod::ContactSurface, 44	jeod::Contact, 18, 19
~ContactSurfaceFactory	contact.cc, 87
jeod::ContactSurfaceFactory, 48	contact.hh, 88
~LineContactFacet	contact_facet.cc, 88
jeod::LineContactFacet, 54	contact_facet.hh, 89
\sim LineContactFacetFactory	contact_facets
jeod::LineContactFacetFactory, 58	jeod::ContactSurface, 46
\sim LineContactPair	contact force
jeod::LineContactPair, 61	jeod::ContactSurface, 46
\sim LinePointContactPair	contact_limit_factor
jeod::LinePointContactPair, 65	jeod::Contact, 23
\sim PairInteraction	contact_messages.cc, 89
jeod::PairInteraction, 68	MAKE_CONTACT_MESSAGE_CODE, 90
\sim PointContactFacet	contact_messages.hh, 90
jeod::PointContactFacet, 73	contact_pair.cc, 91
\sim PointContactFacetFactory	contact_pair.hh, 91
jeod::PointContactFacetFactory, 77	
\sim PointContactPair	contact_pairs
jeod::PointContactPair, 80	jeod::Contact, 23
\sim SpringPairInteraction	contact_params.cc, 92
jeod::SpringPairInteraction, 84	contact_params.hh, 92
	contact_point
active	jeod::PointContactFacet, 76
jeod::Contact, 23	contact_surface.cc, 93
jeod::ContactFacet, 29	contact_surface.hh, 93
add_facet_params	contact_surface_factory.cc, 94
jeod::ContactSurfaceFactory, 49	contact_surface_factory.hh, 94
allocate_array	contact_torque
jeod::ContactSurface, 44	jeod::ContactSurface, 46
allocate_interaction_facet	contact_utils.hh, 95
jeod::ContactSurface, 45	contact_utils_inline.hh, 95
	ContactFacet
calculate_contact_point	jeod::ContactFacet, 26
jeod::LineContactFacet, 54	ContactMessages
jeod::PointContactFacet, 73	jeod::ContactMessages, 32
calculate_forces	ContactPair
jeod::PairInteraction, 69	jeod::ContactPair, 36
jeod::SpringPairInteraction, 84	ContactParams
calculate_torque	jeod::ContactParams, 42
jeod::ContactFacet, 26	ContactSurface
jeod::LineContactFacet, 55	jeod::ContactSurface, 44

ContactSurfaceFactory	jeod::LineContactFacet, 57
jeod::ContactSurfaceFactory, 48, 49	init_attrjeodLineContactFacetFactory
create_facet	jeod::LineContactFacetFactory, 60
jeod::LineContactFacetFactory, 59	init_attrjeodLineContactPair
jeod::PointContactFacetFactory, 78	jeod::LineContactPair, 63
create_pair	init_attrjeodLinePointContactPair
jeod::ContactFacet, 27	
jeod::LineContactFacet, 55	jeod::LinePointContactPair, 66
•	init_attrjeodPairInteraction
jeod::PointContactFacet, 74	jeod::PairInteraction, 70
create_relstate_name	init_attrjeodPointContactFacet
jeod::ContactUtils, 51	jeod::PointContactFacet, 75
create_surface	init_attrjeodPointContactFacetFactory
jeod::ContactSurfaceFactory, 49	jeod::PointContactFacetFactory, 79
create_vehicle_point	init_attrjeodPointContactPair
jeod::ContactFacet, 27	jeod::PointContactPair, 82
demonina de	init_attrjeodSpringPairInteraction
damping_b	jeod::SpringPairInteraction, 85
jeod::SpringPairInteraction, 85	initialization_error
dist_line_segments	jeod::ContactMessages, 33
jeod::ContactUtils, 52	initialization_warns
dyn_manager	jeod::ContactMessages, 33
jeod::Contact, 24	initialize_contact
	jeod::Contact, 20
facets_size	initialize_pair
jeod::ContactSurface, 47	jeod::ContactPair, 37
find_interaction	jeod::LineContactPair, 62
jeod::Contact, 19	jeod::LinePointContactPair, 65
friction_mag	jeod::PointContactPair, 81
jeod::PairInteraction, 70	initialize_relstate
	jeod::ContactPair, 38
get_name	InputProcessor
jeod::ContactFacet, 28	jeod::Contact, 23
get_subject	jeod::ContactFacet, 29
jeod::ContactPair, 36	jeod::ContactMessages, 32
get_target	jeod::Contactwessages, 32 jeod::ContactPair, 39
jeod::ContactPair, 37	jeod::ContactParams, 42
in_contact	jeod::ContactSurface, 46
jeod::ContactPair, 37	jeod::ContactSurfaceFactory, 50
jeod::LineContactPair, 62	jeod::LineContactFacet, 57
jeod::LinePointContactPair, 65	jeod::LineContactFacetFactory, 60
jeod::PointContactPair, 81	jeod::LineContactPair, 63
in_range	jeod::LinePointContactPair, 66
jeod::ContactPair, 37	jeod::PairInteraction, 70
init_attrjeodContact	jeod::PointContactFacet, 75
jeod::Contact, 22	jeod::PointContactFacetFactory, 79
init_attrjeodContactFacet	jeod::PointContactPair, 82
jeod::ContactFacet, 29	jeod::SpringPairInteraction, 85
init_attrjeodContactMessages	interaction
jeod::ContactMessages, 32	jeod::ContactPair, 39
init_attrjeodContactPair	interaction_distance
jeod::ContactPair, 39	jeod::ContactPair, 40
init_attrjeodContactParams	Interactions, 12
jeod::ContactParams, 42	is_active
init_attrjeodContactSurface	jeod::ContactPair, 38
jeod::ContactSurface, 46	is_complete
init_attrjeodContactSurfaceFactory	jeod::ContactPair, 38
jeod::ContactSurfaceFactory, 50	is_correct_factory
init_attrjeodLineContactFacet	jeod::LineContactFacetFactory, 59
	,

jeod::PointContactFacetFactory, 78	init_attrjeodContactPair, 39
is_correct_interaction	initialize_pair, 37
jeod::PairInteraction, 69	initialize_relstate, 38
icad 15	InputProcessor, 39
jeod, 15	interaction, 39
jeod::Contact, 17	interaction_distance, 40
~Contact, 18	is_active, 38
active, 23	is_complete, 38
check_contact, 19 Contact, 18, 19	operator=, 39
	rel_state, 40
contact_limit_factor, 23	subject, 40
contact_pairs, 23	target, 40
dyn_manager, 24	jeod::ContactParams, 41
find_interaction, 19	\sim ContactParams, 42
init_attrjeodContact, 22	ContactParams, 42
initialize_contact, 20	init_attrjeodContactParams, 42
InputProcessor, 23	InputProcessor, 42
operator=, 20	operator=, 42
pair_interactions, 24	jeod::ContactSurface, 43
register_contact, 20, 21	\sim ContactSurface, 44
register_interaction, 22	allocate_array, 44
unique_pair, 22	allocate_interaction_facet, 45
jeod::ContactFacet, 25	collect_forces_torques, 45
~ContactFacet, 26	contact facets, 46
active, 29	contact_force, 46
calculate_torque, 26	contact_torque, 46
ContactFacet, 26	ContactSurface, 44
create_pair, 27	facets_size, 47
create_vehicle_point, 27	init_attrjeodContactSurface, 46
get_name, 28	InputProcessor, 46
init_attrjeodContactFacet, 29	operator=, 45
InputProcessor, 29	jeod::ContactSurfaceFactory, 47
max_dimension, 29	~ContactSurfaceFactory, 48
normal, 29	add_facet_params, 49
operator=, 28	ContactSurfaceFactory, 48, 49
position, 30	create_surface, 49
set_max_dimension, 28	init_attrjeodContactSurfaceFactory, 50
surface_type, 30	InputProcessor, 50
vehicle_body, 30	line_contact_facet_factory, 50
vehicle_point, 30	operator=, 50
jeod::ContactMessages, 31	point_contact_facet_factory, 50
ContactMessages, 32	jeod::ContactUtils, 51
init_attrjeodContactMessages, 32	create_relstate_name, 51
initialization_error, 33	dist_line_segments, 52
initialization_warns, 33	jeod::LineContactFacet, 53
InputProcessor, 32	-
operator=, 32	~LineContactFacet, 54
pre_initialization_error, 33	calculate_contact_point, 54
runtime_error, 33	calculate_torque, 55
runtime_inform, 34	create_pair, 55
runtime_warns, 34	init_attrjeodLineContactFacet, 57
jeod::ContactPair, 34	InputProcessor, 57
~ContactPair, 36	length, 57
check_tree, 36	LineContactFacet, 54
ContactPair, 36	operator=, 56
get_subject, 36	set_max_dimension, 56
get_target, 37	jeod::LineContactFacetFactory, 57
in_contact, 37	~LineContactFacetFactory, 58
in_range, 37	create_facet, 59

init_attrjeodLineContactFacetFactory, 60	in_contact, 81
InputProcessor, 60	init_attrjeodPointContactPair, 82
is_correct_factory, 59	initialize pair, 81
LineContactFacetFactory, 58	InputProcessor, 82
operator=, 60	operator=, 81
jeod::LineContactPair, 60	point_subject, 82
~LineContactPair, 61	point_target, 82
in_contact, 62	PointContactPair, 80
init attrjeod LineContactPair, 63	jeod::SpringPairInteraction, 83
initialize pair, 62	~SpringPairInteraction, 84
InputProcessor, 63	calculate forces, 84
•	damping b, 85
line_subject, 63	init_attrjeodSpringPairInteraction, 85
line_target, 63	InputProcessor, 85
LineContactPair, 61	mu, 85
operator=, 62	operator=, 84
jeod::LinePointContactPair, 64	•
~LinePointContactPair, 65	spring_k, 85
in_contact, 65	SpringPairInteraction, 83, 84
init_attrjeodLinePointContactPair, 66	length
initialize_pair, 65	jeod::LineContactFacet, 57
InputProcessor, 66	-
line_subject, 66	line_contact_facet.cc, 96
LinePointContactPair, 64, 65	line_contact_facet.hh, 96
operator=, 66	line_contact_facet_factory
point_target, 67	jeod::ContactSurfaceFactory, 50
jeod::PairInteraction, 67	line_contact_facet_factory.cc, 97
\sim PairInteraction, 68	line_contact_facet_factory.hh, 97
calculate_forces, 69	line_contact_pair.cc, 98
friction_mag, 70	line_contact_pair.hh, 98
init_attrjeodPairInteraction, 70	line_point_contact_pair.cc, 99
InputProcessor, 70	line_point_contact_pair.hh, 99
is_correct_interaction, 69	line_subject
operator=, 70	jeod::LineContactPair, 63
PairInteraction, 68	jeod::LinePointContactPair, 66
params_1, 70	line_target
params_2, 71	jeod::LineContactPair, 63
jeod::PointContactFacet, 71	LineContactFacet
~PointContactFacet, 73	jeod::LineContactFacet, 54
calculate contact point, 73	LineContactFacetFactory
calculate_torque, 73	jeod::LineContactFacetFactory, 58
contact_point, 76	LineContactPair
create_pair, 74	jeod::LineContactPair, 61
init attrjeod PointContactFacet, 75	LinePointContactPair
InputProcessor, 75	jeod::LinePointContactPair, 64, 65
operator=, 75	
PointContactFacet, 72, 73	MAKE_CONTACT_MESSAGE_CODE
	contact_messages.cc, 90
radius, 76	max_dimension
set_max_dimension, 75	jeod::ContactFacet, 29
jeod::PointContactFacetFactory, 77	Models, 11
~PointContactFacetFactory, 77	mu
create_facet, 78	jeod::SpringPairInteraction, 85
init_attrjeodPointContactFacetFactory, 79	
InputProcessor, 79	normal
is_correct_factory, 78	jeod::ContactFacet, 29
operator=, 79	
PointContactFacetFactory, 77, 78	operator=
jeod::PointContactPair, 79	jeod::Contact, 20
\sim PointContactPair, 80	jeod::ContactFacet, 28

jeod::ContactMessages, 32	runtime_inform
jeod::ContactPair, 39	jeod::ContactMessages, 34
jeod::ContactParams, 42	runtime_warns
jeod::ContactSurface, 45	jeod::ContactMessages, 34
jeod::ContactSurfaceFactory, 50	jecanical national geo, or
jeod::LineContactFacet, 56	set_max_dimension
jeod::LineContactFacetFactory, 60	jeod::ContactFacet, 28
jeod::LineContactPair, 62	jeod::LineContactFacet, 56
jeod::LinePointContactPair, 66	jeod::PointContactFacet, 75
jeod::PairInteraction, 70	spring_k
jeod::PointContactFacet, 75	jeod::SpringPairInteraction, 85
jeod::PointContactFacetFactory, 79	spring_pair_interaction.cc, 104
jeod::PointContactPair, 81	spring_pair_interaction.hh, 105
jeod::SpringPairInteraction, 84	SpringPairInteraction
joodoprinigrammoradaen, or	jeod::SpringPairInteraction, 83, 84
pair_interaction.cc, 100	subject
pair interaction.hh, 100	jeod::ContactPair, 40
pair_interactions	surface_type
jeod::Contact, 24	jeod::ContactFacet, 30
PairInteraction	,
jeod::PairInteraction, 68	target
params_1	jeod::ContactPair, 40
jeod::PairInteraction, 70	
params_2	unique_pair
jeod::PairInteraction, 71	jeod::Contact, 22
point_contact_facet.cc, 101	
point_contact_facet.hh, 102	vehicle_body
point_contact_facet_factory	jeod::ContactFacet, 30
jeod::ContactSurfaceFactory, 50	vehicle_point
point_contact_facet_factory.cc, 102	jeod::ContactFacet, 30
point_contact_facet_factory.hh, 103	
point_contact_pair.cc, 103	
point_contact_pair.hh, 104	
point_subject	
jeod::PointContactPair, 82	
point_target	
jeod::LinePointContactPair, 67	
jeod::PointContactPair, 82	
PointContactFacet	
jeod::PointContactFacet, 72, 73	
PointContactFacetFactory	
jeod::PointContactFacetFactory, 77, 78	
PointContactPair	
jeod::PointContactPair, 80	
position	
jeod::ContactFacet, 30	
pre_initialization_error	
jeod::ContactMessages, 33	
,	
radius	
jeod::PointContactFacet, 76	
register_contact	
jeod::Contact, 20, 21	
register_interaction	
jeod::Contact, 22	
rel_state	
jeod::ContactPair, 40	
runtime_error	
jeod::ContactMessages, 33	