
# **QWT Installation & Usage**

Innova Lee(이상훈) gcccompil3r@gmail.com







## **Downloads**

Stable releases or prereleases are available at the Qwt project page.

For getting a snapshot with all bugfixes for the latest 5.2 release:

```
svn export svn://svn.code.sf.net/p/qwt/code/branches/qwt-5.2
```

For getting a snapshot with all bugfixes for the latest 6.1 release:

```
svn export svn://svn.code.sf.net/p/qwt/code/branches/qwt-6.1
```

For getting a development snapshot from the SVN repository:

```
svn export svn://svn.code.sf.net/p/qwt/code/trunk/qwt
```


## Installation

Qwt doesn't distribute binary packages, but today all major Linux distributors offer one. Note, that these packages often don't include the examples.


When no binary packages are available (f.e. on Windows) Qwt needs to be **compiled and installed** on the target system.

## Support

Mailing list



Sign Up





## qwt


Brought to you by: rathmann

Donate 🔼 Tickets ▼ Summary Files Reviews Support Mailing Lists News

### **Download Latest Version** qwt-6.1.3.zip (6.1 MB)

**Get Updates** 

Home / qwt / 6.1.2			
Name 💠	Modified 🔷	Size 🔷	Downloads / Week 💠
<b>Ĵ</b> Parent folder			
qwt-6.1.2.tar.bz2	2014-12-11	3.5 MB	14
qwt-6.1.2.zip	2014-12-11	5.3 MB	26
qwt-6.1.2.pdf	2014-12-11	2.6 MB	9 🛕
qwt-6.1.2.qch	2014-12-11	4.6 MB	Get latest updates abou Open Source Projects
Totals: 4 Items		16.1 MB	Conferences and New
			Sign Un



'ictorOps™ Integrations are Seamless & Easy. See For Yourself in a Free Trial! ictorops.com

```
Terminal File Edit View Search Terminal Help

sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/gst_proj$ cd ~/sw
sdr@sdr-Samsung-DeskTop-System:~/sw$ ls
iso opencv sdk vmware

sdr@sdr-Samsung-DeskTop-System:~/sw$ mkdir qwt
sdr@sdr-Samsung-DeskTop-System:~/sw$ cd qwt
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt$ ls
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt$ mv ~/Downloads/qwt-6.1.2.tar.bz2 ./
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt$ tar
jxvf qwt-6.1.2.tar.bz2
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt$ tar jxvf qwt-6.1.2.tar.bz2
```

```
Terminal File Edit View Search Terminal Help
qwt-6.1.2/examples/stockchart/plot.cpp
qwt-6.1.2/examples/stockchart/legend.cpp
qwt-6.1.2/examples/stockchart/plot.h
qwt-6.1.2/examples/stockchart/main.cpp
qwt-6.1.2/examples/sinusplot/
qwt-6.1.2/examples/sinusplot/sinusplot.pro
qwt-6.1.2/examples/sinusplot/sinusplot.cpp
qwt-6.1.2/INSTALL
_qwt-6.1.2/CHANGES-6.1
qwt-6.1.2/README
qwt-6.1.2/qwt.pro
qwt-6.1.2/qwt.prf
|qwt-6.1.2/designer/
qwt-6.1.2/designer/qwt designer plotdialog.cpp
gwt-6.1.2/designer/gwt designer plugin.grc
qwt-6.1.2/designer/qwt designer plugin.cpp
qwt-6.1.2/designer/qwt designer plotdialog.h
gwt-6.1.2/designer/designer.pro
qwt-6.1.2/designer/qwt designer plugin.h
gwt-6.1.2/designer/pixmaps/
gwt-6.1.2/designer/pixmaps/gwtplot.png
qwt-6.1.2/designer/pixmaps/qwtcompass.png
qwt-6.1.2/designer/pixmaps/qwtthermo.png
gwt-6.1.2/designer/pixmaps/gwtknob.png
qwt-6.1.2/designer/pixmaps/qwtwidget.png
qwt-6.1.2/designer/pixmaps/qwtdial.png
qwt-6.1.2/designer/pixmaps/qwtanalogclock.png
"qwt-6.1.2/designer/pixmaps/qwtcounter.png
qwt-6.1.2/designer/pixmaps/qwtscale.png
gwt-6.1.2/designer/pixmaps/gwtslider.png
qwt-6.1.2/designer/pixmaps/qwtwheel.png
 sdr@sdr-Samsung-DeskTop-System:~/sw/qwt$ ls
qwt-6.1.2 qwt-6.1.2.tar.bz2
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt$ cd qwt-6.1.2/
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$ ls
                                       gwtfunctions.pri
CHANGES-6.1 doc
                        playground
                                                         README
                       gwtbuild.pri
COPYING
             examples
                                       qwt.prf
                                                         STC
designer
             INSTALL
                       qwtconfig.pri qwt.pro
                                                         textengines
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$
```

```
😰 🖃 🗊 Terminal File Edit View Search Terminal Help
 sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$ ls
CHANGES-6.1 doc
COPYING exam
                        playground
                                       qwtfunctions.pri README
              examples qwtbuild.pri
                                       qwt.prf
                                                          STC
_designer
              INSTALL
                        gwtconfig.pri
                                                         textengines
                                       qwt.pro
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$ qmake qwt.pro
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$ ls
DICHANGES-6.1 doc
                        Makefile
                                      qwtconfig.pri
                                                        qwt.pro textengines
 COPYING
              examples playground
                                      qwtfunctions.pri
                                                        README
designer
              INSTALL
                        qwtbuild.pri qwt.prf
                                                         SFC
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$
```

```
Terminal File Edit View Search Terminal Help
 sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$ ls
CHANGES-6.1 doc
                       playground
                                      qwtfunctions.pri README
COPYING
             examples qwtbuild.pri
                                      qwt.prf
                                                        SIC
_designer
             INSTALL
                       qwtconfig.pri qwt.pro
                                                        textengines
sdr@sdr-Samsung-DeskTop-System:~/sw/gwt/gwt-6.1.2$ gmake gwt.pro
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.2$ ls
                       Makefile
                                     qwtconfig.pri
                                                       qwt.pro textengines
CHANGES-6.1 doc
                       playground
                                     qwtfunctions.pri
 COPYING
             examples
                                                       README
designer
             INSTALL
                       qwtbuild.pri qwt.prf
                                                       SIC
sdr@sdr-Samsung-DeskTop-System:~/sw/gwt/gwt-6.1.2$ make
cd src/ && ( test -e Makefile || /usr/lib/x86 64-linux-qnu/qt5/bin/qmake /home/sdr/sw/qw
t/qwt-6.1.2/src/src.pro -o Makefile ) && make -f Makefile
gmake[1]: Entering directory '/home/sdr/sw/qwt/qwt-6.1.2/src'
compiling gwt abstract scale draw.cpp
 compiling gwt clipper.cpp
.compiling gwt color map.cpp
 compiling qwt column symbol.cpp
 compiling gwt date.cpp
compiling gwt date scale draw.cpp
                                                아마 여기서 오류가 날 것임
rcompiling gwt date scale engine.cpp
 compiling gwt dyngrid layout.cpp
fcompiling qwt event pattern.cpp
compiling gwt graphic.cpp
 compiling qwt interval.cpp
compiling gwt interval symbol.cpp
```

```
ited, o to remove and 270 not approach.
 🔞 🗐 🕕 Terminal File Edit View Search Terminal Help
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt proj/18th$ vi /etc/apt/sources.list
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt_proj/18th$ cp /etc/apt/sources.list /et
c/apt/bak sources.list
cp: cannot create regular file '/etc/apt/bak sources.list': Permission denied
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt proj/18th$ sudo cp /etc/apt/sources.lis
t /etc/apt/bak sources.list
[sudo] password for sdr:
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt_proj/18th$ sudo vi /etc/apt/sources.lis
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt proj/18th$ sudo apt-get update
Hit:1 http://ppa.launchpad.net/maarten-baert/simplescreenrecorder/ubuntu xenial InRelease
Get:2 http://security.ubuntu.com/ubuntu xenial-security InRelease [107 kB]
Get:3 http://kaist.archive.ubuntu.com/ubuntu xenial InRelease [247 kB]
Hit:4 http://deb.playonlinux.com precise InRelease
Hit:5 http://ppa.launchpad.net/soylent-tv/screenstudio/ubuntu xenial InRelease
Get:6 http://kaist.archive.ubuntu.com/ubuntu xenial-updates InRelease [109 kB]
Get:7 http://kaist.archive.ubuntu.com/ubuntu xenial-backports InRelease [107 kB]
Get:8 http://kaist.archive.ubuntu.com/ubuntu xenial/main amd64 Packages [1.201 kB]
Get:9 http://kaist.archive.ubuntu.com/ubuntu xenial/main i386 Packages [1,196 kB]
Get:10 http://kaist.archive.ubuntu.com/ubuntu xenial/main Translation-en [568 kB]
Get:11 http://kaist.archive.ubuntu.com/ubuntu xenial/main amd64 DEP-11 Metadata [733 kB]
Get:12 http://kaist.archive.ubuntu.com/ubuntu xenial/main DEP-11 64x64 Icons [409 kB]
Get:13 http://kaist.archive.ubuntu.com/ubuntu xenial/restricted amd64 Packages [8,344 B]
Get:14 http://kaist.archive.ubuntu.com/ubuntu xenial/restricted i386 Packages [8,684 B]
Get:15 http://kaist.archive.ubuntu.com/ubuntu xenial/restricted Translation-en [2.908 B]
Get:16 http://kaist.archive.ubuntu.com/ubuntu xenial/restricted amd64 DEP-11 Metadata [186
B]
Get:17 http://kaist.archive.ubuntu.com/ubuntu xenial/universe amd64 Packages [7,532 kB]
32% [17 Packages 4,454 kB/7,532 kB 59%]
                                                                          467 kB/s 1min 7s
```

## 경우에 따라 /etc/apt/sources.list 수정

```
iteu, o to remove and 240 not upgradeu.
 🙉 🖨 📵 Terminal File Edit View Search Terminal Help
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt_proj/18th$ sudo apt-get install libowt-
dev
Reading package lists... Done
Building dependency tree
Reading state information... Done
The following additional packages will be installed:
  libgwt-headers libgwt6abi1
The following NEW packages will be installed:
  libqwt-dev libqwt-headers libqwt6abi1
0 upgraded, 3 newly installed, 0 to remove and 240 not upgraded.
Need to get 510 kB of archives.
After this operation, 2,067 kB of additional disk space will be used.
Do you want to continue? [Y/n] y
```

```
ted, o to remove and 240 not approach.
 🙉 🖨 📵 Terminal File Edit View Search Terminal Help
 97 alias alert='notify-send --urgency=low -i "$([ $? = 0 ] && echo terminal || echo error)
    " "$(history|tail -n1|sed -e '\''s/^\s*[0-9]\+\s*//;s/[;&|]\s*alert$//'\'')"'
 98
 99 # Alias definitions.
100 # You may want to put all your additions into a separate file like
101 # ~/.bash aliases, instead of adding them here directly.
102 # See /usr/share/doc/bash-doc/examples in the bash-doc package.
103
104 if [ -f ~/.bash aliases ]; then
        . ~/.bash aliases
105
106 fi
107
108 # enable programmable completion features (you don't need to enable
109 # this, if it's already enabled in /etc/bash.bashrc and /etc/profile
110 # sources /etc/bash.bashrc).
111 if ! shopt -og posix: then
    if [ -f /usr/share/bash-completion/bash completion ]; then
112
        . /usr/share/bash-completion/bash completion
113
     elif [ -f /etc/bash completion ]; then
114
115

    /etc/bash completion

116
117 fi
118
119 # Enable Vivado 2015 & Petalinux 2015
120 #source /home/sdr/petalinux zyng/petalinux-v2015.4-final/settings.sh
121 #source /opt/Xilinx/Vivado/2015.4/settings64.sh
122
123 # Enable Vivado 2017 & Petalinux 2017
124 source /opt/Xilinx/Vivado/2017.4/settings64.sh
125 source /opt/pkg/petalinux/settings.sh
126
127 # Enable OT5 OWT6
128 OT PLUGIN PATH="${OWT ROOT}/plugins:$OT PLUGIN PATH"
129
```

130 export OT PLUGIN PATH

- INSERT --

```
Terminal File Edit View Search Terminal Help
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt proj/18th$ sudo apt-get install gttools
5-dev
Reading package lists... Done
Building dependency tree
Reading state information... Done
The following NEW packages will be installed:
  attools5-dev
0 upgraded, 1 newly installed, 0 to remove and 240 not upgraded.
Need to get 188 kB of archives.
After this operation, 1,656 kB of additional disk space will be used.
Get:1 http://kaist.archive.ubuntu.com/ubuntu xenial-updates/universe amd64 qttools5-dev amd
64 5.5.1-3ubuntu0.1 [188 kB]
rFetched 188 kB in 1s (104 kB/s)
Selecting previously unselected package gttools5-dev:amd64.
(Reading database ... 252429 files and directories currently installed.)
Preparing to unpack .../qttools5-dev 5.5.1-3ubuntu0.1 amd64.deb ...
Unpacking gttools5-dev:amd64 (5.5.1-3ubuntu0.1) ...
Setting up gttools5-dev:amd64 (5.5.1-3ubuntu0.1) ...
sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt_proj/18th$
```

```
cannot ring rile: qwt.pr.
sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.3$ qmake qwt.pro
sdr@sdr-Samsung-DeskTop-System:~/sw/gwt/gwt-6.1.3$ make
cd src/ && ( test -e Makefile || /usr/lib/x86_64-linux-gnu/qt5/bin/qmake /home/sdr/sw/qwt/q
wt-6.1.3/src/src.pro -o Makefile ) && make -f Makefile
make[1]: Entering directory '/home/sdr/sw/gwt/gwt-6.1.3/src'
make[1]: Nothing to be done for 'first'.
make[1]: Leaving directory '/home/sdr/sw/qwt/qwt-6.1.3/src'
cd textengines/ && ( test -e Makefile || /usr/lib/x86 64-linux-gnu/gt5/bin/gmake /home/sdr/
sw/qwt/qwt-6.1.3/textengines/textengines.pro -o Makefile ) && make -f Makefile
make[1]: Entering directory '/home/sdr/sw/qwt/qwt-6.1.3/textengines'
make[1]: Nothing to be done for 'first'.
make[1]: Leaving directory '/home/sdr/sw/qwt/qwt-6.1.3/textengines'
cd doc/ && ( test -e Makefile || /usr/lib/x86 64-linux-qnu/qt5/bin/qmake /home/sdr/sw/qwt/q
wt-6.1.3/doc/doc.pro -o Makefile ) && make -f Makefile
make[1]: Entering directory '/home/sdr/sw/qwt/qwt-6.1.3/doc'
make[1]: Nothing to be done for 'first'.
make[1]: Leaving directory '/home/sdr/sw/qwt/qwt-6.1.3/doc'
cd designer/ && ( test -e Makefile || /usr/lib/x86 64-linux-gnu/qt5/bin/qmake /home/sdr/sw/
qwt/qwt-6.1.3/designer/designer.pro -o Makefile ) && make -f Makefile
make[1]: Entering directory '/home/sdr/sw/qwt/qwt-6.1.3/designer'
compiling gwt designer plugin.cpp
In file included from qwt designer plugin.h:13:0.
                 from qwt designer plugin.cpp:23:
/usr/include/x86_64-linux-gnu/qt5/QtDesigner/QDesignerCustomWidgetInterface:4:4: warning: #
warning Header <0tDesigner/0DesignerCustomWidgetInterface> is deprecated. Please include <0
tUiPlugin/ODesignerCustomWidgetInterface> instead. [-Wcpp]
   warning Header <QtDesigner/QDesignerCustomWidgetInterface> is deprecated. Please includ
compiling qwt designer plotdialog.cpp
rcc qwt designer plugin.qrc
compiling resources/qrc_qwt_designer_plugin.cpp
moc gwt designer plugin.h
compiling moc/moc_qwt_designer plugin.cpp
In file included from moc/../qwt_designer_plugin.h:13:0,
                 from moc/moc_qwt_designer_plugin.cpp:9:
```

🙉 🖃 🔟 Terminal File Edit View Search Terminal Help sdr@sdr-Samsung-DeskTop-System:~/sw/qwt/qwt-6.1.3\$ sudo make install cd src/ && ( test -e Makefile || /usr/lib/x86 64-linux-gnu/qt5/bin/qmake /home/sdr/sw/qwt/q wt-6.1.3/src/src.pro -o Makefile ) && make -f Makefile install make[1]: Entering directory '/home/sdr/sw/qwt/qwt-6.1.3/src' install -m 755 -p ../lib/libqwt.so.6.1.3 /usr/local/qwt-6.1.3/lib/libqwt.so.6.1.3 strip --strip-unneeded /usr/local/qwt-6.1.3/lib/libqwt.so.6.1.3 ln -f -s libqwt.so.6.1.3 /usr/local/qwt-6.1.3/lib/libqwt.so ln -f -s libqwt.so.6.1.3 /usr/local/qwt-6.1.3/lib/libqwt.so.6 ln -f -s libqwt.so.6.1.3 /usr/local/qwt-6.1.3/lib/libqwt.so.6.1 install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt.h /usr/local/qwt-6.1.3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt abstract scale draw.h /usr/local/qwt-6 .1.3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt\_clipper.h /usr/local/qwt-6.1.3/include install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt color map.h /usr/local/qwt-6.1.3/inclu de/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt compat.h /usr/local/qwt-6.1.3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt column symbol.h /usr/local/qwt-6.1.3/i nclude/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt date.h /usr/local/qwt-6.1.3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt date scale draw.h /usr/local/qwt-6.1.3 /include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt\_date\_scale\_engine.h /usr/local/qwt-6.1 .3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt dyngrid layout.h /usr/local/qwt-6.1.3/ include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt qlobal.h /usr/local/qwt-6.1.3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt graphic.h /usr/local/qwt-6.1.3/include install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt interval.h /usr/local/qwt-6.1.3/includ e/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt interval symbol.h /usr/local/qwt-6.1.3 /include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt math.h /usr/local/qwt-6.1.3/include/ install -m 644 -p /home/sdr/sw/qwt/qwt-6.1.3/src/qwt magnifier.h /usr/local/qwt-6.1.3/inclu

de/

```
🔊 🗐 🗊 Terminal File Edit View Search Terminal Help
        sleep 10; alert
 97 alias alert='notify-send --urgency=low -i "$([ $? = 0 ] && echo terminal ||
    echo error)" "$(history|tail -n1|sed -e '\''s/^\s*[0-9]\+\s*//;s/[;&|]\s*ale
    rt$//'\'')"'
 98
99 # Alias definitions.
100 # You may want to put all your additions into a separate file like
101 # ~/.bash aliases, instead of adding them here directly.
102 # See /usr/share/doc/bash-doc/examples in the bash-doc package.
103
104 if [ -f ~/.bash aliases ]; then
105
        . ~/.bash aliases
106 fi
107
108 # enable programmable completion features (you don't need to enable
109 # this, if it's already enabled in /etc/bash.bashrc and /etc/profile
110 # sources /etc/bash.bashrc).
111 if ! shopt -og posix: then
112
    if [ -f /usr/share/bash-completion/bash completion ]; then
113

    /usr/share/bash-completion/bash completion

      elif [ -f /etc/bash completion ]: then
114
115

    /etc/bash completion

116
      fi
117 fi
118
119 # Enable Vivado 2015 & Petalinux 2015
120 #source /home/sdr/petalinux zyng/petalinux-v2015.4-final/settings.sh
121 #source /opt/Xilinx/Vivado/2015.4/settings64.sh
122
123 # Enable Vivado 2017 & Petalinux 2017
124 source /opt/Xilinx/Vivado/2017.4/settings64.sh
125 source /opt/pkg/petalinux/settings.sh
126
127 # Enable OT5 OWT6
128 OT PLUGIN PATH="/usr/local/gwt-6.1.3/plugins:$OT PLUGIN PATH"
129 export OT PLUGIN PATH
130
131 # Enable LD LIB PATH
132 LD LIBRARY PATH=/usr/local/qwt-6.1.3/lib:$LD LIBRARY PATH
133 export LD LIBRARY PATH
                                                               133,1
                                                                             Bot
```

sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt\_proj/18th\$ qmake qt 18th.pro

#### sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt\_proj/18th\$ make

g++ -c -m64 -pipe -std=c++11 -O2 -Wall -W -D REENTRANT -fPIC -DQWT DLL -DQT NO D EBUG -DOT SVG LIB -DOT WIDGETS LIB -DOT GUI LIB -DOT CORE LIB -I. -I. -I/usr/loc al/qwt-6.1.3/include -I/usr/local/qwt-6.1.3 -isystem /usr/include/x86 64-linux-g nu/qt5 -isystem /usr/include/x86 64-linux-gnu/qt5/QtSvg -isystem /usr/include/x8 6 64-linux-qnu/qt5/0tWidgets -isystem /usr/include/x86 64-linux-qnu/qt5/0tGui -i system /usr/include/x86 64-linux-gnu/qt5/QtCore -I. -I/usr/lib/x86 64-linux-gnu/ qt5/mkspecs/linux-q++-6<u>4 -o CustomWidaet.o CustomWid</u>get.cpp

q++ -c -m64 -pipe -std= 🙉 🖹 🗊 Custom OwtDial EBUG -DOT SVG LIB -DOT al/qwt-6.1.3/include -I nu/qt5 -isystem /usr/in 6 64-linux-gnu/gt5/OtWi system /usr/include/x86 qt5/mkspecs/linux-q++-6 /usr/lib/x86 64-linux-g WIDGETS LIB -DOT GUI LI inux-q++-64 -I/home/sdr /qt proj/18th -I/usr/lo de/x86 64-linux-gnu/qt5 /x86 64-linux-gnu/qt5/Q /include/x86 64-linux-a linux-qnu/c++/5 -I/usr/ include -I/usr/local/in usr/include/x86 64-linu

50 60 30 - 80 20 10 90 35 km/h

NT -fPIC -DOWT DLL -DOT NO D CORE LIB -I. -I. -I/usr/loc /usr/include/x86 64-linux-g svg -isystem /usr/include/x8 36 64-linux-gnu/qt5/OtGui -i -I/usr/lib/x86 64-linux-gnu/

NO DEBUG -DOT SVG LIB -DOT 5 64-linux-gnu/qt5/mkspecs/l -I/home/sdr/lecture/Project local/qwt-6.1.3 -I/usr/inclu nu/qt5/QtSvg -I/usr/include 4-linux-qnu/qt5/OtGui -I/usr :++/5 -I/usr/include/x86 64-/lib/qcc/x86 64-linux-qnu/5/ inux-gnu/5/include-fixed -I/ lget.h -o moc CustomWidget.c

pр g++ -c -m64 -pipe -std=c++11 -O2 -Wall -W -D REENTRANT -fPIC -DOWT DLL -DOT NO D EBUG -DOT SVG LIB -DOT WIDGETS LIB -DOT GUI LIB -DOT CORE LIB -I. -I. -I/usr/loc al/qwt-6.1.3/include -I/usr/local/qwt-6.1.3 -isystem /usr/include/x86\_64-linux-g nu/qt5 -isystem /usr/include/x86 64-linux-gnu/qt5/OtSvg -isystem /usr/include/x8 6 64-linux-gnu/qt5/QtWidgets -isystem /usr/include/x86 64-linux-gnu/qt5/QtGui -i system /usr/include/x86 64-linux-gnu/qt5/OtCore -I. -I/usr/lib/x86\_64-linux-gnu/ qt5/mkspecs/linux-g++-64 -o moc CustomWidget.o moc CustomWidget.cpp q++ -m64 -Wl,-O1 -o qt 18th CustomWidget.o qt 18th.o moc CustomWidget.o -L/usr /X11R6/lib64 -L/usr/local/qwt-6.1.3/lib -lqwt /usr/local/qwt-6.1.3/lib/libqwt.so .6 -lQt5Svg -lQt5Widgets -lQt5Gui -lQt5Core -lGL -lpthread sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt proj/18th\$ ./qt 18th sdr@sdr-Samsung-DeskTop-System:~/lecture/Project/qt\_proj/18th\$ ./qt 18th