

DHCP 설치	
<pre>[root@localhost ~]# dnf -y install dhcp-server Last metadata expiration check: 1:46:41 ago on Wed Oct 22 16:07:23 2025. Dependencies resolved. ===== Package Architecture Version Repository Size ----- Installing: dhcp-server x86_64 12:4.4.2-19.b1.el9 baseos 1.2 M Installing dependencies: dhcp-common noarch 12:4.4.2-19.b1.el9 baseos 128 k Transaction Summary ----- Install 2 Packages Total download size: 1.3 M Installed size: 4.2 M Downloading Packages: (1/2): dhcp-common-4.4.2-19.b1.el9.noarch.rpm 1.3 MB/s 128 kB 00:00 (2/2): dhcp-server-4.4.2-19.b1.el9.x86_64.rpm 5.9 MB/s 1.2 MB 00:00 ----- Total 1.7 MB/s 1.3 MB 00:00 Running transaction check Transaction check succeeded. Running transaction test Transaction test succeeded. Running transaction Preparing : Installing : dhcp-common-12:4.4.2-19.b1.el9.noarch 1/2 Running scriptlet : dhcp-server-12:4.4.2-19.b1.el9.x86_64 2/2 Installing : dhcp-server-12:4.4.2-19.b1.el9.x86_64 2/2 Running scriptlet : dhcp-server-12:4.4.2-19.b1.el9.x86_64 2/2 Verifying : dhcp-common-12:4.4.2-19.b1.el9.noarch 1/2 Verifying : dhcp-server-12:4.4.2-19.b1.el9.x86_64 2/2 Installed: dhcp-common-12:4.4.2-19.b1.el9.noarch dhcp-server-12:4.4.2-19.b1.el9.x86_64 Complete!</pre>	<pre>[root@localhost ~]# rpm -qa grep dhcp dhcp-common-4.4.2-19.b1.el9.noarch dhcp-server-4.4.2-19.b1.el9.x86_64</pre>
dnf -y install dhcp-server dhcp설치	dhcp 설치 확인 : rpm -qa grep dhcp
<pre>[root@localhost ~]# cd /etc/dhcp/ [root@localhost dhcp]# mv dhcpd.conf dhcpd.conf.bak [root@localhost dhcp]# cp /usr/share/doc/dhcp-server/dhcpd.conf.example dhcpd.conf [root@localhost dhcp]# ls dhcpd.conf dhcpd.conf.bak dhcpd8.conf</pre>	<pre>vim /etc/dhcp/dhcpd.conf #설정 파일 수정하러 가기 default-lease-time 600; max-lease-time 7200; authoritative; #앞에 주석 없는지 확인 (있으면 지워주기) subnet 10.1.1.0 netmask 255.255.255.0 { range 10.1.1.10 10.1.1.254; option routers 10.1.1.1; option domain-name-servers 8.8.8.8; } #설정파일 맨 밑에 원하는 IP주소로 바꿔서 삽입</pre>
디렉토리 이동 -> dhcpd.conf를 dhcpd.conf.bak 변경 -> cp /usr/share/doc/dhcp-server/dhcpd.conf.example dhcpd.conf	conf파일 들어가서 주석 제거 밑 맨 아래 내용 추가 subnet 10.1.1.0 netmask 255.255.255.0 { range 10.1.1.10 10.1.1.170; option routers 10.1.1.1; option domain-name-servers 8.8.8.8; }
<pre>[root@localhost ~]# dnf -y install dhcp-server Last metadata expiration check: 1:46:41 ago on Wed Oct 22 16:07:23 2025. Dependencies resolved. ===== Package Architecture Version Repository Size ----- Installing: dhcp-server x86_64 12:4.4.2-19.b1.el9 baseos 1.2 M Installing dependencies: dhcp-common noarch 12:4.4.2-19.b1.el9 baseos 128 k Transaction Summary ----- Install 2 Packages Total download size: 1.3 M Installed size: 4.2 M Downloading Packages: (1/2): dhcp-common-4.4.2-19.b1.el9.noarch.rpm 1.3 MB/s 128 kB 00:00 (2/2): dhcp-server-4.4.2-19.b1.el9.x86_64.rpm 5.9 MB/s 1.2 MB 00:00 ----- Total 1.7 MB/s 1.3 MB 00:00 Running transaction check Transaction check succeeded. Running transaction test Transaction test succeeded.</pre>	
dnf -y install inxi = 예러방지	