



<Ubuntu – Jupyter 설치 및 설정>

<pre>(base) root@localhost:~# cd /tmp wget https://repo.anaconda.com/miniconda/Miniconda3-latest-linux-x86_64.sh -O miniconda.sh bash miniconda.sh -b -p /root/miniconda3 who "export PATH=\$PATH:/root/miniconda3/bin/" sudo tee -a /etc/bash.bashrc source /etc/bash.bashrc --2025-10-22 06:25:22-- https://repo.anaconda.com/miniconda/Miniconda3-latest-linux-x86_64.sh Resolving repo.anaconda.com (repo.anaconda.com)... 104.16.32.241, 104.16.191.158, 2006:4700:c810:20f1:: Connecting to repo.anaconda.com (repo.anaconda.com)[104.16.32.241]:443... connected. HTTP request sent, awaiting response... 200 OK Length: 162129736 (155M) [application/octet-stream] Saving to: 'miniconda.sh' miniconda.sh 100%[=====] 154.62M 11.2MB/s in 14s</pre>	[1단계 : Miniconda3 설치] cd /tmp # 다운로드 전용 임시폴더 wget https://repo.anaconda.com/miniconda/Miniconda3-latest-Linux-x86_64.sh -O miniconda.sh # 아나콘다 공식 홈페이지에서 최신 버전의 리눅스용 미니콘다 설치 파일 다운로드하고 그 파일의 이름을 간단하게 miniconda.sh로 저장하라는 의미																		
<pre>fi export PATH=\$PATH:/root/miniconda3/bin/</pre>	[2단계: 환경 설정] bash miniconda.sh -b -p /root/miniconda3 #다운로드한 미니콘다 설치 파일을 실행하고, 시스템 어디서든 conda 명령어를 쓸 수 있도록 경로를 설정하는 과정 echo "export PATH=\\$PATH:/root/miniconda3/bin/" sudo tee -a /etc/bash.bashrc source /etc/bash.bashrc # 터미널을 켤 때마다 conda 명령어의 위치를 자동으로 알려주도록 설정하는 과정																		
<pre>root@localhost:~# /root/miniconda3/bin/conda tos accept --override-channels --channel https://repo.anaconda.com/pkgs/main /root/miniconda3/bin/conda tos accept --override-channels --channel https://repo.anaconda.com/pkgs/r accepted Terms of Service for https://repo.anaconda.com/pkgs/main accepted Terms of Service for https://repo.anaconda.com/pkgs/r root@localhost:~# /root/miniconda3/bin/conda install -y jupyter 2 channel Terms of Service accepted Retrieving notices: done Channels: - default Platform: linux-64 Collecting package metadata (repodata.json): done Solving environment: done ## Package Plan ## environment location: /root/miniconda3 added / updated specs: - jupyter The following packages will be downloaded:</pre> <table><thead><tr><th>package</th><th>build</th><th>size</th></tr></thead><tbody><tr><td>anyio-4.10.0</td><td>py313h06a4308_0</td><td>292 KB</td></tr><tr><td>argon2-cffi-21.3.0</td><td>pyhd3eb1b0_0</td><td>15 KB</td></tr><tr><td>argon2-cffi-bindings-25.1.0</td><td>py313h06a4308_0</td><td>34 KB</td></tr><tr><td>asttokens-3.0.0</td><td>py313h06a4308_0</td><td>47 KB</td></tr><tr><td>async-lru-2.0.4</td><td>py313h06a4308_0</td><td>21 KB</td></tr></tbody></table>	package	build	size	anyio-4.10.0	py313h06a4308_0	292 KB	argon2-cffi-21.3.0	pyhd3eb1b0_0	15 KB	argon2-cffi-bindings-25.1.0	py313h06a4308_0	34 KB	asttokens-3.0.0	py313h06a4308_0	47 KB	async-lru-2.0.4	py313h06a4308_0	21 KB	[3단계: jupyter 설치] /root/miniconda3/bin/conda tos accept --override-channels --channel https://repo.anaconda.com/pkgs/main # 서비스 이용 약관 동의 (main 채널) /root/miniconda3/bin/conda tos accept --override-channels --channel https://repo.anaconda.com/pkgs/r # 서비스 이용 약관 동의 (r 채널)
package	build	size																	
anyio-4.10.0	py313h06a4308_0	292 KB																	
argon2-cffi-21.3.0	pyhd3eb1b0_0	15 KB																	
argon2-cffi-bindings-25.1.0	py313h06a4308_0	34 KB																	
asttokens-3.0.0	py313h06a4308_0	47 KB																	
async-lru-2.0.4	py313h06a4308_0	21 KB																	

	<pre>/root/miniconda3/bin/conda install -y jupyter # conda를 이용해 jupyter 패키지를 설치하는 최종 명령어</pre>
	[4단계: jupyter 비밀번호 설정] <pre>jupyter server password</pre>
<pre>root@u3:~# ufw allow 8000/tcp Rule added Rule added (v6) root@u3:~# ufw status Status: active To Action From -- 22/tcp ALLOW Anywhere 8000/tcp ALLOW Anywhere 22/tcp (v6) ALLOW Anywhere (v6) 8000/tcp (v6) ALLOW Anywhere (v6) root@u3:~# ufw allow 8001/tcp Rule added Rule added (v6) root@u3:~# ufw status Status: active To Action From -- 22/tcp ALLOW Anywhere 8000/tcp ALLOW Anywhere 8001/tcp ALLOW Anywhere 22/tcp (v6) ALLOW Anywhere (v6) 8000/tcp (v6) ALLOW Anywhere (v6) 8001/tcp (v6) ALLOW Anywhere (v6)</pre>	[5단계: 방화벽 설정] <pre>ufw allow 8000/tcp ufw allow 8001/tcp -> 혹시 몰라서..</pre>
	[6단계: 재부팅시 자동 활성화] <pre>vim /etc/systemd/system/jupyter.service</pre> [Unit] Description=Jupyter Notebook After=network.target [Service] Type=simple User=root WorkingDirectory=/root ExecStart=/root/miniconda3/bin/jupyter notebook --ip=172.16.16.222 --port=8000 --no-browser & Restart=always [Install] WantedBy=multi-user.target

	<pre>ExecStart=/root/miniconda3/bin/jupyter n o t e b o o k --config=/root/.jupyter/jupyter_server_conf g.json --ip=172.16.18.29 --port=8000 --no-browser --allow-root</pre> [Install] WantedBy=multi-user.target
<pre>root@localhost:/tmp# sudo vim /etc/systemd/system/jupyter.service root@localhost:/tmp# sudo systemctl daemon-reload sudo systemctl enable jupyter sudo systemctl start jupyter Created symlink /etc/systemd/system/multi-user.target.wants/jupyter.se rvice to /etc/systemd/system/jupyter.service. (base) root@localhost:~# systemctl status jupyter ● jupyter.service - Jupyter Notebook Loaded: loaded (/etc/systemd/system/jupyter.service; enabled; preset: enabled) Active: active (running) since Wed 2025-10-22 08:53:10 UTC; 33s ago Invocation: 5193e6e3662945a3a22e3433850cf5f1 Main PID: 1166 (jupyter-notebook) Tasks: 2 (limit: 3921) Memory: 143M (peak: 143.5M) CPU: 1.917s CGroup: /system.slice/jupyter.service └─1166 /root/.miniconda3/bin/python /root/.miniconda3/bin/jupyter-notebook --</pre>	[7단계: systemd 리로드 및 서비스 등록] <pre>sudo systemctl daemon-reload sudo systemctl enable jupyter sudo systemctl start jupyter</pre>