

우분투 FTP 매뉴얼 – Apache 설치 되어있어야됨

우분투 환경

설명

```
root@root:~# apt install -y vsftpd
vsftpd is already the newest version (3.0.5-0.1).
The following packages were automatically installed and are no longer required:
  libmecab2 libprotobuf-lite32t64 mecab-ipadic mecab-ipadic-utf8 mecab-utils
Use 'apt autoremove' to remove them.

Summary:
  Upgrading: 0, Installing: 0, Removing: 0, Not Upgrading: 10
root@root:~#
```

1. FTP 서버 설치 (vsftpd)

명령어 : `apt install -y vsftpd`

```
root@root:~# systemctl enable vsftpd
Synchronizing state of vsftpd.service with SysV service script with /usr/lib/systemd/s
ysdmd-sysv-install.
Executing: /usr/lib/systemd/systemd-sysv-install enable vsftpd
root@root:~#
```

2. vsftpd 서비스 부팅 시 자동 시작 설정

명령어 : `systemctl enable vsftpd`

```
root@root:~# systemctl start vsftpd
root@root:~# systemctl status vsftpd
● vsftpd.service - vsftpd FTP server
   Loaded: loaded (/usr/lib/systemd/system/vsftpd.service; enabled; preset: enabled)
   Active: active (running) since Wed 2025-10-22 14:33:37 UTC; 29min ago
  Invocation: 30a2ed00a6dc4009a7830ef685047453
    Main PID: 1830 (vsftpd)
      Tasks: 1 (limit: 3913)
     Memory: 1M (peak: 1.6M)
        CPU: 18ms
       CGroup: /system.slice/vsftpd.service
               └─1830 /usr/sbin/vsftpd /etc/vsftpd.conf

Oct 22 14:33:37 root systemd[1]: Starting vsftpd.service - vsftpd FTP server...
Oct 22 14:33:37 root systemd[1]: Started vsftpd.service - vsftpd FTP server.
root@root:~#
```

3. vsftpd 서비스 시작 및 상태 확인

명령어 : `systemctl start vsftpd`

`systemctl status vsftpd`

4. vsftpd 환경 설정 수정

명령어 : `vim /etc/vsftpd.conf`

설정 내용 수정

anonymous_enable=NO

→ 익명 사용자 접속 허용 여부

local_enable=YES

→ 우분투 사용자의 ftp 접속 허용(본인)

write_enable=YES

→ 파일 업로드, 삭제 등 쓰기 작업 허용 여부를 결정

chroot_local_user=YES

→ 로컬 사용자가 자신의 홈 디렉터리 바깥으로 이동하는 것을 차단 (보안상 권장)

5. 설정 적용으로 서비스 재시작

명령어 : `systemctl restart vsftpd`

6. 방화벽(ufw) 설정 및 규칙 적용

명령어 : `ufw allow 20/tcp`

`ufw allow 21/tcp`

`ufw reload # 적용`