










The screenshot shows a web browser window with the address bar displaying a URL from labs.surenetwork.com. The browser has several tabs open, including 'PNETLab | Topology', 'Terminal', and 'Isfaq-File/PROJECT/Projec'. The main content area shows a terminal window titled 'Win-1 x' with the following text:

```
C:\WINDOWS\system32\cmd.exe
Microsoft Windows XP [Version 5.1.2600]
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>ping 10.0.0.10


Pinging 10.0.0.10 with 32 bytes of data:

Reply from 10.0.0.10: bytes=32 time<1ms TTL=128
Reply from 10.0.0.10: bytes=32 time<1ms TTL=128
Reply from 10.0.0.10: bytes=32 time<1ms TTL=128
Reply from 10.0.0.10: bytes=32 time<1ms TTL=128

Ping statistics for 10.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms

C:\Documents and Settings\user>ping 15.0.0.10

Pinging 15.0.0.10 with 32 bytes of data:
```



```
R4
R4(config)#
R4(config)#ip route 10.0.0.0 255.0.0.0 172.19.0.1
R4(config)#ip route 20.0.0.0 255.0.0.0 172.19.0.1
R4(config)#ip route 30.0.0.0 255.0.0.0 172.19.0.1
R4(config)#ip route 21.0.0.0 255.0.0.0 172.19.0.1
R4(config)#ip route 192.168.168.0 255.255.255.0 172.19.0.1
R4(config)#ip route 162.14.0.0 255.255.0.0 172.19.0.1
R4(config)#
R4(config)#exit
R4#w
*Aug 25 03:17:05.879: %SYS-5-CONFIG_I: Configured from console by console
R4#write
Building configuration...
[OK]
R4#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
        a - application route
        + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 172.19.0.1
C    15.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
     15.0.0.0/8 is directly connected, Ethernet0/0
L    15.0.0.1/32 is directly connected, Ethernet0/0
S    20.0.0.0/8 [1/0] via 172.19.0.1
S    21.0.0.0/8 [1/0] via 172.19.0.1
S    30.0.0.0/8 [1/0] via 172.19.0.1
S    162.14.0.0/16 [1/0] via 172.19.0.1
C    172.19.0.0/16 is variably subnetted, 2 subnets, 2 masks
     172.19.0.0/16 is directly connected, Ethernet0/1
L    172.19.0.2/32 is directly connected, Ethernet0/1
S    192.168.168.0/24 [1/0] via 172.19.0.1
R4#
R4#
R4#
```

```
Chrome File Edit View History Bookmarks Profiles Tab Window Help 70% Tue Aug 25 8:43 AM
(130) WhatsApp x PNETLab | Topology x Terminal x Isfaq-File/PROJECT/Project x See Gateway Command x + Ask Gemini
labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWZlZjpbeyJuYW11IjojQilCJ1cmwiOiIvaHRtbDUvly9jbGllbnQvTXpFNE5EUXhPVGd5QUdNQWJYbH...
R4 x
% Invalid input detected at '^' marker.
R4(config)#ip add 172.19.0.2 255.255.0.0
% Invalid input detected at '^' marker.
R4(config)#int e0/1
R4(config-if)#ip add 172.19.0.2 255.255.0.0
R4(config-if)#no sh
R4(config-if)#exit
R4(config)#int e0/0
R4(config-if)#15.0.0.1 255.0.0.0
% Invalid input detected at '^' marker.
R4(config-if)#15.0.0.1 255.0.0.0
% Invalid input detected at '^' marker.
R4(config-if)#ip add 15.0.0.1 255.0.0.0
R4(config-if)#no sh
R4(config-if)#exit
R4(config)#exit
R4#sho
*Aug 25 03:12:37.998: %SYS-5-CONFIG_I: Configured from console by console
R4#show ip interface bref
% Invalid input detected at '^' marker.
R4#show ip interface brief
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 15.0.0.1 YES manual up up
Ethernet0/1 172.19.0.2 YES manual up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
R4#
R4#
R4#config t
Enter configuration commands, one per line. End with CNTL/Z.
R4(config)#
R4(config)#
R4(config)#
```

```
(130) WhatsApp x PNETLab | Topology x Terminal x Isfaq-File/PROJECT/Project x See Gateway Command x + Ask Gemini
labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWZlZjpbeyJuYW11Ijo1JmILCj1cmwiOiIvaHRtbDUvly9jbGllbnQvTXpFNE5ETXhPVGd5QUdNQWJYbH...
R3 x
Ethernet0/0      30.0.0.2      YES manual up      up
Ethernet0/1      172.19.0.1    YES manual up      up
Ethernet0/2      unassigned    YES TFTP up      up
Ethernet0/3      unassigned    YES TFTP down      down
R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#ip route 10.0.0.0 255.0.0.0 3
*Aug 25 03:00:05.375: %PNP-6-PNP DISCOVERY STOPPED: PnP Discovery stopped (Config Wizard)
R3(config)#ip route 10.0.0.0 255.0.0.0 30.0.0.1
R3(config)#ip route 20.0.0.0 255.0.0.0 30.0.0.1
R3(config)#ip route 15.0.0.0 255.0.0.0 30.0.0.1
R3(config)#no ip route 15.0.0.0 255.0.0.0 30.0.0.1
R3(config)#ip route 15.0.0.0 255.0.0.0 172.19.0.2
R3(config)#ip route 192.168.168.0 255.255.255.0 21.0.0.2
R3(config)#ip route 162.14.0.0 255.255.0.0 21.0.0.2
R3(config)#exit
R3#
*Aug 25 03:06:42.231: %SYS-5-CONFIG_I: Configured from console by console
R3#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
        a - application route
        + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

S    10.0.0.0/8 [1/0] via 30.0.0.1
S    15.0.0.0/8 [1/0] via 172.19.0.2
S    20.0.0.0/8 [1/0] via 30.0.0.1
C    30.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
        30.0.0.0/8 is directly connected, Ethernet0/0
L    30.0.0.2/32 is directly connected, Ethernet0/0
L    172.19.0.0/16 is variably subnetted, 2 subnets, 2 masks
C    172.19.0.0/16 is directly connected, Ethernet0/1
L    172.19.0.1/32 is directly connected, Ethernet0/1
R3#
R3#
```

```
R3#
R3#
R3#
R3#config t
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#int e0/0
R3(config-if)#ip add 30.0.0.2 255.0.0.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#int e0/1
R3(config-if)#ip add 172.19.0.1 255.255.0.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#exit
R3#wr
*Aug 25 02:39:36.817: %SYS-5-CONFIG_I: Configured from console by console
R3#write
Building configuration...
[OK]
R3#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
Ethernet0/0    30.0.0.2        YES manual  up          up
Ethernet0/1    172.19.0.1      YES manual  up          up
Ethernet0/2    unassigned      YES TFTP   up          up
Ethernet0/3    unassigned      YES TFTP   down        down
R3#
R3#
R3#
```



```
R2 x
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#exit
R2#s
*Aug 25 02:27:40.882: %SYS-5-CONFIG_I: Configured from console by console
R2#show ip interface brief
Interface                IP-Address      OK? Method Status          Protocol
Ethernet0/0              20.0.0.2        YES manual up              up
Ethernet0/1              30.0.0.1        YES manual up              up
Ethernet0/2              unassigned      YES TFTP  down            down
Ethernet0/3              unassigned      YES TFTP  down            down
R2#
*Aug 25 02:27:55.448: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2#wirte
Translating "wirte"

Translating "wirte"

% Bad IP address or host name
% Unknown command or computer name, or unable to find computer address
R2#write
Building configuration...
[OK]
R2#
R2#
R2#config t
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip route 10.0.0.0 255.0.0.0 20.0.0.1
R2(config)#ip route 172.19.0.0 255.255.0.0 30.0.0.2
R2(config)#ip route 15.0.0.0 255.0.0.0 30.0.0.2
R2(config)#ip route 21.0.0.0 255.0.0.0 30.0.0.2
R2(config)#ip route 192.168.168.0 255.255.255.0 30.0.0.2
R2(config)#ip route 162.14.0.0 255.255.0.0 30.0.0.2
^
% Invalid input detected at '^' marker.

R2(config)#ip route 162.14.0.0 255.255.0.0 30.0.0.2
R2(config)#
R2(config)#
R2(config)#
R2(config)#
```

```
(130) WhatsApp x | PNETLab | Topology x | Terminal x | Isfaq-File/PROJECT/ x | New Tab x | See Gateway Comm... x | + Ask Gemini
labs.surennetwork.com/store/public/admin/labs/terminal?terminals=eyJ0YWZzljpbeyJuYW11IjoUjilLCJ1cmwiOiIvaHRtbDUvly9jbGllbnQvTXpFNESESXhPVGd5QUdNQWJYbHpj...
R2 x
% Invalid input detected at '^' marker.
R2(config-if)#
R2(config-if)#
R2(config-if)#
R2(config-if)#
R2(config-if)#
R2(config-if)#
R2(config-if)#int e0/0
R2(config-if)#ip add 20.0.0.2 255.0.0.0
R2(config-if)#
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#int e0/1
R2(config-if)#ip add 30.0.0.1 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#exit
R2#s
*Aug 25 02:27:40.882: %SYS-5-CONFIG_I: Configured from console by console
R2#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
Ethernet0/0        20.0.0.2        YES manual up          up
Ethernet0/1        30.0.0.1        YES manual up          up
Ethernet0/2        unassigned      YES TFTP  down        down
Ethernet0/3        unassigned      YES TFTP  down        down
R2#
```

```
R1 x
[OK]
R1#show ip interface brief
Interface          IP-Address      OK? Method Status      Protocol
Ethernet0/0         10.0.0.1        YES manual up          up
Ethernet0/1         20.0.0.1        YES manual up          up
Ethernet0/2         unassigned      YES TFTP  down        down
Ethernet0/3         unassigned      YES TFTP  down        down
R1#
R1#
R1#
R1#
R1#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
R1(config)#ip route 30.0.0.1 255.0.0.0 20.0.0.2
%Inconsistent address and mask
R1(config)#ip route 30.0.0.0 255.0.0.0 20.0.0.2
R1(config)#ip route 172.19.0.0 255.255.0.0 20.0.0.2
R1(config)#ip route 15.0.0.0 255.0.0.0 20.0.0.2
R1(config)#ip route 21.0.0.0 255.0.0.0 20.0.0.2
R1(config)#ip route 192.168.168.0 255.255.255.0 20.0.0.2
R1(config)#ip route 162.14.0.0 255.255.0.0 20.0.0.2
R1(config)#
R1(config)#
R1(config)#route print
% Ambiguous command: "route print"
R1(config)#show router ip
^
% Invalid input detected at '^' marker.

R1(config)#exit
R1#
*Aug 25 02:16:43.322: %SYS-5-CONFIG_I: Configured from console by console
R1#show router ip
^
% Invalid input detected at '^' marker.

R1#route print
^
% Invalid input detected at '^' marker.

R1#show ip route
```

```
R1 x
R1#show router ip
^
% Invalid input detected at '^' marker.

R1#route print
^
% Invalid input detected at '^' marker.

R1#shoe ip route
^
% Invalid input detected at '^' marker.

R1#shoe ip router
^
% Invalid input detected at '^' marker.

R1#
R1#
R1#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
        D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
        N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
        E1 - OSPF external type 1, E2 - OSPF external type 2
        i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
        ia - IS-IS inter area, * - candidate default, U - per-user static route
        o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
        a - application route
        + - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

    10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C       10.0.0.0/8 is directly connected, Ethernet0/0
L       10.0.0.1/32 is directly connected, Ethernet0/0
S       15.0.0.0/8 [1/0] via 20.0.0.2
C       20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C       20.0.0.0/8 is directly connected, Ethernet0/1
L       20.0.0.1/32 is directly connected, Ethernet0/1
S       21.0.0.0/8 [1/0] via 20.0.0.2
S       30.0.0.0/8 [1/0] via 20.0.0.2
S       162.14.0.0/16 [1/0] via 20.0.0.2
--More--
```

```
R1#
R1#
R1#
R1#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
R1(config)#int e0/0
R1(config-if)#ip add 10.0.0.1
*Aug 25 02:04:23.423: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config-if)#ip add 10.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#int e0/1
R1(config-if)#ip add 20.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#exit
R1#w
*Aug 25 02:06:17.497: %SYS-5-CONFIG_I: Configured from console by console
R1#write
Building configuration...
[OK]
R1#show ip interface brief
Interface      IP-Address      OK? Method Status      Protocol
Ethernet0/0    10.0.0.1        YES manual up          up
Ethernet0/1    20.0.0.1        YES manual up          up
Ethernet0/2    unassigned      YES TFTP  down        down
Ethernet0/3    unassigned      YES TFTP  down        down
R1#
```