





Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
194
Router0
PC-PT
Samrat1 182.11.0.2
PC-PT
Samrat2 182.22.0.2






Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
1941
Router0
PC-PT
PC0
PC-PT
PC1



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
194
Router0
PC-PT
Samrat1 182.11.0.2
PC-PT
Samrat2 192.22.0.2


Samrat1 182.11.0.2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
182.11.0.2
Subnet Mask
255.255.0.0
Default Gateway
182.11.0.1
DNS Server
0.0.0.0
IPv6 Configuration
Automatic
Static
IPv6 Address
/
Link Local Address
FE80::205:5EFF:FE6E:D643
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password
Top



Router0
Physical
Config
CLI
Attributes
IOS Command Line Interface
Cisco IOS Software, C1900 Software (C1900-UNIVERSALK9-M), Version 15.1(4)M4,
RELEASE SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2012 by Cisco Systems, Inc.
Compiled Thurs 5-Jan-12 15:41 by pt_team
Image text-base: 0x2100F918, data-base: 0x24729040
This product contains cryptographic features and is subject to United
States and local country laws governing import, export, transfer and
use. Delivery of Cisco cryptographic products does not imply
third-party authority to import, export, distribute or use encryption.
Importers, exporters, distributors and users are responsible for
compliance with U.S. and local country laws. By using this product you
agree to comply with applicable laws and regulations. If you are unable
to comply with U.S. and local laws, return this product immediately.
A summary of U.S. laws governing Cisco cryptographic products may be found
at:
http://www.cisco.com/wwl/export/crypto/tool/stqrg.html
If you require further assistance please contact us by sending email to
export@cisco.com.
Cisco CISCO1941/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
2 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)
--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]:
Copy
Paste
Top



Router0
Press RETURN to get started!
Router>en
Router#
Copy
Paste
Top



Router0
Press RETURN to get started!
Router>en
Router#congig t
^
% Invalid input detected at '^' marker.
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname samrat
samrat(config)#
Copy
Paste
Top



Router0
Would you like to enter the initial configuration dialog? [yes/no]: no
Press RETURN to get started!
Router>en
Router#congig t
^
% Invalid input detected at '^' marker.
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname samrat
samrat(config)#enable secret samratpassword
samrat(config)#
Copy
Paste



Router0
samrat>
samrat>
samrat>en
Password:
samrat#
Copy
Paste



Router0
samrat>
samrat>
samrat>en
Password:
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#interface GigabitEthernet0/0
samrat(config-if)#
Copy
Paste
Top



Router0
Password:
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#interface GigabitEthernet0/0
samrat(config-if)#ip address 182.11.0.1 255.255.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
Copy
Paste
Top



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
x: 764, y: 277
1941
Router0
PC-PT
Samrat1 182.11.0.2
PC-PT
Samrat2 182.22.0.2



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router1
1941
Router2
50.0.0.1
60.0.0.1
2960-24TT
Switch0
2960-24TT
Switch1
PC-PT
Samrat01 50.0.0.2
PC-PT
Samrat02 60.0.0.2



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
1941
Router1
1941
Router2
2960-24TT
Switch0
2960-24TT
Switch1
PC-PT
PC2
PC-PT
PC3



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab11samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router1
1941
Router2
50.0.0.1
60.0.0.1
2960-24TT
Switch0
2960-24TT
Switch1
PC-PT
Samrat01 50.0.0.2
PC-PT
Samrat02 60.0.0.2



Samrat02 60.0.0.2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
60.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
60.0.0.1
DNS Server
0.0.0.0
IPv6 Configuration
Automatic
Static
IPv6 Address
Link Local Address
FE80::20D:BDFF:FEB9:92B5
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password
Top



Samrat01 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
50.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
50.0.0.1
DNS Server
0.0.0.0
IPv6 Configuration
Automatic
Static
IPv6 Address
/
Link Local Address
FE80::209:7CFF:FE7D:D7A8
Default Gateway
DNS Server
802.1X
Use 802.1X Security
Authentication
MD5
Username
Password
Top



Router1
Physical
Config
CLI
Attributes
IOS Command Line Interface
249856K bytes of ATA System CompactFlash 0 (Read/Write)
--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]: no
Press RETURN to get started!
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname samrat
samrat(config)#interface GigabitEthernet0/0
samrat(config-if)#ip address 50.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
samrat(config-if)#interface GigabitEthernet0/1
samrat(config-if)#ip address 70.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
Copy
Paste
Top



Samrat01 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 60.0.0.2
Pinging 60.0.0.2 with 32 bytes of data:
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Ping statistics for 60.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),



Samrat02 60.0.0.2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Reply from 60.0.0.1: Destination host unreachable.
Reply from 60.0.0.1: Destination host unreachable.
Reply from 60.0.0.1: Destination host unreachable.
Reply from 60.0.0.1: Destination host unreachable.
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Router1
samrat>
samrat>n
Translating "n"...domain server (255.255.255.255)
% Unknown command or computer name, or unable to find computer address
samrat>en
samrat#config t
Enter configuration commands, one per line. End with CNTL/Z.
samrat(config)#ip route 70.0.0.0 255.0.0.0 70.0.0.2
samrat(config)#ip route 40.0.0.0 255.0.0.0 70.0.0.2
samrat(config)#
Copy
Paste
Top



Router2
Press RETURN to get started.
samrat>en
samrat#config t
Enter configuration commands, one per line. End with CNTL/Z.
samrat(config)#ip route 70.0.0.0 255.0.0.0 70.0.0.1
samrat(config)#ip route 50.0.0.0 255.0.0.0 70.0.0.1
samrat(config)#
Copy
Paste
Top



Samrat01 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
C:\>clear
Invalid Command.
C:\>cls
Invalid Command.
C:\>ping 60.0.0.2
Pinging 60.0.0.2 with 32 bytes of data:
Request timed out.
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Ping statistics for 60.0.0.2:
Packets: Sent = 4, Received = 3, Lost = 1 (25% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\>ping 60.0.0.2
Pinging 60.0.0.2 with 32 bytes of data:
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Reply from 60.0.0.2: bytes=32 time<1ms TTL=126
Ping statistics for 60.0.0.2:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\>



C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Reply from 50.0.0.2: bytes=32 time<1ms TTL=126
Reply from 50.0.0.2: bytes=32 time<1ms TTL=126
Reply from 50.0.0.2: bytes=32 time<1ms TTL=126
Reply from 50.0.0.2: bytes=32 time=1ms TTL=126
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 1ms, Average = 0ms
C:\>






Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab13-samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
PC-PT
Samrat03 70.0.0.2
1941
Router3
2960-24TT
Switch2
PC-PT
Samrat01 50.0.0.2
PC-PT
Samrat02 60.0.0.3



Logical
Physical
PC-PT
PC5
1941
Router3
2960-24TT
Switch2
PC-PT
PC4
PC-PT
PC0



Samrat01 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
50.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
50.0.0.1
DNS Server
0.0.0.0
IPv6 Configuration



Samrat02 60.0.0.3
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
60.0.0.3
Subnet Mask
255.0.0.0
Default Gateway
60.0.0.1
DNS Server
0.0.0.0
IPv6 Configuration


Samrat03 70.0.0.2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
70.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
70.0.0.1
DNS Server
0.0.0.0


Router3
Physical
Config
CLI
Attributes
Cisco CISCO1941/K9 (revision 1.0) with 491520K/32768K bytes of memory.
Processor board ID FTX152400KS
2 Gigabit Ethernet interfaces
DRAM configuration is 64 bits wide with parity disabled.
255K bytes of non-volatile configuration memory.
249856K bytes of ATA System CompactFlash 0 (Read/Write)
--- System Configuration Dialog ---
Would you like to enter the initial configuration dialog? [yes/no]:
% Please answer 'yes' or 'no'.
Would you like to enter the initial configuration dialog? [yes/no]:
% Please answer 'yes' or 'no'.
Would you like to enter the initial configuration dialog? [yes/no]: no
Press RETURN to get started!
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname samrat
samrat(config)#intrface GigabitEthernet0/0
^
% Invalid input detected at '^' marker.
samrat(config)#interface GigabitEthernet0/0
samrat(config-if)#ip address 50.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-3-UPDOWN: Interface GigabitEthernet0/0, changed state to down
samrat(config-if)#xit
^
% Invalid input detected at '^' marker.
samrat(config-if)#exit
samrat(config)#interface GigabitEthernet0/1
samrat(config-if)#ip address 60.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-3-UPDOWN: Interface GigabitEthernet0/1, changed state to down
samrat(config-if)#exit
samrat(config)#ip address 60.0.0.1 255.0.0.0
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up


Samrat03 70.0.0.2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 60.0.0.3
Pinging 60.0.0.3 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 60.0.0.3:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>


Samrat02 60.0.0.3
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 70.0.0.2
Pinging 70.0.0.2 with 32 bytes of data:
Reply from 60.0.0.1: Destination host unreachable.
Reply from 60.0.0.1: Destination host unreachable.
Reply from 60.0.0.1: Destination host unreachable.
Reply from 60.0.0.1: Destination host unreachable.
Ping statistics for 70.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Router3
samrat>en
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#access-list 1deny host 60.0.0.3
                           ^
% Invalid input detected at '^' marker.
samrat(config)#access-list 1 deny host 60.0.0.3
samrat(config)#access-list 1 permit host 60.0.0.2
samrat(config)#interface GigabitEthernet0/1
samrat(config-if)#ip access-group 1 in
samrat(config-if)#exit
samrat(config)#
Copy
Paste
Top


```
C:\>ping 50.0.0.2


Pinging 50.0.0.2 with 32 bytes of data:


Reply from 50.0.0.2: bytes=32 time=1ms TTL=127
Reply from 50.0.0.2: bytes=32 time<1ms TTL=127
Reply from 50.0.0.2: bytes=32 time<1ms TTL=127
Reply from 50.0.0.2: bytes=32 time<1ms TTL=127


Ping statistics for 50.0.0.2:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
    Minimum = 0ms, Maximum = 1ms, Average = 0ms
```









Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab12-samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router0
1941
Router1
50.0.0.1
60.0.0.1
2960-24TT
2960-24TT
PC-PT
Samrat1 50.0.0.2
PC-PT
Samrat2 60.0.0.2



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab12-samratpaudel.pkt
Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router0
1941
Router1
50.0.0.1
60.0.0.1
2960-24TT
Switch0
2960-24TT
Switch1
PC-PT
Samrat1 50.0.0.2
PC-PT
Samrat2 60.0.0.2



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab12-samratpaudel.pkt
Logical
Physical
1941
Router0
1941
Router1
2960-24TT
Switch0
2960-24TT
Switch1
PC-PT
PC0
PC-PT
PC1



Samrat1 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
50.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
50.0.0.1
DNS Server
0.0.0.0



Samrat2 60.0.0.2
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
60.0.0.2
Subnet Mask
255.0.0.0
Default Gateway
60.0.0.1
DNS Server
0.0.0.0
IPv6 Configuration



Router0
Physical
Config
CLI
Attributes
IOS Command Line Interface
Would you like to enter the initial configuration dialog? [yes/no]: no
Press RETURN to get started!
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname samrat
samrat(config)#interface GigabitEthernet0/0
samrat(config-if)#ip address 50.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
samrat(config-if)#exit
samrat(config)#interface GigabitEthernet0/1
samrat(config-if)#ip address 70.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
Copy
Paste



Router1
Physical
Config
CLI
Attributes
IOS Command Line Interface
Press RETURN to get started!
Router>en
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname samrat
samrat(config)#interface GigabitEthernet0/0
samrat(config-if)#ip address 60.0.0.1 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
samrat(config-if)#exit
samrat(config)#interface GigabitEthernet0/1
samrat(config-if)#ip address 70.0.0.2 255.0.0.0
samrat(config-if)#no shutdown
samrat(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up
Copy
Paste



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab12-samratpaudel.pkt
File Edit Options View Tools Extensions Window Help
Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router0
1941
Router1
50.0.0.1
60.0.0.1
2960-24TT
Switch0
2960-24TT
Switch1
PC-PT
Samrat1 50.0.0.2
PC-PT
Samrat2 60.0.0.2



Samrat1 50.0.0.2
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 60.0.0.2
Pinging 60.0.0.2 with 32 bytes of data:
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Ping statistics for 60.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Samrat2 60.0.0.2
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Router0
samrat#en
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#router rip
samrat(config-router)#version 2
samrat(config-router)#nerwork 50.0.0.0
                      ^
% Invalid input detected at '^' marker.
samrat(config-router)#network 50.0.0.0
samrat(config-router)#network 70.0.0.0
Copy
Paste
Top



Router1
samrat>en
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#router rip
samrat(config-router)#version 2
samrat(config-router)#network 60.0.0.0
samrat(config-router)#network 70.0.0.0
samrat(config-router)#exit
samrat(config)#
Copy
Paste
Top



Samrat1 50.0.0.2
C:\>ping 60.0.0.2
Pinging 60.0.0.2 with 32 bytes of data:
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Ping statistics for 60.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Samrat2 60.0.0.2
C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Cisco Packet Tracer - C:\Users\ACER\Cisco Packet Tracer 9.0.0\saves\lab12-samratpaudel.pkt
Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router0
1941
Router1
50.0.0.1
60.0.0.1
PC-PT
samrat0 50.0.0.3
PC-PT
Samrat1 50.0.0.2
PC-PT
Samrat2 60.0.0.2
PC-PT
samrat4 50.0.0.3



samrat3 50.0.0.3
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 60.0.0.3
Pinging 60.0.0.3 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 60.0.0.3:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



samrat4 60.0.0.3
Command Prompt
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 50.0.0.3
Pinging 50.0.0.3 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 50.0.0.3:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>



Router0
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#routr ospf 1
                 ^
% Invalid input detected at '^' marker.
samrat(config)#router ospf 1
samrat(config-router)#network 70.0.0.0 255.0.0.0 area 0
samrat(config-router)#network 50.0.0.0 255.0.0.0 area 0
samrat(config-router)#exit
samrat(config)#
Copy
Paste
Top



Router1
samrat>en
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#router ospf 2
samrat(config-router)#network 70.0.0.0 255.0.0.0 area 0
samrat(config-router)#network 60.0.0.0 255.0.0.0 area 0
samrat(config-router)#exit
samrat(config)#
Copy
Paste
Top



samrat3 50.0.0.3
Pinging 50.0.0.3 with 32 bytes of data:
Reply from 50.0.0.3: bytes=32 time<1ms TTL=126
Reply from 50.0.0.3: bytes=32 time<1ms TTL=126
Reply from 50.0.0.3: bytes=32 time<1ms TTL=126
Reply from 50.0.0.3: bytes=32 time<1ms TTL=126
Ping statistics for 50.0.0.3:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\>



Logical
Physical
70.0.0.1
70.0.0.0
70.0.0.2
1941
Router0
1941
Router1
50.0.0.1
60.0.0.1
As 100
As 200
PC-PT
Samrat1 50.0.0.2
PC-PT
Samrat2 60.0.0.2



Samrat1 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 60.0.0.2
Pinging 60.0.0.2 with 32 bytes of data:
Reply from 50.0.0.1: Destination host unreachable.
Reply from 50.0.0.1: Destination host unreachable.
Request timed out.
Reply from 50.0.0.1: Destination host unreachable.
Ping statistics for 60.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
C:\>


Samrat2 60.0.0.2
Physical
Config
Desktop
Programming
Attributes
Command Prompt
X
Cisco Packet Tracer PC Command Line 1.0
C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),


Router0
samrat>en
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#router bgp 100
samrat(config-router)#network 70.0.0.0
samrat(config-router)#network 50.0.0.0
samrat(config-router)#neighbor 70.0.0.2 remote-as 200
samrat(config-router)#%BGP-5-ADCHANGE: neighbor 70.0.0.2 up
Copy
Paste
Top


Router1
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to
up
samrat>en
samrat#config t
Enter configuration commands, one per line.  End with CNTL/Z.
samrat(config)#router bgp 200
samrat(config-router)#ntwork 70.0.0.0
^
% Invalid input detected at '^' marker.
samrat(config-router)#network 70.0.0.0
samrat(config-router)#network 60.0.0.0
samrat(config-router)#neighbor 70.0.0.1 remote-as 100
samrat(config-router)#%BGP-5-ADCHANGE: neighbor 70.0.0.1 up
^


Samrat1 50.0.0.2
Physical
Config
Desktop
Programming
Attributes
C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Reply from 50.0.0.2: bytes=32 time<1ms TTL=126
Reply from 50.0.0.2: bytes=32 time=12ms TTL=126
Reply from 50.0.0.2: bytes=32 time=12ms TTL=126
Reply from 50.0.0.2: bytes=32 time=12ms TTL=126
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 12ms, Average = 9ms


Samrat2 60.0.0.2
Physical
Config
Desktop
Programming
Attributes
C:\>ping 50.0.0.2
Pinging 50.0.0.2 with 32 bytes of data:
Reply from 50.0.0.2: bytes=32 time<1ms TTL=128
Reply from 50.0.0.2: bytes=32 time=7ms TTL=128
Reply from 50.0.0.2: bytes=32 time<1ms TTL=128
Reply from 50.0.0.2: bytes=32 time=4ms TTL=128
Ping statistics for 50.0.0.2:
Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
Approximate round trip times in milli-seconds:
Minimum = 0ms, Maximum = 7ms, Average = 2ms
C:\>