Sabre | Airline | Solutions |

Documentation

Using Sabre OADP For NOFEP

DATED: 03/10/10

Prepared for

Sabre Communications/Airline Solutions

Prepared by

Sabre Inc. Ken Low Solution Architect Sabre Airlines Solutions


Configuring Sabre OADP For NOFEP

1. **IMPORTANT** *** Please make sure you OADP version is **4.6.0.19** before you continue. **NOFEP** only works with this version of OADP.


Please update to this version if you have older version of OADP or **Sabre Printing Module** (SPM). The software is available in the Sabre Community Portal.

- 2. Open the Sabre OADP printer software.
- 3. For Win2000 or XP, OADP is started via Services utility called Sabre Print
- 2. This action places an OADP Printer icon in the system tray (by default bottom right corner of main Windows desktop).
- 4. Move the cursor to the system tray in the bottom right corner beside time display and double-click the **Sabre OADP printer** icon to configure printers.


The Sabre Print window opens show below




5. Click on **Device**, select **Properties**.




6. Click on Add




7. Name the Printer. Under \underline{T} ype select Printer. Click **Next.**



8. Select the appropriate **COM** port. Click **Next**.




9. Configure all the appropriate **COMMS** Setting. Click **System Setting**.




10. Verify **COMM Port Properties** in **System Setting** matches **COMMS** setting on previous page.

Click **OK**, then **Next**.



11. Click Next.




12. Select **HSSP2**. Click **Configure Connection**.



13. Type **ACCESS.SABRE.COM** in the **Host Name** field. Type the **Printer LNIATA** in the **LNIATA** field.



14. Click **OK**. Then Click **Next, Finish and Close**. Then **RESTART SERVICES**.




IMPORTANT NOTE: NOFEP requires EACH Printer LNIATA to be configured for 3 OADP instances below

RES (ACCESS.SABRE.COM)


CERT (ACCESS.CERT.SABRE.COM)

TSTS (ACCESS.TSTS.SABRE.COM)

15. **Repeat Steps 4 to 14**. Change the Host Name using **ACCESS.CERT.SABRE.COM.** Keep the **SAME Printer LNIATA.**



15. **Repeat Steps 4 to 14**. Change the Host Name using ACCESS.TSTS.SABRE.COM. Keep the **SAME Printer LNIATA.**



16. **RESTART THE SERVICES** for the changes to take effect.