
Manejo de errores en PHP.


Configuración del archivo php.ini.

Paso1.


Ejecutamos la aplicación de xampp y hacemos clic en el botón de config



y abrimos el archivo PHP.ini el cual se abrirá de manera automática con el bloc de notas.



Dar clic en el menú editar y en la opción buscar y digitar error_reporting



Dar dos veces en el botón de búsqueda para llegar a la línea que debemos modificar

Se comenta la línea de error reporting marcada y se copia en la línea inferior

Tal como se muestra en la imagen

Y guardamos los cambio.

Posterior a esto buscamos la línea de Display_error unas líneas debajo de lo modificado

```
of PHP
  E_USER_DEPRECATED - user
                                     error reporting
  Common Values:
    E_ALL (Show all errors, warnings and notices including coding standards.)
    E_ALL & ~E_NOTICE (Show all errors, except for notices)
E_ALL & ~E_NOTICE & ~E_STRICT (Show all errors, except for notices and coding standards warnings.)
    E_COMPILE_ERROR|E_RECOVERABLE_ERROR|E_ERROR|E_CORE_ERROR (Show only errors)
  Default Value: E_ALL
  Development Value: E_ALL
  Production Value: E_ALL & ~E_DEPRECATED & ~E_STRICT
  http://php.net/error-reporting
  error_reporting=E_ALL & ~E_DEPRECATED & ~E_STRICT
error_reporting=E_ALL
; This directive controls whether or not and where PHP will output errors,
 notices and warnings too. Error output is very useful during development, but
; it could be very dangerous in production environments. Depending on the code
 which is triggering the error, sensitive information could potentially leak out of your application such as database usernames and passwords or worse.
  For production environments, we recommend logging errors rather than
  sending them to STDOUT.
 Possible Values:
    Off = Do not display any errors
    stderr = Display errors to STDERR (affects only CGI/CLI binaries!)
    On or stdout = Display errors to STDOUT
 Default Value: On
  Development Value: On
 Production Value: Off
  http://php.net/display-errors
display_errors=On
```

Debemos de verificar que la línea de display _ error se encuentre en estado ON, tal como se muestra en la imagen.

Guardamos los cambios En el archivo de PHP.ini y reiniciamos el apache en xampp

https://youtu.be/gXT48l3USng?si=siZWI_9dxurAln_0