

Robotics Competition 2019-20

Task 0.1 - Software Installation

This file contains the instructions to install the following software/ libraries:

- 1. Python
- 2. Numpy
- 3. Sympy
- 4. Octave
- 5. Octave Symbolic Package
- 6. Octave Control Package
- 7. Arduino IDE

Note: - Installation of software is tested on Windows 10

1. Python

- Download Python 3.7 for Windows <u>here</u>.
- On the first download screen, enable the "Add Python 3.7 to PATH" option.



Figure 1: Python Installation

- In order to verify the installation of Python:
 - Open command prompt, type python V and press Enter. (If you already have python 2.7 installed on your system, you should type py 3 V to confirm the installation of Python 3
 - You should see the prompt as shown in Figure 2.





2019-20



Figure 2: Verify Installation

Note - All programming in Stage 1 is to be done in Octave Programming Language. Python is required because some libraries of octave require Python to be installed.

2. Numpy

■ To install Numpy, open the command prompt and type the following command and press Enter:

pip install numpy

In case you already have Python 2.7 installed, you should use the pip3 command instead of pip

pip3 install numpy

In order to verify the installation, type the following command in command prompt and press Enter:

python -c "import numpy; print("numpy. version")"

■ You should see the command prompt as shown in Figure 3.





2019-20




Figure 3: Numpy Installation

3. Sympy

To install Sympy, open the command prompt and type the following command and press Enter:

pip install sympy

Use pip3 command if python 2.7 is already installed.

In order to verify the installation, type the following command in command prompt and press Enter:

python -c "import sympy; print("sympy. version")"

■ You should see the command prompt as shown in Figure 4.

Figure 4: Sympy Installation





2019-20

4. Octave

- Download Octave 5.1.0 version for Windows from here.
- Click on the installer. You will see the window as given in Figure 5(a).

■ Keep on clicking **Next** till installation is completed. You should see the following window as seen in Figure 5(b).




Figure 5(a): Octave Installation

Figure 5(b): Octave Installation

- Add Octave to PATH. Navigate to the Octave-5.1.0.0 folder where it is installed in your system.
- Navigate to the *Octave-5.1.0.0\mingw64\bin*. Copy the full path of the bin folder. The whole path should be similar to

C: Octave | Octave-5.1.0.0 | mingw64 | bin

Open command prompt and execute the following command: setx PATH=%PATH%;C:Octave\Octave-5.1.0.0\mingw64\bin

Note: The path specified should be the same as the path where octave is installed on your system.




Figure 6: Add Octave to PATH

■ Open command prompt and type octave. The Octave Prompt should appear. This means octave has been installed properly on your system.





2019-20




Figure 7: Octave Prompt

5. Octave Symbolic Package

Open the Octave software installed in your system. Type the following command in the command window and Press Enter:

pkg install -forge symbolic

■ Type the following command to check if symbolic has been installed correctly.

pkg load symbolic

■ If symbolic has been properly been installed, the command should execute without any error.




Figure 8: Install Symbolic





2019-20

6. Octave Control Package

■ Open the Octave software installed in your system. Type the following command in the command window and Press Enter:

pkg install -forge control

■ Type the following command to check if control has been installed correctly.

pkg load control

■ Type the following command to see if the proper version of control is installed.

pkg list

The total list of packages and their versions should show up. Control package latest version that needs to be installed is 3.2.0

7. Arduino IDE

- Download the Web Installer for Arduino from here.
- Run the installer and Install the Arduino Software on your system.




Figure 9: Arduino Installation