Activities

- 1. Open the BOM excel sheet
 - a. <a href="https://certisbelchim.sharepoint.com/:x:/r/sites/CertisBelchimD365/Shared%20Documents/General/Master%20Data%20Management/MDM%20Item/01CE/2.%20SELECTION/BOM%20FILE%20BBE%20MIGRATION.xlsx?d=w32bc1f07c7cd48b6abdbb13eb09ce597&csf=1&web=1
- 2. Color the line you are working on
- 3. Look up the PC sheet
 - a. https://certisbelchim.sharepoint.com/sites/BEXtechnical/PC%20Sheets/Forms/AllIte ms.aspx
- 4. Go to D365 released products (01CE company PROD)
 - a. Go to product and open it
- 5. Tab engineer
 - a. Add route
 - i. New, "route version"
 - ii. Copy value from BOM Excel document XXX
 - iii. Site "01CE"
 - iv. Save
 - v. Route version
 - 1. Approve
 - 2. Activate
 - b. Close the screen
- 6. Go to engineer, BOM version
 - a. Select "New BOM and BOM versions"
 - b. Select PC sheet number as "BOM number"
 - c. Copy "name" from BOM Excel
 - d. Fill site "01CE"
 - e. OK
- 7. Create BOM lines
 - a. First line is second item on the PC sheet. (Don't enter the item you are creating)
 - b. Warehouse check, correct?
 - c. Quantity from Pc sheet
 - d. Per series = "1000'
 - e. Operation number = "depending on BOM line" Select the correct one
 - i. Line type "item" = 15
 - ii. Line type "vendor" = 20, 21, 22...
 - 1. Fill Vendor on vendor account from BOM excel
 - 2. Check checkbox "End"
 - iii. If you are working on a "sub assy" you need to fill the "Density" if the data is available on the PC sheet.
- 8. Next BOM line
 - a. First line is Item number
 - b. Warehouse check. correct?
 - c. Quantity from BOM file
 - d. Per series = "1000'
 - e. Operation number = "depending on BOM line" Select the correct one
 - i. Line type "item" = 15

- ii. Line type "vendor" = 20, 21, 22...
- 9. Next BOM line... (Continue until completed all C lines from PC sheet
- 10. Add service fee (starting item number with 7)
 - a. Select the correct service item for Fee!
 - i. Line type "Vendor" means "operation number = 20, 21, 22...
 - ii. Fill vendor account from BOM Excel
 - 1. Check checkbox "End"
 - b. Save
 - c. Close screen
- 11. On BOM level
 - a. Go to attachments
 - b. Add an attachment of type "Packing instructions"
 - i. Add Packing instructions as description
 - ii. Fill description from PC sheet
 - iii. Copy notes from PC sheet to "Notes"
 - c. Add an attachment of type "BOM changes"
 - i. BOM changes as description
 - ii. Fill description from PC sheet
 - iii. Copy notes from PC sheet to "Notes"

Close, Done

Next 🕹