

How to Access RustDesk Remotely After a Power Outage

Step-by-Step Remote Connection Walkthrough, Pre-Login Authentication, and Outage Recovery

Target Host Machine:	DESKTOP-33BM44J (IP: 192.168.1.128)
Windows Service Status:	Running (Automatic) in Session 0 before logon
Unattended Authentication:	Permanent Password enabled (No physical screen confirmation needed)
Client Supported Platforms:	Windows, macOS, Linux, Android, iOS, iPadOS

1. The Outage Recovery Timeline (What Happens Automatically)

When power is restored to your home or office, the following chain executes without requiring any human presence at the PC:

Step	Event	System Mechanism
1. Power Restored	Motherboard boots immediately	Handled by BIOS setting 'Restore on AC Power Loss' -> Power On.
2. Windows Loads	Windows boots to Lock Screen	Operating system initializes drivers, Ethernet, and network stacks.
3. Service Launches	RustDesk Service starts in Session 0	The installed rustdesk Windows Service starts before any user signs in and connects to the ID/relay server.
4. Remote Ready	Host becomes accessible online	The host shows as online and available for incoming unattended sessions.

2. How to Connect from Your Remote Device

Follow these 5 simple steps from your phone, laptop, or remote workstation:

Step 1: Open RustDesk on Your Remote Device

- Launch the RustDesk app on your remote laptop, Mac, smartphone, or tablet.

Step 2: Enter the Target ID or IP

- In the 'Control Remote Desktop' box, type your host computer's **RustDesk ID** (or its local IP 192.168.1.128 if connected via the same local network / VPN).
- Click **Connect**.

Step 3: Enter Your RustDesk Password

- When prompted for password, enter your configured **Permanent Password**.
- (Tip: Check 'Remember password' on your personal device for 1-click future access).

Step 4: Unlock the Windows Login Screen

- Once connected, you will see the **Windows Lock / Sign-In Screen**.
- Click on the screen or click the top toolbar menu **Actions > Send Ctrl+Alt+Del**.
- Enter your standard Windows user account password or PIN to sign in to your desktop.

Step 5: Full Remote Control

- Your desktop, applications, files, and multi-monitor setup will now be fully interactive and controllable.

3. Practical Tips for Post-Outage Remote Management

Scenario / Feature	Recommendation & Action
Router Boot Delay	After a widespread power outage, your home Wi-Fi router / modem typically takes 2 to 4 minutes to reconnect to the Internet. Allow a few minutes after power returns before attempting the connection.
Sending Special Keys	Use the RustDesk toolbar at the top of your remote session to send system hotkeys: Ctrl+Alt+Del (to wake lock screen), Win+L (to lock screen when done), and Alt+Tab .
Remote Rebooting	If you need to restart the computer remotely in the future, you can safely restart from Windows Start menu or RustDesk toolbar; the background service will automatically come back online.