

RustDesk Readiness & Power Outage Checklist

Final Readiness Status, Power Outage Recovery Analysis, and Remaining User Action

Question 1: Is it ready to access right now?	YES (RustDesk client is running; server keys & binaries configured)
Question 2: Will it restart after power outage?	ALMOST (1 User Click Required)
Hardware AC Power Recovery (BIOS):	DONE (PC will automatically turn on & boot Windows)
Windows Pre-Login Service (Session 0):	PENDING (Requires clicking 'Install' in RustDesk client or running Setup)

1. Power Outage Timeline: What Happens When Power Returns

Here is exactly what happens during an outage cycle and where the current gap exists:

Stage	Mechanism	Status	Outcome
1. Electricity Returns	Motherboard BIOS restores AC power.	READY	PC boots automatically without needing to press the physical power button.
2. Windows Boots	Windows loads to the Lock / Sign-In Screen.	READY	Windows OS starts up and initializes network drivers.
3. Pre-Login Service	RustDesk service initializes in Session 0.	ACTION NEEDED	Current Gap: Because the Windows Service is not installed yet, RustDesk will wait for a user to log in before starting.
4. Remote Login	Remote user enters credentials via RustDesk.	PENDING #3	Once the service is installed, you can connect and type your Windows password remotely.

2. How to Close the Gap in 30 Seconds

Action 1: Click 'Install' in the RustDesk Client Window

- Bring up the **RustDesk** window on your screen.
- Click the **'Install'** button on the left sidebar / top card.
- Click **'Accept and Install'** and confirm the Windows UAC (Admin) prompt.
- This installs RustDesk to C:\Program Files\RustDesk\ and enables the background Windows Service that runs before login.

Action 2: Self-Hosted Server Setup (Optional for dedicated relay)

- We opened the rustdesk-server\ folder in File Explorer for you.
- Double-click **RustDeskServer.Setup.exe** and confirm the UAC prompt to install the server as a permanent background service.
- Configure client devices with IP: 192.168.1.128:21116 and Key: AiyzL2kd7b0z4smaSpvsE07og9tJEMEV8+QhEXkX6m0=