



BMBridge Lite — Quick-Start Guide

Get your first notes on a Bookmap chart in five minutes

BMBridge Lite 1.0 · SDE-Software (SDES.DEV)

Used at your own risk. No support is provided by SDES.DEV, Bookmap, Tom B, the Bookmap Discord channels, or the Bookmap support team. See the full disclaimer at the end of this document.

Version: Lite 1.0 **Audience:** First-time users who want to get notes on a Bookmap chart in under five minutes.

1. Launch the Program

- Run **BMBridge_Lite.exe** (or **python BMBridge_Lite.py** for the source build).

Windows SmartScreen Warning (first launch only)

On the first launch, Windows may display a blue "**Windows protected your PC**" dialog from SmartScreen. This is expected because BMBridge Lite is not code-signed. To proceed:

- 1 Click **More info** on the dialog.
- 2 Click **Run anyway**.

This warning will not reappear on subsequent launches on the same machine. Some third-party antivirus products may also prompt once — allow the program if you downloaded it from the intended source. If your antivirus blocks it outright, add an exception for the **BMBridge_Lite.exe** file.

Disclaimer Acceptance

- On first launch, the **About / Disclaimer** window appears. Read it in full and click **I Understand & Accept** to continue. Clicking **Decline & Exit** closes the program.

2. Set the Global Bookmap Symbol

- In the left panel, enter the Bookmap symbol string in the **Global Bookmap Symbol** field.
- Format example: **ESM6.CME@TM.Lite**
- This symbol is used for any feed that does not have its own **Symbol Override**.

3. Add a Note

- On the feed tab, fill in:
- **Description** — short label shown on the chart
- **Price** — numeric price level
- **Align** — text alignment on the chart
- **Draw Line** — whether to draw the horizontal price line
- Click **Text Color** / **BG Color** to pick colors.
- Click **ADD NEW**. The note appears as a card below.

4. Start the Servers

- Click **START SERVERS** on the left panel.
- The status light turns green (**LIVE**) and the per-feed LED on the feed tab also turns green.

- The **URL** field on the feed tab shows the address Bookmap needs, for example:

http://127.0.0.1:8000/Feed_1.csv

Windows Firewall prompt: the first time servers start, Windows Defender Firewall will prompt to allow BMBridge Lite through. The servers bind to **127.0.0.1** only (local machine, loopback) and do not accept external connections. Allow on **Private networks**; **Public networks** is not required and can be left unchecked.

5. Point Bookmap at the URL

- In Bookmap, open **Settings** → **Cloud Notes** (or the Custom Notes configuration panel for your Bookmap version).
- Add a new Cloud Notes source and paste the URL from step 4.
- Set the poll interval on Bookmap's side as desired.
- Save. Your notes should now render on the chart.

Reference: Bookmap's official Custom Notes documentation —

<https://bookmap.com/knowledgebase/docs/KB-Appendices-All-CustomNotes>

6. Editing Notes

- Click **SEL** on any note card to load it back into the entry form, then click **UPDATE**.
- Use ▲ ▼ to reorder, ■ to clone, ■ to delete.
- Uncheck the note's enable checkbox to hide it from the CSV output without deleting it.

7. Closing the Program

- Closing the window normally stops all servers.
- If **Minimize to tray on close** is checked in the left panel, closing hides the app to the system tray and servers keep running. Right-click the tray icon for **Show / Quit**.

Disclaimer

BMBridge Lite is provided **as-is** and is used at the user's own risk. **SDES.DEV, Bookmap, Tom B, the Bookmap Discord channels, and the Bookmap support team offer no support, walkthroughs, or individual assistance for this program.** Users are responsible for reading this guide, the full user manual, and the official Bookmap Cloud Notes documentation. Bugs and glitches will be addressed as they are identified; no service-level agreement is offered.