

Sistemle İlgili Ekran ve Sistemin Çalışma Görüntüleri

Ekran görüntüleri:

Pilot_PC

Physical Config **Desktop** Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.2.10

Subnet Mask 255.255.255.0

Default Gateway 192.168.2.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::201:64FF:FEBD:A509

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Merkez_Server

Physical Config Services **Desktop** Programming Attributes

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.10

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::20C:CFFF:FE1C:7C3E

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

Pegasus_HQ_Router

Physical Config **CLI** Attributes

IOS Command Line Interface

Press RETURN to get started.

Press RETURN to get started!

```
Pegasus_HQ_Router> enable
Pegasus_HQ_Router# configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Pegasus_HQ_Router(config)# interface gigabitEthernet 0/0
Pegasus_HQ_Router(config-if)# ip address 192.168.1.1 255.255.255.0
Pegasus_HQ_Router(config-if)# no shutdown

Pegasus_HQ_Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
exit
Pegasus_HQ_Router(config)# interface gigabitEthernet 0/1
Pegasus_HQ_Router(config-if)# ip address 10.0.0.1 255.255.255.0
Pegasus_HQ_Router(config-if)# no shutdown

Pegasus_HQ_Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up
exit
Pegasus_HQ_Router(config)#
```

Copy Paste

☐ Top

SAW_Router

Physical Config **CLI** Attributes

IOS Command Line Interface

Press RETURN to get started.

Press RETURN to get started!

```
SAW_Router>enable
SAW_Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
SAW_Router(config)#interface gigabitEthernet 0/0
SAW_Router(config-if)#ip address 192.168.2.1 255.255.255.0
SAW_Router(config-if)#no shutdown

SAW_Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/0, changed state to up



%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/0, changed state to up
exit
SAW_Router(config)#interface gigabitEthernet 0/1
SAW_Router(config-if)#ip address 10.0.0.2 255.255.255.0
SAW_Router(config-if)#no shutdown


SAW_Router(config-if)#
%LINK-5-CHANGED: Interface GigabitEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet0/1, changed state to up
exit
SAW_Router(config)#
```

Copy Paste

☐ Top





Cisco Packet Tracer - C:\Users\hp\Desktop\Bulut Bilgimi\Pegasus_Network_Projesi.pkt

File Edit Options View Tools Extensions Window Help

Logical Physical x: 1064, y: 201

Simulation Panel

Event List

Vis.	Time(sec)	Last Device
...	0.005	Switch0
...	0.006	Merkez_Server
...	0.007	Switch0
...	0.008	Pegasus_HQ_Router
...	0.009	SAW_Router
...	0.010	Switch1

Reset Simulation Constant Delay Captured to 0.010 s

Play Controls

Event List Filters - Visible Events

ACL Filter, ARP, BGP, Bluetooth, CAPWAP, CDP, DHCP, DHCPv6, DNS, DTCP, EAPOL, EIGRP, EIGRPv6, FTP, H.323, HSRP, HSRPv6, HTTP, HTTPS, ICMP, ICMPv6, ECN, IPsec, ISAKMP, IOT, IOT TCP, LACP, LLDP, MODBUS, NetFlow, NTP, OSPF, OSPFv6, RARP, POP3, PPP, PPPoE, PTP, ProfNet, RADIUS, REP, RIP, RIPng, RTP, SCCP, SMTP, SNMP, SSH, STP, SYSLOG, TACACS, TCP, TFTP, Telnet, UDP, USB, VTP

Edit Filters Show AllNone

Time: 00:09:36.063 PLAY CONTROLS

Scenario 0

New Delete

Toggle PDU List Window

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
...	Successful	Pilot_PC	Merkez_S...	ICMP	...	0.000	N	0	(e...	(delete)
...	In Progress	Pilot_PC	Pegasus_...	ICMP	...	0.000	N	1	(e...	(delete)

Realtime Simulation										
Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
...	Successful	Pilot_PC	Merkez_S...	ICMP	...	0.000	N	0	(e...	(delete)

Pegasus_Web

Physical Config Services **Desktop** Programming Attributes

IP Configuration X

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 10.0.0.3

Subnet Mask 255.0.0.0

Default Gateway 10.0.0.1

DNS Server 10.0.0.2

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::204:9AFF:FE51:790

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Pegasus_Mail

Physical Config Services **Desktop** Programming Attributes

IP Configuration X

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 10.0.0.4

Subnet Mask 255.0.0.0

Default Gateway 10.0.0.1

DNS Server 10.0.0.2

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::2E0:A3FF:FECA:538A

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Pegasus_DNS

Physical Config Services Desktop Programming Attributes

IP Configuration

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 10.0.0.5

Subnet Mask 255.0.0.0

Default Gateway 10.0.0.1

DNS Server 10.0.0.2

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::290:21FF:FE30:14AD

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Sistem

Sanal Makine Oluştur

Özet



Aşağıdaki tablo, yeni sanal makine için seçtiğiniz yapılandırmayı özetler. Yapılandırmadan memnun olduğunuzda, sanal makineyi oluşturmak için Bitir'e basın. Alternatif olarak, geri dönebilir ve yapılandırmayı değiştirebilirsiniz.

Makine Adı ve İS Türü	
Makine Adı	Pegasus_Merkez_Server
Makine Klasörü	C:/Users/hp/VirtualBox VMs/Pegasus_Merkez_Server
ISO Kalıbı	C:/Users/hp/Downloads/SERVER_EVAL_x64FRE_en-us.iso
Misafir İS Türü	Windows 2022 (64-bit)
Katılsız Yüklemeyi Atla	true

Donanım	
Ana Bellek	4096
İşlemci	2
EFI Etkin	false

Disk	
Disk Boyutu	35,00 GB
Tam Boyutu Önceden Ayır	false

Yardım Geri Bitir İptal



Sedanur ARSLAN-230710012

