



Criteria #1a: Secure network device configuration files – Both Firewalls: SSH, Policy Map

ASA5506-INTERNAL



The screenshot displays the configuration page for an ASA5506-INTERNAL device. The 'CLI' tab is selected, showing the following configuration commands:

```
access-list PUBLIC_TRAFFIC extended permit udp any host 199.199.199.1 eq domain
access-list PUBLIC_TRAFFIC extended permit icmp 172.21.2.0 255.255.255.0 host
199.199.199.1
access-list PUBLIC_TRAFFIC extended permit icmp any host 199.199.199.1
!
!
access-group PUBLIC_TRAFFIC in interface outside
aaa authentication ssh console LOCAL
!
username admin password k9r5AdXgwjIJsqLf encrypted
!
class-map inspection_default
  match default-inspection-traffic
!
policy-map type inspect dns preset_dns_map
  parameters
    message-length maximum 512
policy-map global_policy
  class inspection_default
    inspect dns preset_dns_map
    inspect ftp
    inspect tftp
!
service-policy global_policy global
!
telnet timeout 5
ssh 172.21.1.0 255.255.255.0 inside
ssh timeout 5
!
!
!
```



ASA DMZ

Physical Config CLI Attributes

IOS Command Line Interface

```
route outside 0.0.0.0 0.0.0.0 199.199.199.9 1
!
access-list OUTSIDEIN extended permit icmp any any
access-list OUTSIDEIN extended permit tcp any object webserver eq www
access-list OUTSIDEIN extended permit udp any object webserver eq domain
access-list OUTSIDEIN extended permit icmp any any echo
access-list OUTSIDEIN extended permit icmp any any echo-reply
access-list OUTSIDEIN extended permit tcp any object webserver eq 443
!
!
access-group OUTSIDEIN in interface outside
aaa authentication ssh console LOCAL
!
username admin password 89YenYLlCYftnmXP encrypted
!
class-map inspection_default
  match default-inspection-traffic
!
policy-map type inspect dns preset_dns_map
  parameters
    message-length maximum 512
policy-map global_policy
  class inspection_default
    inspect dns preset_dns_map
    inspect ftp
    inspect tftp
!
service-policy global_policy global
!
telnet timeout 5
ssh 10.10.10.0 255.255.255.0 DMZ
ssh timeout 5
!
!
!
!
DMZASA(config)#
```

Copy

Paste

Physical Config Desktop Programming Attributes

SSH Client


X

Password:

DMZASA>|

Criteria #1b: Secure network device NOC Switch: DHCP and VLANs

NOC Switch



The screenshot shows a web-based interface for a network device named "NOC-Dist-Sw". The interface has tabs for "Physical", "Config", "CLI", and "Attributes", with "CLI" currently selected. The main area displays the "IOS Command Line Interface" with a scrollable text box containing the following text:

```
%LINK-5-CHANGED: Interface GigabitEthernet2/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet2/1, changed state to up
%LINK-5-CHANGED: Interface GigabitEthernet3/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface GigabitEthernet3/1, changed state to up
Unauthorized Access is Prohibited

User Access Verification

Password:

NOC-Dist-Sw>enable
Password:
Password:
Password:
% Bad secrets

NOC-Dist-Sw>% Bad secrets

NOC-Dist-Sw>
NOC-Dist-Sw>enable
Password:
Password:
NOC-Dist-Sw#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
NOC-Dist-Sw(config)#interface GigabitEthernet0/1
NOC-Dist-Sw(config-if)#ex
NOC-Dist-Sw(config)#ex
NOC-Dist-Sw#
%SYS-5-CONFIG_I: Configured from console by console
show running-config | include dhcp
ip dhcp excluded-address 172.21.2.1 172.21.2.99
ip dhcp excluded-address 172.21.1.1 172.21.2.99
ip dhcp pool VL200-GUEST-WIFI
NOC-Dist-Sw#
```

Below the text box are "Copy" and "Paste" buttons. At the bottom left of the interface is a "Top" button.

NOC-Dist-Sw#show vlan brief

VLAN	Name	Status	Ports
1	default	active	Gig5/1
100	Vlan100	active	
200	Vlan200	active	Gig0/1, Gig1/1, Gig2/1, Gig3/1 Gig4/1
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005	trnet-default	active	

NOC-Dist-Sw#show running-config | section vlan


```
switchport access vlan 200
switchport access vlan 200
switchport access vlan 200
switchport access vlan 200
switchport access vlan 200
switchport trunk allowed vlan 2-99,101-1001
switchport trunk allowed vlan 2-99,101-1001
switchport trunk allowed vlan 2-99,101-1001
switchport trunk allowed vlan 2-99,101-1001
```

NOC-Dist-Sw#

Copy

Paste

Criteria #2a: Secure Server Services Primary Server: Certification Authority Properties General Tab



zeroday-ZDSRV1-JAAB-CA Properties

Extensions	Storage	Certificate Managers	
Enrollment Agents	Auditing	Recovery Agents	Security
General	Policy Module	Exit Module	

Certification authority (CA)

Name: zeroday-ZDSRV1-JAAB-CA

CA certificates:

Certificate #0

View Certificate

Cryptographic settings

Provider: Microsoft Software Key Storage Provider

Hash algorithm: SHA256

OK Cancel Apply Help

Criteria #2b: Secure Server Services Primary Server: Advanced Settings screen from the ZeroDay Website

 Server Certificates

Use this feature to request and manage certificates that the Web server can use with websites configured for SSL.

Filter:	Go	Show All	Group by:	No Grouping
Name	Issued To	Issued By	Expiration Date	Certificate Hash
	www.zeroday.local	zeroday-ZDSRV1-JAAB-CA	7/17/2026 9:37:39 ...	C4BE82597B988F66690634159...
FTPCert	ZDDMZ1-JAAB.zeroday.local	ZDDMZ1-JAAB.zeroday.local	7/13/2026 5:00:00 ...	5B9C9766129B3B268C39FBEA...

Edit Site Binding



Type: https IP address: All Unassigned Port: 443

Host name:

☐ Require Server Name Indication

☐ Disable HTTP/2

☐ Disable OCSP Stapling

SSL certificate:

www.zeroday.local


Select...

View...

OK

Cancel

Connections



SSL Settings

This page lets you modify the SSL settings for the content of a website or application.

☒ Require SSL

Client certificates:

☐ Ignore

☒ Accept

☐ Require

zeroday.local

← → ↻ <https://www.zeroday.local>

Welcome to the Internal Web Server