

Instalación y uso de Portainer CE en Ubuntu Server para gestionar Docker

Version de docker

```
serralta@serralta: ~  
serralta@serralta:~$ docker --version  
Docker version 28.2.2, build 28.2.2-0ubuntu1~24.04.1  
serralta@serralta:~$
```

1-Instalación de Portainer CE

PASO1: Crear un volumen persistente

`sudo docker volume create portainer_data`

```
serralta@serralta:~$ sudo docker volume create portainer_data  
[sudo] password for serralta:  
portainer_data
```

PASO2: Desplegar el contenedor de Portainer

```
sudo docker run -d \  
-p 9000:9000 \  
-p 9443:9443 \  
--name=portainer \  
--restart=always \  
-v /var/run/docker.sock:/var/run/docker.sock \  
-v portainer_data:/data \  
portainer/portainer-ce:latest
```

```
serralta@serralta:~$ sudo docker run -d \  
-p 9000:9000 \  
-p 9443:9443 \  
--name=portainer \  
--restart=always \  
-v /var/run/docker.sock:/var/run/docker.sock \  
-v portainer_data:/data \  
portainer/portainer-ce:latest  
Unable to find image 'portainer/portainer-ce:latest' locally  
latest: Pulling from portainer/portainer-ce  
22d4f45bf667: Pull complete  
089b96337e3d: Pull complete  
c551c6af3241: Pull complete  
9f7772ceb88a: Pull complete  
d35c85f36345: Pull complete  
f3e139b9cd66: Pull complete  
2d896f38a01e: Pull complete  
4f4fb700ef54: Pull complete  
Digest: sha256:d38a6876b61df32e4da13c0ca61cf2aa0f27afc103abb4ca7ad4e1cf000e17c3  
Status: Downloaded newer image for portainer/portainer-ce:latest  
07a48f088dd3ec4034549cefe6818df288bad3a9ea195621fecda13594c254a8  
serralta@serralta:~$
```

2- Acceso y configuración inicial

Crea el usuario administrador **admin** / **admin123456789**

PORTAINER.IO

New Portainer installation

Please create the initial administrator user.

Username: admin

Password:

Confirm password: ✓

⚠ The password must be at least 12 characters long. ✓

Create user

☒ Allow collection of anonymous statistics. You can find more information about this in our [privacy policy](#).

> Restore Portainer from backup

Environments

Home

admin

Environments

Search by name, group, tag, status, URL... x

Refresh

Kubeconfig

Click on an environment to manage

Plat... Con... Stat... Tags Gro... Age... Clear all S... ↓↑

local Up 2025-11-16 13:24:30 Standalone 28.2.2 /var/run/docker.sock

Group: Unassigned No tags Local

1 stack 3 containers 3 0 0 0 5 volumes

3 images 1 CPU 4.1 GB RAM

Live connect

Disconnected

Items per page 10

