

NAME : SHAH FAISAL

ROLL NO : 23I-0058


SECTION : BSE – 6A

CNET LAB 08

BSSE SPRING 2026

LAB 08

Task 1: Implementing Inter-VLAN Routing (15 Marks)



PC1 Configuration

Physical Config Desktop Programming Attributes

IP Configuration

Interface: FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address: 192.168.1.6

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.1.1

DNS Server: 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address: /

Link Local Address: FE80::2D0:D3FF:FED5:948E

Default Gateway:

DNS Server:

802.1X

☐ Use 802.1X Security

Authentication: MD5

Username:

Password:

☐ Top

Root

Name : Shah Faisal
Roll Number : 23I-0058
Section : Bse-6A

Realtime Simulation

Logical

Physical

Switch0

Physical Config CLI Attributes

IOS Command Line Interface

```

10 Faculty active
20 Students active
30 Guests active
1002 fddi-default active
1003 token-ring-default active
1004 fddinet-default active
1005 trnet-default active
Switch#enable
Switch#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int range fa0/2-3
Switch(config-if-range)#switchport mode access
Switch(config-if-range)#switchport access vlan 10
Switch(config-if-range)#exit
Switch(config)#int range fa0/4-5
Switch(config-if-range)#switchport mode access
Switch(config-if-range)#switchport access vlan 20
Switch(config-if-range)#exit
Switch(config)#int range fa0/6-7
Switch(config-if-range)#switchport mode access
Switch(config-if-range)#switchport access vlan 30
Switch(config-if-range)#exit
Switch(config)#do wr
Building configuration...
[OK]
Switch(config)#
          
```

Copy Paste

Root

Name : Shah Faisal
 Roll Number : 231-0058
 Section : Bse-6A

Log

Switch0

Physical Config CLI Attributes

IOS Command Line Interface

```

Switch(config)#enable
% Incomplete command.
Switch(config)#exit
Switch#
$SYS-5-CONFIG_I: Configured from console by console

Switch#enable
Switch#config terminal
Enter configuration commands, one per line. End with
CNTL/Z.
Switch(config)#int fa0/1
Switch(config-if)#switchport mode trunk

Switch(config-if)#switchport mode trunk

Switch(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/1, changed state to down


%LINEPROTO-5-UPDOWN: Line protocol on Interface
FastEthernet0/1, changed state to up

Switch(config-if)#exit
Switch(config)#do wr
Building configuration...
[OK]
Switch(config)#
          
```

Copy Paste


Root

Name : Shah Faisal
 Roll Number : 231-0058
 Section : Bse-6A



Time: 0

Realtime Simulation




The screenshot shows the Cisco Packet Tracer interface with Router1 selected. The CLI window displays the following configuration commands:

```

GigabitEthernet0/0.10, changed state to up
Router(config-subif)#encapsulation dot1q 10
Router(config-subif)#ip address 192.168.1.1 255.255.255.0
Router(config-subif)#exit
Router(config)#int gig0/0.20
Router(config-subif)#
%LINK-3-UPDOWN: Interface GigabitEthernet0/0.20, changed
state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface
GigabitEthernet0/0.20, changed state to up
Router(config-subif)#encapsulation dot1q 20
Router(config-subif)#ip address 192.168.2.1 255.255.255.0
Router(config-subif)#int gig0/0.30
Router(config-subif)#
%LINK-3-UPDOWN: Interface GigabitEthernet0/0.30, changed
state to down
%LINEPROTO-5-UPDOWN: Line protocol on Interface
GigabitEthernet0/0.30, changed state to up
Router(config-subif)#encapsulation dot1q 30
Router(config-subif)#ip address 192.168.3.1 255.255.255.0
Router(config-subif)#exit
Router(config)#do wr
Building configuration...
[OK]
Router(config)#
  
```

Other visible elements include a text editor window with the student's name and ID, and a network diagram showing a PC connected to the router.



The screenshot displays a network topology in Cisco Packet Tracer. A central 2950 switch is connected to a 2911 router and several PCs. The PCs are organized into three groups, each with a default gateway:

- Group 1 (Left):** PC-PT PC0 and PC-PT PC1. Default Gateway: 192.168.1.1.
- Group 2 (Bottom):** PC-PT PC2 and PC-PT PC3. Default gateway: 192.168.2.1.
- Group 3 (Right):** PC-PT PC4 and PC-PT PC5. Default gateway: 192.168.3.1.

The right sidebar shows the Simulation Panel with an Event List table:

Vis.	Time(sec)	Last Device
	0.001	PC0
	0.001	--
	0.001	--
	0.002	PC2
	0.002	--
	0.002	--
	0.003	Switch0

Below the table are simulation controls (Reset, Play, Pause, Stop) and a list of visible events (ACL, Filter, ARP, BGP, etc.).

