
❖ TOPIC:- HARDWARE

Module_2-Day_4:

❖ Tasks:

1. **Connect a USB webcam to your computer, install any required drivers, and verify that the webcam works by opening the default camera app and capturing a photo.**

⇨



❖ Steps to Connect and Test a USB Webcam:

(1) **Connect the webcam:** Plug the USB webcam into an available USB port on the computer.
(2) **Install the driver:** Allow Windows to install the driver automatically. If required, download the correct driver from the manufacturer's official website.
(3) **Open the Camera app:** Click the Windows Start menu, search for Camera, and open the app.
(4) **Check the webcam:** Ensure that the webcam video appears on the screen.
(5) **Capture a photo:** Click the camera button to take a photo.
(6) **Verify the result:** Open the captured photo and confirm that the image is clear and properly saved.

2. Set up a local printer (USB or network), install the correct driver, and print a test page to confirm successful installation.

⇨

❖ Steps to Set Up a Local Printer and Print a Test Page:

(1) **Connect the printer:** Turn on the printer and connect it to the computer using a USB cable.
(2) **Install the driver:** Allow Windows to install the driver automatically, or download the correct driver from the printer manufacturer's official website.
(3) **Open printer settings:** Go to Settings → Bluetooth & devices → Printers & scanners in Windows 11. On Windows 10, go to Settings → Devices → Printers & scanners.
(4) **Add the printer:** Click Add device and select your printer if it is not already listed.
(5) **Open printer properties:** Select your printer and open Printer properties.
(6) **Print a test page:** Click Print Test Page and wait for the page to print.

3. **Simulate a connectivity issue by unplugging the printer's USB cable, then use Windows Device Manager to identify and resolve the 'printer not detected' problem.

Hint: Check for error icons and use the 'Scan for hardware changes' option after reconnecting.**

⇨

❖ Troubleshooting Steps: Printer Connectivity

(1) **Disconnect the printer:** Unplug the printer's USB cable from the computer to simulate a connectivity problem.
(2) **Open Device Manager:** Press Windows + X and select Device Manager.
(3) **Check the printer status:** Expand Printers, Print queues, or Universal Serial Bus controllers. Check whether the printer is missing or displays a yellow warning icon.
(4) **Reconnect the printer:** Plug the USB cable back into the computer and ensure the printer is switched on.
(5) **Scan for hardware changes:** In Device Manager, click Action → Scan for hardware changes. Windows will search for the reconnected printer.
(6) **Verify the solution:** Check whether the printer appears in Device Manager without an error icon. Open Settings → Bluetooth & devices → Printers & scanners to confirm that Windows detects it.

4. **A user reports that their webcam video is not displaying in Zoom, but it works in the default camera app. Troubleshoot and resolve the issue so the webcam works in both applications.

Hint: Check if another app is using the webcam or if Zoom permissions are enabled.**

⇨

❖ Troubleshooting Steps: Webcam Not Working in Zoom

(1) **Close other applications:** Close the Camera app and any other application that may be using the webcam.
(2) **Check Zoom camera settings:** Open Zoom, go to Settings → Video, and select the correct webcam from the camera dropdown menu.
(3) **Enable camera permissions:** In Windows, open Settings → Privacy & security → Camera and turn on camera access and Let desktop apps access your camera.
(4) **Restart Zoom:** Completely close Zoom, reopen it, and join the meeting again.
(5) **Test the webcam:** Open Zoom's video settings and check whether the webcam preview is displaying correctly.
(6) **Update Zoom:** If the webcam still does not work, update Zoom to the latest version and restart the computer.