Commands

Fire Router:

Router>en

Router#conf t

Router(config)#hostname Fire

Fire(config)#interface fa0/0

Fire(config-if)#ip address 192.168.7.1 255.255.255.0

Fire(config-if)#no shut

Fire>en

Fire#conf t

Fire(config)#int Se0/0/0

Fire(config-if)#ip address 192.168.8.193 255.255.255.252

Fire(config-if)#no shut

Fire(config-if)#exit

Fire(config)#int Se0/0/1

Fire(config-if)#ip address 192.168.8.201 255.255.255.252

Fire(config-if)#no shut

Fire(config-if)#exit

Fire(config)#int Se0/1/0

Fire(config-if)#ip address 192.168.8.205 255.255.255.252

Fire(config-if)#no shut

Fire>en

Fire#conf t

Fire(config)#ip route 192.168.8.128 255.255.255.192 se0/0/0

Fire(config)#ip route 192.168.6.0 255.255.255.0 se0/0/0

Fire(config)#ip route 192.168.6.0 255.255.255.0 se0/0/0 5

Fire(config)#router rip

Fire(config-router)#version 2

Fire(config-router)#no auto-summary

Fire(config-router)#network 192.168.7.0

Fire(config-router)#network 192.168.8.204

Fire(config-router)#redistribute static

Fire(config-router)#exit

Fire(config)#end

Fire#copy run start

Fire#show ip route

Fire>en

Fire#conf t
Fire(config)#int fa0/0
Fire(config-if)#ip helper-address 192.168.8.132

Water Router:

Router>en

Router#conf t

Router(config)#int fa0/0

Router(config-if)#ip address 192.168.8.129 255.255.255.192

Router(config-if)#no shut

Router(config-if)#exit

Router(config)#int se0/0/0

Router(config-if)#ip address 192.168.8.194 255.255.255.252

Router(config-if)#no shut

Router>en

Router#conf t

Router(config)#int Se0/0/1

Router(config-if)#ip address 192.168.8.197 255.255.255.252

Router(config-if)#no shut

Router(config-if)#exit

Router(config)#hostname Water

Water>en

Water#conf t

Water(config)#ip route 192.168.8.200 255.255.255.252 se0/0/0

Water(config)#ip route 192.168.8.204 255.255.255.252 se0/0/0

Water(config)#ip route 192.168.8.208 255.255.255.252 se0/0/0

Water(config)#ip route 192.168.8.212 255.255.255.252 se0/0/0

Water(config)#ip route 192.168.7.0 255.255.255.0 se0/0/0

Water(config)#ip route 192.168.6.0 255.255.255.0 se0/0/1

Water(config)#ip route 192.168.0.0 255.255.252.0 se0/0/0

Water(config)#ip route 192.168.4.0 255.255.254.0 se0/0/0

Water(config)#ip route 192.168.8.0 255.255.255.128 se0/0/0

Water(config)#exit

Mind Router:

Router>en

Router#conf t

Router(config)#hostname Mind

Mind(config)#int fa0/0

Mind(config-if)#ip address 192.168.6.1 255.255.255.0

Mind(config-if)#no shut

Mind(config-if)#exit

Mind(config)#int se0/0/0

Mind(config-if)#ip address 192.168.8.198 255.255.255.252

Mind(config-if)#no shut

Mind(config-if)#exit

Mind(config)#int se0/0/1

Mind(config-if)#ip address 192.168.8.202 255.255.255.252

Mind(config-if)#no shut

Mind>en

Mind#conf t

Mind(config)#ip route 192.168.8.192 255.255.255.252 se0/0/0

Mind(config)#ip route 192.168.8.204 255.255.255.252 se0/0/0

Mind(config)#ip route 192.168.8.208 255.255.255.252 se0/0/0

Mind(config)#ip route 192.168.8.212 255.255.255.252 se0/0/0

Mind(config)#ip route 192.168.8.128 255.255.255.192 se0/0/0

Mind(config)#ip route 192.168.7.0 255.255.255.0 se0/0/0

Mind(config)#ip route 192.168.7.0 255.255.255.0 se0/0/1 5

Mind(config)#ip route 192.168.0.0 255.255.252.0 se0/0/0

Mind(config)#ip route 192.168.4.0 255.255.254.0 se0/0/0

Mind(config)#ip route 192.168.8.0 255.255.255.128 se0/0/0

Mind>en

Mind#conf t

Mind(config)#int fa0/0

Mind(config-if)#ip helper-address 192.168.8.132

Wind Router:

Router>en

Router#conf t

Router(config)#hostname Wind

Wind(config)#int fa0/0

Wind(config-if)#ip address 192.168.0.1 255.255.252.0

Wind(config-if)#no shut

Wind(config-if)#exit

Wind(config)#int se0/0/0

Wind(config-if)#ip address 192.168.8.209 255.255.255.252

Wind(config-if)#no shut

Wind(config-if)#exit

Wind(config)#int se0/0/1

Wind(config-if)#ip address 192.168.8.213 255.255.255.252

Wind(config-if)#no shut

Wind(config-if)#exit

Wind(config)#int se0/1/0

Wind(config-if)#ip address 192.168.8.206 255.255.255.252

Wind(config-if)#no shut

Wind>en

Wind#conf t

Wind(config)#router rip

Wind(config-router)#version 2

Wind(config-router)#no auto-summary

Wind(config-router)#network 192.168.8.204

Wind(config-router)#network 192.168.8.208

Wind(config-router)#network 192.168.8.212

Wind(config-router)#network 192.168.0.0

Wind(config-router)#end

Wind#copy run start

Wind>en

Wind#conf t

Wind(config)#int fa0/0

Wind(config-if)#ip helper-address 192.168.8.132

Speed router:

Router>en

Router#conf t

Router(config)#hostname Speed

Speed(config)#int fa0/0

Speed(config-if)#ip address 192.168.4.1 255.255.254.0

Speed(config-if)#no shut

Speed(config-if)#exit

Speed(config)#int se0/0/0

Speed(config-if)#ip address 192.168.8.210 255.255.255.252

Speed(config-if)#no shut

Speed>en

Speed#conf t

Speed(config)#router rip

Speed(config-router)#version 2

Speed(config-router)#no auto-summary

Speed(config-router)#network 192.168.8.208

Speed(config-router)#network 192.168.4.0

Speed(config-router)#end

Speed#copy run start

Intelligence router:

Router>en

Router#conf t

Router(config)#int fa0/0

Router(config-if)#ip address 192.168.8.1 255.255.255.128


Router(config-if)#no shut

Router(config-if)#exit

Router(config)#hostname Intelligence Intelligence(config)#int se0/0/0 Intelligence(config-if)#ip address 192.168.8.214 255.255.252 Intelligence(config-if)#no shut

Intelligence>en
Intelligence#conf t
Intelligence(config)#router rip
Intelligence(config-router)#version 2
Intelligence(config-router)#no auto-summary
Intelligence(config-router)#network 192.168.8.212
Intelligence(config-router)#network 192.168.8.0
Intelligence(config-router)#end
Intelligence#copy run start

Intelligence>en
Intelligence#conf t
Intelligence(config)#int fa0/0
Intelligence(config-if)#ip helper-address 192.168.8.132



IP Address Table

Device	Interface	IP address	Subnet Mask	Def. Gateway
Fire	Fa0/0	192.168.7.1	255.255.255.0	N/A
	Se0/0/0	192.168.8.193	255.255.255.252	N/A
	Se0/0/1	192.168.8.201	255.255.255.252	N/A
	Se0/1/0	192.168.8.205	255.255.255.252	N/A
Water	Fa0/0	192.168.8.129	255.255.255.192	N/A
	Se0/0/0	192.168.8.194	255.255.255.252	N/A
	Se0/0/1	192.168.8.197	255.255.255.252	N/A
Mind	Fa0/0	192.168.6.1	255.255.255.0	N/A
	Se0/0/0	192.168.8.198	255.255.255.252	N/A
	Se0/0/1	192.168.8.202	255.255.255.252	N/A
Wind	Fa0/0	192.168.0.1	255.255.252.0	N/A
	Se0/0/0	192.168.8.209	255.255.255.252	N/A
	Se0/0/1	192.168.8.213	255.255.255.252	N/A
	Se0/1/0	192.168.8.206	255.255.255.252	N/A
Speed	Fa0/0	192.168.4.1	255.255.254.0	N/A
	Se0/0/0	192.168.8.210	255.255.255.252	N/A
Intelligence	Fa0/0	192.168.8.1	255.255.255.128	N/A
	Se0/0/0	192.168.8.214	255.255.255.252	N/A
PC_Fire	Fa0	192.168.7.2 (DHCP)	255.255.255.0	192.168.7.1
PC_Water	Fa0	192.168.8.130	255.255.255.192	192.168.8.129
PC_Mind	Fa0	192.168.6.2 (DHCP)	255.255.255.0	192.168.6.1
PC_Wind	Fa0	192.168.0.2 (DHCP)	255.255.252.0	192.168.0.1
PC_Speed	Fa0	192.168.4.2	255.255.254.0	192.168.4.1
PC_Intelligence	Fa0	192.168.8.2 (DHCP)	255.255.255.128	192.168.8.1

Device	Interface	IP address	Subnet Mask	Def. Gateway
Printer_Fire	0	192.168.7.3 (DHCP)	255.255.255.0	192.168.7.1
Printer_Water	0	192.168.8.131	255.255.255.192	192.168.8.129
Printer_Mind	0	192.168.6.3 (DHCP)	255.255.255.0	192.168.6.1
Printer_Wind	0	192.168.0.3 (DHCP)	255.255.252.0	192.168.0.1
Printer_Speed	0	192.168.4.3	255.255.254.0	192.168.4.1
Printer_Intelligence	0	192.168.8.3 (DHCP)	255.255.255.128	192.168.8.1
Web+DHCP Server	Fa0	192.168.8.132	255.255.255.192	192.168.8.129
DNS Server	Fa0	192.168.8.133	255.255.255.192	192.168.8.129
Email Server	Fa0	192.168.8.4 (DHCP)	255.255.255.128	192.168.8.1