

Firewall: Rules

ATTACK

Categorie

Search

500 -

☐		☒	Icons		Version	Protocol	Source	Port	Destination	Commands
☐	L	☒		ATTACK	IPv4	*	ATTACK network	*	! InternalNets	
☐	L	☐		ATTACK	IPv4	*	ATTACK network	*	LAN network	
☐	L	☐		ATTACK	IPv4	*	ATTACK network	*	CLIENTS network	

< < 1 > >

Showing 1 to 25 of 25 entries

Apply

Firewall: Rules

CLIENTS

Categorie

Search

500

Automatically generated rules

Interface rules

		Icons		Version	Protocol	Source	Port	Destination	Commands	
	L			CLIENTS	IPv4	*	CLIENTS network	*	DC01	
	L			CLIENTS	IPv4	*	CLIENTS network	*	! InternalNets	

<

<

1

>

>

Showing 1 to 24 of 24 entries

Firewall Rules for the CLIENTS and ATTACK Zones

Firewall rules were created in OPNsense under **Firewall → Rules** to control what each zone can reach. OPNsense blocks any traffic that isn't allowed by a rule, so these rules define exactly what's permitted.

CLIENTS Rules

#	Action	Source	Destination	Purpose
1	Pass	CLIENTS network	DC01	Allow clients to reach the DC01 server
2	Pass	CLIENTS network	!InternalNets	Allow internet access

The first rule lets client machines reach DC01, which they need for services like DNS. The second rule uses the InternalNets alias with "!" (meaning "not"), so it allows traffic to anywhere *except* private networks, which is effectively internet-only. As a result, clients can reach DC01 and the internet, but not the other zones.

ATTACK Rules

#	Action	Source	Destination	Status
1	Pass	ATTACK network	! InternalNets	Enabled
2	Pass	ATTACK network	LAN network	Disabled
3	Pass	ATTACK network	CLIENTS network	Disabled

With only the first rule active, the ATTACK zone can reach the internet but is isolated from every internal network. The rules allowing access to the LAN and CLIENTS networks were created but left disabled, so they can be switched on when testing attacks against those zones and turned off again afterward.

Summary

The CLIENTS zone has limited access to DC01 and the internet, while the ATTACK zone is fully isolated from the internal network by default. This keeps the attack machines contained unless access is deliberately enabled.