

Services: Dnsmasq DNS & DHCP



General Domains Hosts DHCP ranges DHCP options DHCP boot DHCP tags

Tags & Interfaces

50

☐	Interface	Start address	End address	Domain	Description	Commands
▶ LAN						
▼ CLIENTS						
☐	CLIENTS	10.10.20.100	10.10.20.200			
▼ ATTACK						
☐	ATTACK	10.10.30.100	10.10.30.200			

◀ ◁ 1 ▷ ▶

Showing 1 to 3 of 3 entries

Apply

Services: Dnsmasq DNS & DHCP



General Domains Hosts DHCP ranges DHCP options DHCP boot DHCP tags

Tags & Interfaces

50

☐	Interface	Type	Option	Option6	Value	Description	Commands
▼ CLIENTS							
☐	CLIENTS	Set	dns-server [6]		10.10.10.10		

◀ ◁ 1 ▷ ▶

Showing 1 to 1 of 1 entries

Apply

 After changing settings, please remember to apply them.

System: Diagnostics: Services

	Name	Description	
	configd	Configd	
	cron	Cron	
	dnsmasq	Dnsmasq DNS/DHCP	
	hostwatch	Hostwatch	
	login	Users and Groups	
	ntpd	Ntpd	
	pf	Packet Filter	
	routing	System routing	
	svsctl	System tunables	

◀ ◁ 1 ▷ ▶

Showing 1 to 12 of 12 entries

Configuring DHCP for the CLIENTS and ATTACK Zones

DHCP was set up in OPNsense under **Services → Dnsmasq DNS & DHCP** so that machines in the new zones receive IP addresses automatically.

Under the **DHCP ranges** tab, an address range was created for each zone:

Interface	Start Address	End Address
CLIENTS	10.10.20.100	10.10.20.200
ATTACK	10.10.30.100	10.10.30.200

This gives each zone 101 addresses to hand out, while keeping the lower addresses free for static assignments such as the gateways at 10.10.20.1 and 10.10.30.1.

Under the **DHCP options** tab, a dns-server option was added for the CLIENTS zone with the value 10.10.10.10. Devices on the CLIENTS network will be told to use the server at 10.10.10.10 for DNS instead of the firewall.

The changes were saved and applied, and the Dnsmasq service is running.