

Network Administration

Lab 3

Introduction

to

IPv4 Addressing



SWIN BUR * NE *

SWINBURNE UNIVERSITY OF TECHNOLOGY

Aims:

- Configure IPv4 Addresses
- Observe the purpose of the default gateway
- Observe the purpose of the subnet mask

Note: For those of you who have studied networking before, this lab will appear deceptively simple. The focus of this lab for experienced students is to explain the observations.


Preliminary settings

Note: How to do these preliminary steps have been covered in past labs. If you cannot remember how to do these steps refer to Lab 01 and make sure you record how to do it in your journal for future labs.


- 1. Revert and launch sWin22RTR, sWin22SVR1, sWin10PC201and sWin22SVR3
- 2. Check the virtual PC network configuration and ensure that virtual PCs have connected to the correct networks, as given in the topology diagram.
- 3. Ensure that the virtual PCs sWin22SVR1, sWin10PC201 and sWin22SVR3 have IP addresses configured as outlined in the topology diagram before proceeding. Note:

To get to the adapter configuration:


i Launch **File Explorer** . Within the *File Explorer* window, *Right-click* on **Network**, then click to select **Properties**.



ii Within the *Network and Sharing Centre* window, *click* on the **Ethernet** link, then double-click to select **Properties.**



iii Within the *Ethernet Properties* window, *double-click* on **Internet Protocol Version 4 (TCP/IPv4)**, then configure the virtual PC's IP settings as required.



Topology





Figure 1 - Network Topology diagram for Lab 3



Gateway Addresses

In order to understand what a gateway address does, lets' do some preliminary tests:

- 4. On **sWin10PC201** right-click **Start** and select **Powershell**.
- 5. At the PowerShell prompt, type **ipconfig** and press **Enter**.
- 6. Record the output here:

| Connection-Specific DNS Suffix: | | |
|---------------------------------|----|--|
| IPv4 Address: | 3 | |
| Subnet Mask: | 13 | |
| Default Gateway: | -3 | |

7. We will now use the **ping** command to see which devices we can communicate with, with our current IP configuration.

Ping stands for **Packet Internet Groper**. It uses the ICMP protocol to request a reply packet to be sent back. If we can successfully ping a device it means that our ICMP *Echo-request* packet arrived and the *Echo-reply* has also been returned. Thus confirming that our devices have two way communication.

8. Still on sWin10PC201 we will ping the IP address of sWin22SVR1. At the PowerShell prompt type:

Was the ping successful?

If it wasn't get a fellow student to check for errors. If neither of you can find an error in your typing, call your supervisor over to help.

If the ping was successful you should have received a message similar to this:

9. We will now ping the IP address of our router. At the PowerShell prompt type:

Your ping should have been successful (if not have a fellow student try and troubleshoot, if neither of you can find the error, call your supervisor over).

| 10. N | low ping the IP | address of o | ur sWin22SVR3 . | At the Po | werShell | prompt type |
|-------|-----------------|--------------|------------------------|-----------|----------|-------------|
|-------|-----------------|--------------|------------------------|-----------|----------|-------------|

Ping 192.168.100.13

Was this successful?

11. Pinging sWin22SVR3 should not have been successful.

Reviewing the theory covered in the lecture:

In order to communicate on any IPv4 network a device needs an **IP address** and a **Subnet mask**.

Without an IP address and Subnet mask the device cannot communicate on the network. With **only** an IP address and Subnet mask, the device can communicate with other devices that are:

- a) Connected to the same network segment, and...
- b) Configured with an IP address in the **same subnet.**

If a device needs to communicate with a device in another network segment and subnet, then the network needs a router. The IP address of the local port of the router (i.e. the port on the device's subnet) must be configured as the **Default gateway**.

Because 192.168.100.13 is in a different subnet we expect the ping to fail when no default gateway address is configured.

Let's see if configuring the default gateway fixes this problem.

- 12. Review the topology diagram on page 3.
 - a. Which address do you think should be used as sWin10PC201's gateway address?

b. On **sWin10PC201** go back to the **Ethernet** adaptor properties (Hint: check step 3 on page 2, if you cannot remember how to do this). In the *Internet Protocol Version 4* settings type the IP address: **172.16.32.1** as the *Default gateway*.




Figure 2 -Configuring the Default gateway address

- 13. Click **OK**, and close the Ethernet properties dialog box.
- 14. Back in **Powershell** see if you can ping 192.168.100.13 successfully.

You should observe output similar to the following:

```
Pinging 192.168.100.13 with 32 bytes of data:

Reply from 192.168.100.13: bytes=32 time<1ms TTL=127

Reply from 192.168.100.13: bytes=32 time<1ms TTL=127

Reply from 192.168.100.13: bytes=32 time<1ms TTL=127

Reply from 192.168.100.13: bytes=32 time<1ms TTL=127
```

(If not have a fellow student try and troubleshoot, if neither of you can find the error, call your supervisor over).

A gateway address is required if you need to communicate with a device in another subnet. The IP address of the local router interface, (i.e. the router interface that is connected to your network) should be configured as your gateway address.

We have now observed the importance of the Default gateway address.

Subnet Mask

We will now explore the function of the subnet mask.

A networked device uses the **subnet mask** to determine which MAC address needs to be entered into the Data-link layer's **Destination Address**. There are only two options, the MAC address of the destination device or the MAC address of the Default gateway.

If the network portion of the destination device's address **matches** the network portion of the source device's address then the MAC address of the **destination device** will be entered.

If the network portion of the destination device's address **does not match** the network portion of the source device's address then the MAC address of the **default gateway** will be entered.



Figure 3 illustrates how the destination MAC address is selected and used.




Figure 3 - How Subnet masks determine destination MAC addresses

Laboratory 6

| 15. Question: Look at the source and destination addresses of Frame 1 and Frame 2. | | | | |
|--|--|--|--|--|
| a. Which addresses change? | | | | |
| b. Which addresses stay the same? | | | | |
| c. Try to explain why some change and others don't: | | | | |
| | | | | |
| ANDing | | | | |
| 16. Subnet masks work by: | | | | |
| a. ANDing the binary Source IP address with the local subnet mask. | | | | |

b. ANDing the binary Destination IP address with the local subnet mask.

(Remember when both bits are 1 the result is 1, if either bit is 0 the result is 0)

- c. Comparing the resultant network addresses to see if they are identical.
 - i If identical they use the destination's MAC address as the layer 2 destination address.
 - ii If different they use the default gateway's MAC address as the layer 2 destination address. (Note: In this situation, if no gateway address is configured the packet will be dropped)

17. **Example**

a. PCa has the IP4 configuration of:

IP: 10.10.10.100

SN: 255.255.255.0

GW: 10.10.10.1

PCa wants to communicate with PCb.

PCb has the IP address of IP: 10.10.10.102

i To calculate its own **network address** PCa uses its IP address and Subnet mask.

It performs an AND operation:

```
00001010
PCa IP
           00001010
                                   00001010
                                                  01100100
PCa SN
           11111111
                        11111111
                                     11111111
                                                  0000000
PCa
          00001010 .
                       00001010
                                     00001010
                                                  0000000
Network
Address
```

ii To calculate PCb's **network address** PCa uses its own subnet mask and ANDs it with PCb's IP address

```
PCb IP
           00001010
                        00001010
                                      00001010
                                                   01100110
                                     11111111
                                                   00000000
PCa SN
           11111111
                        11111111
PCb
           00001010 .
                        00001010 .
                                     00001010
                                                   00000000
Network
Address
```

iii If we convert both PCa's and PCb's network addresses back to decimal we get:

```
PCa 10 . 10 . 10 . 0
PCb 10 . 10 . 10 . 0
```

We can see that both network addresses are identical. So at the Data-link layer PCb's MAC address will be inserted as the destination address.

18. Question: Do PCc and PCd have the same network address?

PCc IP:192.168.100.103


PCc SN: 255.255.255.0

PCd IP: 192.168.111.104

Laboratory 6

| 19. On sWin10PC201 ping 172.16.32.1 (the local router interface). |
|---|
| Make sure the ping is successful. |
| 20. On sWin10PC201 change the subnet mask to 255.255.255.192 , and delete the Default gateway address (the Default gateway should be " "). (Hint: check step 3 on page 2, if you have forgotten where to configure this) |
| a. Make sure that you click OK on the Ethernet Properties dialogue box. |
| b. Now try to ping 172.16.32.1 |
| Were you successful? |
| 21. On sWin22Svr1 make the same IP configuration changes. Change the subnet mask |
| to 255.255.255.192 , and delete the Default gateway address. |
| a. Now try to ping 172.16.32.1 Were you successful? |
| b. Now try to ping sWin10PC201 |
| Were you successful? |

22. Review the addressing of our current network segment.



| a. | Why could sWin22SVR1 successfully ping sWin22RTR(E₀) but not sWin10PC201 ? |
|----|---|
| | |
| | |
| | |
| | |
| | |
| b. | sWin22SVR1 and sWin22RTR(E ₀) could successfully ping, but they have different subnet masks. Explain how this could be? (Note: If you are new to networking, do not |
| | stress if you cannot answer this question you will be able to by the end of the semester). |
| | |
| | |
| | |
| | |
| | THE REPORT OF |

Extension - Investigating ARP

Note: This is an optional component of the lab. Only students who have finished early should consider doing the practical exercises in this extension.

The Address Resolution Protocol is how the Network Layer and the Data-link layer are able to link IPv4 addresses with MAC addresses.

It achieves this by keeping a table of IP and MAC addresses. Every time a device tries to communicate with another device it uses the IP address (and subnet mask) that has come from the Network Layer and tries to locate the appropriate MAC address in the ARP table. If there is no match, ARP will then send out a broadcast to try and locate the device with that IP address. If that device replies to the broadcast, the reply will have the MAC address in the source field of the frame, which can then be inserted as a new entry in the ARP table.

In this exercise we will observe how an ARP table is constructed, and how addresses within the same subnet and addresses in another subnet are treated differently.

23. Configure the IP address settings of sWin10PC201 and sWin22SVR1 as given in Figure 4.




Figure 4 - Extension Network Topology

24. Start up the virtual machines sWin22DC1 and sWin22SVR2

| 25. On sWin10PC201 | , load up | Windows | PowerShell | (Admin) | , and type |
|----------------------|-----------|---|-------------------|---|------------|
| 23. 01131111101 6201 | , iouu up | , ,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,, | I OVICE SELECT | (,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,, | , and cype |

arp -d

26. Now display the ARP table by typing:

arp - a

Ideally (if you were fast enough) there will be no entries in your ARP table, however you may observe one or two 224.0.0.x addresses (.22 is used by IGMP, and .252 is used by LLMNR – both are beyond the scope of this course). If you were slow the Default gateway may have an entry appear.

- 27. Now ping sWin22SVR1, and display your ARP table (i.e. arp –a). You should now see an entry for it.
- 28. Now ping sWin22DC1 (172.16.32.10) and display your ARP table. There should now be an entry for this.
- 29. If your default gateway is not appearing in your ARP table ping it (172.16.32.1) and make sure that there is an entry in the ARP table.
 - a. What happened every time you pinged a new address?
 b. How many entries do you now have in your ARP table? ______
- 30. Now ping sWin22SVR3 and check your ARP table. Are there any new entries? _____
- 31. Now ping sWin22SVR2 (10.10.10.12) and check your ARP table. Are there new entries now? _____
- 32. Explain your observations:

| | (5) |
|-----------|-----------------|
| | |
| OM PER-LI | 79 |
| | ~ |
| | |

33. Get your supervisor to check your explanation.

Pack Up

- 1. Shut down all guest VMs.
- Sign out from the Host virtual machine and make sure that it is Stopped otherwise it will run in the background and use up your quota.
- 3. If on campus, **log off from the ATC626 lab PC**, and push your chair in as you leave.

