





Docking Manual



1. Protein File Preparation:



Docking Manual





Docking Manual




Docking Manual


2.Grid Box Preparation:





Docking Manual




3. Ligand File Preparation:



Docking Manual



Docking Manual



AutoDock Vina Manual

How to get started learning to use Vina?

Watching the [video tutorial](#) might be the best way to do that.

Platform Notes and Installation

Windows

Compatibility

Vina is expected to work on Windows XP and newer systems.

Installing

Double-click the downloaded [MSI file](#) and follow the instructions

Running

Open the [Command Prompt](#) and, if you installed Vina in the default location, type

```
" \ Program Files \ The Scripps Research Institute \ Vina \ vina.exe" - help
```

Configuration File

Docking Manual

For convenience, some command line options can be placed into a configuration file.

For example:

```
receptor =  
hsg1/rigid.pdbqt ligand =  
ligand.pdbqt center_x =  
2 center_y =  
6 center_z =  
-7  
  
size_x = 25  
size_y = 25  
size_z = 25  
  
energy_range = 4
```

Autodock vina cmd commands

1. Open the terminal in the docking folder. Docking folder must be contains **conf.txt**, **protein.pdbqt** file, **ligand.pdbqt** file which you defined in the config file (Check [config file](#)).
2. Then edit the files in the **docking** as you want.
3. If you see Process finished that means script is finished working. You can check the **log.txt** for the pick result
4. Then run
5. `Vina.exe --config config.txt -log log.txt`
6. Click enter
7. You get results in ligand.out in the Docking Folder

Command Prompt

```
Microsoft Windows [Version 10.0.19045.5247]  
c) Microsoft Corporation. All rights reserved.  
  
C:\Users\SHIVA>cd C:\Users\SHIVA\Downloads\dock3  
  
C:\Users\SHIVA\Downloads\dock3>vina.exe --config config.txt --log log.txt_
```

Docking Manual

Output File (log.txt):

MODE | AFFINITY | DIST FROM BEST MODE

| (KCAL/MOL) | RMSD L.B. | RMSD U.B.

-----+-----+-----+-----

1	-8.7	0.000	0.000
2	-8.4	1.293	2.965
3	-7.9	28.429	29.854
4	-7.6	28.601	30.151
5	-7.6	1.870	6.984
6	-7.6	26.157	28.578
7	-7.5	28.105	30.835
8	-7.3	28.374	30.252
9	-7.1	28.320	30.102

WRITING OUTPUT ... DONE.