


In Cyver Core, in addition to your standard pentest report, you can generate an "External Report" version. This allows you to exclude highly technical or sensitive sections so you can safely share the document with external parties, such as third-party vendors, clients, or auditors.


To use this feature, you first need to enable and configure the external download option within your Report Template.

CONFIGURE THE REPORT TEMPLATE

1. Navigate to **Settings > Report Templates** from the left-hand menu.



2. Locate the report template you would like to generate an external version for. Click the three dots (**...**) in the **Actions** column and select **Edit**.



3. Navigate to the **PDF settings** tab.

Edit Report Template: Report Template Demo

Template General Settings **PDF settings** Word Settings Customize Text

[Learn more about Report Templates](#)

Title*
Report Template Demo

Status
Published

Managed by team
Select

+ Add Section

Section Title
Cover

Move down

Section Content Section Settings

Report Template Tokens + Add Text Block to Library

Heading 1 B I

Security Assessment Report
{Client_Name} - {Project_Name}

+ Add Section

4. Scroll down to the **External Report** section and check the box to **Enable external report PDF download**.

Edit Report Template: Report Template Demo

Template General Settings PDF settings Word Settings Customize Text

Download Preview PDF

Adjust CSS to customize the PDF report look and feel [View CSS customization](#)

PDF settings
☐ Protect the Report PDF with a Password

PDF bookmarks
None

PDF Footer
☐ Replace background image
☐ Display page number

Footer Text
Paragraph B I Tokens

PDF Header
Display Header

External Report
☒ Enable external report PDF download

Cancel Save

5. A **Select report sections** list will appear. Check the boxes next to the specific sections you want to include in the external report (e.g., Executive Summary).

External Report
☒ Enable external report PDF download

Select report sections

☐ Cover

☐ Table of Contents

☐ Project Details

☒ Executive Summary

☐ Vulnerability Summary

☐ Detailed Findings

Tip: If all sections don't appear in the list, please save the report template first.

Cancel Save

- *Tip: If all your custom sections do not appear in the list right away, please save the report template first, then re-open it.*


6. Click **Save**.

DOWNLOAD THE


EXTERNAL REPORT

Once the template is configured, you can generate the document directly from your project.


1. Navigate to your project and open the **Report** tab.
2. Apply the template changes to your current project data based on what you updated:
 - **If you only updated settings** (e.g., you only checked the "External PDF" box): Click the three dots (**...**) at the top right of the report window and select **Apply Report Template Settings**. This applies the new configuration while preserving any custom text edits you've already made inside the report editor.



- **If you updated template content** (e.g., you added new sections or edited the template text): Click the **+ New Version** dropdown and select **Generate Report from Report Template** to pull in the fresh content and sections.




3. Next, click **Generate Report PDF**.
This step is required for the download options to appear.



4. Once the standard PDF is generated, a new **Download External Report PDF** button will appear at the top of

the report window.



5. Click it to download a PDF containing only the safe, pre-selected sections you configured.