| ID | Testing         | Function                      | Pre-                  | Steps   | Expected result  | Actual | Comments |
|----|-----------------|-------------------------------|-----------------------|---|--|--------|----------|
|    | Item            |                               | condition             |   |  | result |          |
| 1  | Sign-up<br>page | Elements<br>default<br>status | Open Sign-<br>up page | 1. Locate element 2. Check Button types and default status 3. Check inputs placeholder.   | 1. No button has been checked 2. Button type is 'radio' 3. Default placeholders email- 'Please input email' Password – 'please input password' Confirm Password – 'Tap password again'   | Pass   | N/A      |
| 2  | Sign-up<br>page | Email input                   | Open Sign-<br>up page | 1. Locate element 2. Check the inputs type 3. Type wrong email format 4. Empty 5. Type right email format   | 1. Inputs type should be 'email' 2. Wrong email format – error message: 'email' is not a valid email 3. Empty – error message: 'email' is required 4. Right email format – no error message  | Pass   | N/A      |
| 3  | Sign-up<br>page | Password input                | Open Sign-<br>up page | 1. Locate element 2. Check the inputs type 3. Type a password with a length of 3 4. Type a password with a length of 4 5. Type a password with a length of 16 6. Type a password with a length of 17 7. Empty 8. Type a password with number only and have a length between 4 – 16 9. Type a password with letters only and have a length between 4 –16 | 1. Input type should be 'password' by default  2. Length with 3 and 17 – error message: 'password' must be between 4 and 16 characters  3. Length between 4 and 16 with numbers only, letters only or combination will have no error | Pass   | N/A      |

|   |                 |                               |                       | 10. Type a password combine with number and letters and have a length between 4 -16  | message  4. Empty – error message: 'password' is required  |      |     |
|---|-----------------|-------------------------------|-----------------------|--|--|------|-----|
| 4 | Sign-up<br>page | Confirm<br>Password<br>inputs | Open Sign-<br>up page | 1. Locate the element 2. Check the input type 3. Inputs is matched with Password inputs 4. Inputs isn't matched Password inputs                | 1. Input type is 'Password' by default. 2. Matched – no error message 3. Different – error message: The two passwords that you entered do not match! | Pass | N/A |
| 5 | Sign-up<br>page | Eye icon                      | Open Sign-<br>up page | 1. Locate the elements 2. Check the numbers 3. Randomly inputs in 'Password' and 'Confirm Password' field and check if eye icon is functional. | 1. 2 'eye icon' elements 2. Click to switch to 'text' type and password and confirm password are visible.  | Pass | N/A |
| 6 | Sign-up<br>page | Sign-Up<br>Requirement        | Open Sign-<br>up page | Locate 'Sign-up' button     Submit button with     empty inputs     Submit button with all     correct information                             | <ol> <li>The number of error message will be four</li> <li>No error message.</li> </ol>  | Pass | N/A |