

```
root@srv2: /srv/share/upload
root@srv2:~# apt list --installed|grep nfs
WARNING: apt does not have a stable CLI interface. Use with caution in scripts.

libnfsidmap1/noble-updates,now 1:2.6.4-3ubuntu5.1 amd64 [installed,automatic]
nfs-common/noble-updates,now 1:2.6.4-3ubuntu5.1 amd64 [installed]
nfs-kernel-server/noble-updates,now 1:2.6.4-3ubuntu5.1 amd64 [installed]
root@srv2:~# mkdir -p /srv/share/upload
root@srv2:~# chown -R nobody:nogroup /srv/share
root@srv2:~# chmod 777 /srv/share/upload
root@srv2:~# ls -l /srv/share
total 4
drwxrwxrwx 2 nobody nogroup 4096 Jul 22 19:01 upload
root@srv2:~# cat >> /etc/exports <<EOF
/srv/share 192.168.0.0/24(rw,sync,root_squash)
EOF
root@srv2:~# cat /etc/exports
# /etc/exports: the access control list for filesystems which may be exported
#                 to NFS clients.  See exports(5).
#
# Example for NFSv2 and NFSv3:
# /srv/homes      hostname1(rw,sync,no_subtree_check) hostname2(ro,sync,no_subtree_check)
#
# Example for NFSv4:
# /srv/nfs4       gss/krb5i(rw,sync,fsid=0,crossmnt,no_subtree_check)
# /srv/nfs4/homes gss/krb5i(rw,sync,no_subtree_check)
#
/srv/share 192.168.0.0/24(rw,sync,root_squash)
root@srv2:~# exportfs -ra
exportfs: /etc/exports [1]: Neither 'subtree_check' or 'no_subtree_check' specified for export "192.168.0.0/24:/srv/share".
    Assuming default behaviour ('no_subtree_check').
    NOTE: this default has changed since nfs-utils version 1.0.x

root@srv2:~# exportfs -s
/srv/share 192.168.0.0/24(sync,wdelay,hide,no_subtree_check,sec=sys,rw,secure,root_squash,no_all_squash)
root@srv2:~# ip -br a
lo                UNKNOWN          127.0.0.1/8 ::1/128
enp0s3            UP                192.168.0.110/24 fe80::a00:27ff:febd:1321/64
root@srv2:~# cd /srv/share/upload/
root@srv2:/srv/share/upload# touch check_file
root@srv2:/srv/share/upload# ls
check_file  client_file
root@srv2:/srv/share/upload# reboot
```

```
usr1@srv2: ~  
Broadcast message from root@srv2 on pts/1 (Wed 2026-07-22 19:30:37 UTC):  
The system will reboot now!  
  
root@srv2:/srv/share/upload#  
login as: usr1  
usr1@192.168.0.110's password:  
Welcome to Ubuntu 24.04.3 LTS (GNU/Linux 6.8.0-136-generic x86_64)  
  
* Documentation:  https://help.ubuntu.com  
* Management:    https://landscape.canonical.com  
* Support:       https://ubuntu.com/pro  
  
System information as of Wed Jul 22 07:33:36 PM UTC 2026  
  
System load:      0.65          Processes:          366  
Usage of /home:   0.0% of 1.90GB Users logged in:    0  
Memory usage:    7%           IPv4 address for enp0s3: 192.168.0.110  
Swap usage:      0%  
  
* Strictly confined Kubernetes makes edge and IoT secure. Learn how MicroK8s  
  just raised the bar for easy, resilient and secure K8s cluster deployment.  
  
  https://ubuntu.com/engage/secure-kubernetes-at-the-edge  
  
Expanded Security Maintenance for Applications is not enabled.  
  
65 updates can be applied immediately.  
11 of these updates are standard security updates.  
To see these additional updates run: apt list --upgradable  
  
Enable ESM Apps to receive additional future security updates.  
See https://ubuntu.com/esm or run: sudo pro status  
  
Last login: Wed Jul 22 19:24:35 2026 from 192.168.0.106  
usr1@srv2:~$ ls /srv/share/upload/  
check_file  client_file  
usr1@srv2:~$ sudo exportfs -s  
[sudo] password for usr1:  
/srv/share 192.168.0.0/24(sync,wdelay,hide,no_subtree_check,sec=sys,rw,secure,r  
oot_squash,no_all_squash)  
usr1@srv2:~$ showmount -a  
All mount points on srv2:  
192.168.0.111:/srv/share  
usr1@srv2:~$
```