

Warehouses

Warehouses are the compute horses that does the processing of queries, running Machine Learning algorithms etc.,

Valid Sizes

- X-Small
- Small
- Medium
- Large
- X-Large
- 2X-Large
- 3X-Large
- 4X-Large
- 5X-Large
- 6X-Large

Check [overview](#) for details on size and its associated credits.

Create Warehouse

Create warehouse requires only one parameter the **NAME** of the warehouse. e.g. CREATE WAREHOUSE

MY_FIRST_WH

Property	Description	Default
WAREHOUSE_SIZE	The warehouse compute size.	X-small
WAREHOUSE_TYPE	The type of warehouse, STANDARD or SNOWPARK-OPTIMIZED.	STANDARD
MIN_CLUSTER_COUNT	Minimum number of servers to scale down to.	1
MIN_CLUSTER_COUNT	Maximum number of servers to scale out to.	1
MAX_CLUSTER_COUNT	Minimum number of servers to scale down to.	3

Property	Description	Default
AUTO_SUSPEND	Idle number of seconds before suspending the warehouse.	300
AUTO_RESUME	On-demand start of the warehouse .	TRUE
INITIALLY_SUSPENDED	Start warehouse automatically after successful creation.	TRUE

Check the [docs](#) for more details on the parameters and other available options.

Create a Warehouse named MY_FIRST_WH with defaults:

```
CREATE WAREHOUSE MY_FIRST_WH
```

CREATE WAREHOUSE MY_SMALL_WH

Create Warehouse named MY_SMALL_WH with size as Small:

```
CREATE WAREHOUSE MY_SMALL_WH
WAREHOUSE_SIZE = 'Small'
```

Create Warehouse named MY_SMALL_STARTED_WH with size as Small and start it automatically after create:

```
CREATE WAREHOUSE MY_SMALL_STARTED_WH
WAREHOUSE_SIZE = 'Small'
INITIALLY_SUSPENDED = FALSE
```

Create Warehouse named MY_LONG_RUNNING_WH with size as Small and make to automatically suspend after 10 mins(600 seconds):

```
CREATE WAREHOUSE MY_LONG_RUNNING_WH
WAREHOUSE_SIZE = 'Small'
AUTO_SUSPEND = 600
```

[!TIP]

- Use bigger Warehouse size for *CPU* or *Memory* intensive operations.
- Adjust *MIN_CLUSTER_COUNT* and *MAX_CLUSTER_COUNT* to increase concurrency i.e. process more queries in parallel

Check Warehouse Properties

Check a particular warehouse properties

```
SHOW WAREHOUSES LIKE 'MY_SMALL_WH' ;
```

List All Warehouses

```
SHOW WAREHOUSES
```

Working With Warehouse

Use a particular warehouse

```
USE WAREHOUSE MY_SMALL_WH
```

Manually start a warehouse,

```
ALTER WAREHOUSE MY_SMALL_WH RESUME
```

Manually suspend a warehouse,

```
ALTER WAREHOUSE MY_SMALL_WH SUSPEND
```

Change the size of the warehouse

```
ALTER WAREHOUSE MY_SMALL_WH  
SET
```

```
WAREHOUSE_SIZE = 'Small'
```

```
WAIT_FOR_COMPLETION = TRUE; -- 1
```

1. WAIT_FOR_COMPLETION ensures all existing operations are complete before modifying the size

Drop Warehouse

```
DROP WAREHOUSE MY_SMALL_WH
```

[!IMPORTANT]

Warehouse's cant be UNDROPPED.

References

- [Warehouses](#)
- [SQL Commands Reference](#)