

Utilities Reference

for release version 0.2.21

mu-sys

Name: mu-sys – minimal exec command

Synopsis: mu-sys [options...] [file...]

Options: 0.0.2

-l *SRCFILE* load SRCFILE in sequence
-e *SEXPR* evaluate SEXPR and print result
-q *SEXPR* evaluate SEXPR quietly
-c *JSON* environment configuration
[file ...] load source file(s)

mu-server

Name: mu-server – minimal exec command

Synopsis: mu-server [options...] [file...]

Options: 0.0.2

-v print version string and exit
-l *SRCFILE* load SRCFILE in sequence
-e *SEXPR* evaluate SEXPR and print result
-q *SEXPR* evaluate SEXPR quietly
-c *JSON* environment configuration
[file ...] load source file(s)

mu-exec

Name: mu-exec – minimal exec command

Synopsis: mu-exec [options...] [file...]

Options: 0.0.2

-v print version string and exit
-l *SRCFILE* load SRCFILE in sequence
-e *SEXPR* evaluate SEXPR and print result
-q *SEXPR* evaluate SEXPR quietly
-c *JSON* environment configuration
[file ...] load source file(s)

sys-dev

Name: sys-dev – system development tool

Synopsis: sys-dev command [options...]

Description: 0.0.21

Usage: mforge 0.0.21 command [option...]

command:

help ; this message
version ; mforge version

workspace init | env ; manage workspace

bench base | current | report | clean
[--ntests=number] [--all]
; benchmark test suite

regression ; regression test suite

symbols reference | crossref | metrics
[--namespace=name]
; symbol reports,
; namespace defaults
; to mu

precommit ; fmt and clippy,
; pre-commit checking

general options:

--verbose ; verbose operation
--recipe ; show recipe

sys-repl

Name: sys-repl – mu system REPL

Synopsis: sys-repl

Description: 0.0.5

repl is a generalized command-line listener that can be configured to load and run in any of the *mu* namespaces.

It is intended for debugging and exploration during development.

repl has no command-line arguments, it is configured by a *JSON*-format dotfile named *.sys-repl*. If a *.sys-repl* is not found in the current directory, the user's home directory will be searched and if found there will be used. *sys-repl* does not require a *.sys-repl* file.

```
{
  "config": {
    "pages": "2048",
    "gc-mode": "auto"
  },
  "namespace": "mu",
  "load": [ "file"... ]
}
```

The configuration syntax can specify three options, none of which are required.

The *config* option supplies a *mu* Env configuration specification in *JSON* format, see the *mu-ref* refcard *environment* section for details. If this option is not specified, the *mu* Env will be created with default values.

The *namespace* option supplies the namespace that should be loaded, see the *mu-ref* refcard *namespaces* section for details. If this option is not specified *mu-listener* will load only the *mu* namespace.

The *load* option supplies a list of the source files to be loaded before the REPL runs. Additional symbols may be supplied there.