

Contents

Metasploitable Installation Documentation	2
Step 1: Search for Metasploitable 2.....	2
Step 2: Navigate to the Official Repository	2
Step 3: Download the Compressed Archive	3
Step 4: Extract the Compressed Files	3
Step 5: Verify the Extracted Virtual Machine Files	4
Step 6: Open VMware Workstation	4
Step 7: Choose Virtual Machine Configuration Type	5
Step 8: Set Hardware Compatibility	5
Step 9: Select Guest Operating System Installation Source.....	6
Step 10: Name the Virtual Machine and Set Storage Path.....	6
Step 11: Configure Processor Allocation.....	7
Step 12: Set RAM / Memory Allocation.....	7
Step 13: Configure Network Connection Type	8
Step 14: Choose I/O Controller Type	8
Step 15: Select Virtual Disk Type	9
Step 16: Select Existing Disk Attachment Option.....	9
Step 17: Browse and Locate the VMDK File	10
Step 18: Review Summary and Finish Creation	10
Step 19: Power On the Virtual Machine	11
Step 20: Boot System and Log In	12

Name: Md Sohan Hossain

IP:

inet 127.0.0.1

netmask 255.0.0.0

Metasploitable Installation Documentation


Step 1: Search for Metasploitable 2

- **Action:** Open your web browser and navigate to Google.
- **Details:** Type metasploitable 2 download into the Google search box and press Enter.




Step 2: Navigate to the Official Repository

- **Action:** Access the official SourceForge repository page for Metasploitable.
- **Details:** Click the green **Download** button on the page to initiate the download.




Step 3: Download the Compressed Archive

- **Action:** Monitor the download in your browser's download manager.
- **Details:** Wait for the file metasploitable-linux-2.0.0.zip (approximately 825 MB in size) to finish downloading completely.



Step 4: Extract the Compressed Files

- **Action:** Locate the downloaded .zip file on your system.
- **Details:** Right-click metasploitable-linux-2.0.0.zip, select **Extract All...**, select a destination directory, and wait for the extraction process to complete.




Step 5: Verify the Extracted Virtual Machine Files

- **Action:** Open the extracted metasploitable-linux-2.0.0 folder.
- **Details:** Ensure that all required virtual machine files are present, including the main VMware Virtual Disk file (Metasploitable.vmdk ~1.8 GB) and configuration files (.vmx, .vmsd, .vmxf).

name	date modified	type	size
Metasploitable	9/30/2026 11:10 AM	VMware virtual disk f...	1,880,512 KB
Metasploitable	9/30/2026 11:10 AM	VMware snapshot m...	0 KB
Metasploitable	9/30/2026 11:10 AM	VMware virtual mach...	3 KB
Metasploitable	9/30/2026 11:10 AM	VMware Team Mem...	1 KB
Metasploitable	9/30/2026 11:10 AM	VMware Virtual Mac...	9 KB


Step 6: Open VMware Workstation

- **Action:** Launch **VMware Workstation Pro**.
- **Details:** On the main dashboard, click on **Create a New Virtual Machine**.




Step 7: Choose Virtual Machine Configuration Type

- **Action:** Select the wizard configuration mode.
- **Details:** Choose **Custom (advanced)** to enable detailed control over hardware compatibility, disk interfaces, and existing disk attachment, then click **Next >**.




Step 8: Set Hardware Compatibility

- **Action:** Select the target virtual hardware specification.
- **Details:** Keep the default hardware compatibility setting (e.g., Workstation 25H2 or later) and click **Next >**.




Step 9: Select Guest Operating System Installation Source

- **Action:** Define how the guest operating system will be provided.
- **Details:** Select the radio button for **I will install the operating system later.** (since Metasploitable uses a pre-configured virtual disk rather than an ISO installer), then click **Next >**.




Step 10: Name the Virtual Machine and Set Storage Path

- **Action:** Define the VM name and file path on your host machine.
- **Details:** Set the **Virtual machine name** to Metasploitable. Specify the desired directory path in the **Location** field (e.g., C:\Users\SOHAN_SENTINEL\Documents\Metasploitbale), then click **Next >**.




Step 11: Configure Processor Allocation

- **Action:** Specify the processor hardware parameters for the virtual machine.
- **Details:** Set the **Number of processors** to 2 and **Number of cores per processor** to 1 (yielding a total of 2 processor cores), then click **Next >**.




Step 12: Set RAM / Memory Allocation

- **Action:** Define the amount of memory allocated to the virtual machine.
- **Details:** Enter 1024 MB (1 GB) in the memory input field, then click **Next >**.




Step 13: Configure Network Connection Type

- **Action:** Select the networking mode for host and guest communication.
- **Details:** Select the radio button for **Use network address translation (NAT)** to share the host system's network IP address, then click **Next >**.




Step 14: Choose I/O Controller Type

- **Action:** Select the SCSI controller type.
- **Details:** Keep the default recommended option **LSI Logic (Recommended)** selected and click **Next >**.




Step 15: Select Virtual Disk Type

- **Action:** Specify the disk interface configuration.
- **Details:** Select **SCSI (Recommended)** as the virtual disk type and click **Next >**.




Step 16: Select Existing Disk Attachment Option

- **Action:** Choose how the storage media will be attached.
- **Details:** Select the radio button for **Use an existing virtual disk** (to attach the previously extracted Metasploitable file), then click **Next >**.




Step 17: Browse and Locate the VMDK File

- **Action:** Provide the path to the existing virtual hard disk.
- **Details:** Click the **Browse...** button, navigate to the extracted Metasploitable folder, select Metasploitable.vmdk, and confirm the selection.




Step 18: Review Summary and Finish Creation

- **Action:** Verify the virtual machine configuration settings.
- **Details:** Confirm the configuration details (Name: Metasploitable, Memory: 1024 MB, Network: NAT, Processors: 2 cores), then click **Finish**.



Step 19: Power On the Virtual Machine

- **Action:** Boot the newly configured virtual machine.
- **Details:** Select **Metasploitable** from the left library pane in VMware Workstation and click **Power on this virtual machine**.



Step 20: Boot System and Log In

- **Action:** Wait for the operating system boot process to finish and complete authentication.
- **Details:** Once the terminal screen displays the ASCII art banner and the metasploitable login: prompt, log in using the default system credentials:
 - **Username:** msfadmin
 - **Password:** msfadmin

[illegible]