


DHCP LAB



```
R1
R1(config)#interface eth0/0
R1(config-if)#ip add 50.0.0.0 255.0.0.0
Bad mask /8 for address 50.0.0.0
R1(config-if)#ip add 50.0.0.1 255.0.0.0
R1(config-if)#no shut
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#
R1(config)#interface eth0/1
R1(config-if)#ip add 172.16.0.1 255.255.0.0
R1(config-if)#no shut
R1(config-if)#exit
R1(config)#
R1(config)#ip route 192.168.2.0 255.255.255.0
% Incomplete command.
R1(config)#ip route 192.168.2.0 255.255.255.0 172.16.0.1
%Invalid next hop address (it's this router)
R1(config)#
*Sep 24 15:51:52.907: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#ip route 192.168.2.0 255.255.255.0 172.16.0.2
R1(config)#exit
```

```
R1
R1(config)#ip dhcp pool hr
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#deff
R1(dhcp-config)#def
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#
R1(config)#
R1(config)#ip dhcp exc
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.20
R1(config)#exit
R1#
*Sep 24 15:57:16.622: %SYS-5-CONFIG_I: Configured from console by console
R1#
5R1#
R1#
R1#config terminal
6Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool sales
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
AR1(dhcp-config)#def
```

```
R1
R1#
*Sep 24 15:57:16.622: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#
R1#
R1#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool sales
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#def
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#
R1(config)#ip dhcp exc
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.20
R1(config)#exit
R1#
*Sep 24 16:01:31.640: %SYS-5-CONFIG_I: Configured from console by console
R1#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
```

```
R2
R2(config)#int
*Sep 24 15:52:13.713: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config)#interface eth0/0
R2(config-if)#ip add 192.168.2.1 255.255.255.0
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#interface eth0/1
R2(config-if)#ip add 172.16.0.2 255.255.0.0
R2(config-if)#no shut
R2(config-if)#exit
R2(config)#ip route 50.0.0.0 255.0.0.0 172.16.0.1
R2(config)#exit
R2#
*Sep 24 15:54:57.781: %SYS-5-CONFIG_I: Configured from console by console
R2#
config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#interface eth0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#exit
R2(config)#
```

```
VPC-1
Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> dhcp
DDORA IP 50.0.0.21/8 GW 50.0.0.1

VPC-1>
```

```
VPC-2

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May  7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-2> dhcp
DDORA IP 50.0.0.22/8 GW 50.0.0.1

VPC-2> █
```

