

Router Configuration Lab

```
ROUTER
ROUTER#show ip interface brief
Interface      IP-Address      OK? Method Status      Prot
Ethernet0/0    unassigned      YES TFTP   up          up
Ethernet0/1    unassigned      YES TFTP   down        down
Ethernet0/2    unassigned      YES TFTP   down        down
Ethernet0/3    unassigned      YES TFTP   down        down
ROUTER#
```

```
ROUTER
Interface      IP-Address      OK? Method Status      Prot
Ethernet0/0    unassigned      YES TFTP   up          up
Ethernet0/1    unassigned      YES TFTP   down        down
Ethernet0/2    unassigned      YES TFTP   down        down
Ethernet0/3    unassigned      YES TFTP   down        down
ROUTER#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override

Gateway of last resort is not set

ROUTER#
```

```
ROUTER
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Aug  2 14:19:15.404: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              50.0.0.1        YES manual  up          up
Ethernet0/1              unassigned      YES TFTP   down        down
Ethernet0/2              unassigned      YES TFTP   down        down
Ethernet0/3              unassigned      YES TFTP   down        down
ROUTER#
```

```
ROUTER
ROUTER(config)#exit
ROUTER#
*Aug  2 14:19:15.404: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface                IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0              50.0.0.1        YES manual  up          up
Ethernet0/1              unassigned      YES TFTP   down        down
Ethernet0/2              unassigned      YES TFTP   down        down
Ethernet0/3              unassigned      YES TFTP   down        down
ROUTER#hostname R1
^
% Invalid input detected at '^' marker.
ROUTER#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
ROUTER(config)#hostname R1
R1(config)#
R1(config)#
R1(config)#
```

```
ROUTER
R1(config)#exit
R1#
*Aug 2 14:24:33.667: %SYS-5-CONFIG_I: Configured from console by console
R1#ping 50.0.0.1
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.0.1, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 4/4/5 ms
R1#
R1#
R1#ping 50.0.0.10
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.0.10, timeout is 2 seconds:
.!!!!
Success rate is 80 percent (4/5), round-trip min/avg/max = 1/1/3 ms
R1#
R1#
R1#ping 50.0.0.10
Type escape sequence to abort.
Sending 5, 100-byte ICMP Echos to 50.0.0.10, timeout is 2 seconds:
!!!!
Success rate is 100 percent (5/5), round-trip min/avg/max = 1/1/2 ms
R1#
```





