




```

R1#
R1#show ip interface brief
Interface          IP-Address      OK? Method Status  Prot
ocol
Ethernet0/0        172.50.0.1      YES TFTP  up      up
Ethernet0/1        1.0.0.1         YES TFTP  up      up
Ethernet0/2        unassigned      YES TFTP  down    down
Ethernet0/3        unassigned      YES TFTP  down    down

R1#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from PfR
  
```

```
R2#
R2#show ip interface brief
Interface IP-Address OK? Method Status Prot
ocol
Ethernet0/0 172.50.0.2 YES TFTP up up
Ethernet0/1 12.0.0.1 YES TFTP up up
Ethernet0/2 222.215.0.1 YES TFTP up up
Ethernet0/3 62.0.0.1 YES TFTP up up

R2#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR
```

```
R3#
R3#show ip interface brief
Interface IP-Address OK? Method Status Prot
ocol
Ethernet0/0 12.0.0.2 YES TFTP up up
Ethernet0/1 29.0.0.1 YES TFTP up up
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down

R3#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR
```

```
R4#
R4#show ip interface brief
Interface              IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0            222.215.0.2     YES TFTP  up          up
Ethernet0/1            129.23.0.1      YES TFTP  up          up
Ethernet0/2            unassigned      YES TFTP  down        down
Ethernet0/3            unassigned      YES TFTP  down        down

R4#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from PfR
```

```
R5#
R5#show ip interface brief
Interface              IP-Address      OK? Method Status      Prot
ocol
Ethernet0/0            62.0.0.2        YES TFTP  up          up
Ethernet0/1            212.25.0.1      YES TFTP  up          up
Ethernet0/2            unassigned      YES TFTP  down        down
Ethernet0/3            unassigned      YES TFTP  down        down

R5#show ip route
Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2
       i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
       ia - IS-IS inter area, * - candidate default, U - per-user static route
       o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
       a - application route
       + - replicated route, % - next hop override, p - overrides from PfR
```

```
R2#
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool HR
R2(dhcp-config)#net
R2(dhcp-config)#network 29.0.0.0 255.0.0.0
R2(dhcp-config)#def
R2(dhcp-config)#default-router 29.0.0.1
R2(dhcp-config)#dns
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#
R2(config)#
R2(config)#ip dhcp exc
R2(config)#ip dhcp excluded-address 29.0.0.1 29.0.0.20
R2(config)#exit
R2#
*Sep 22 15:53:29.014: %SYS-5-CONFIG_I: Configured from console by console
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool SALES
R2(dhcp-config)#network 1.0.0.0 255.0.0.0
R2(dhcp-config)#def
```

```
R2#
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool SALES
R2(dhcp-config)#network 1.0.0.0 255.0.0.0
R2(dhcp-config)#def
R2(dhcp-config)#default-router 1.0.0.1
R2(dhcp-config)#dns
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#ip dhcp ex
R2(config)#ip dhcp excluded-address 1.0.0.1 1.0.0.20
R2(config)#exit
R2#
*Sep 22 15:55:35.255: %SYS-5-CONFIG_I: Configured from console by console
R2#
R2#
R2#
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool PRODUCTION
R2(dhcp-config)#network 212.25.0.0 255.255.255.0
R2(dhcp-config)#def
R2(dhcp-config)#default-router 212.25.0.1
R2(dhcp-config)#dns
```

```
R2#
R2#
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool PRODUCTION
R2(dhcp-config)#network 212.25.0.0 255.255.255.0
R2(dhcp-config)#def
R2(dhcp-config)#default-router 212.25.0.1
R2(dhcp-config)#dns
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#
R2(config)#ip dhcp ex
R2(config)#ip dhcp excluded-address 212.25.0.1 212.25.0.20
R2(config)#exit
R2#
*Sep 22 15:58:24.054: %SYS-5-CONFIG_I: Configured from console by console
R2#
R2#
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool MGMT
R2(dhcp-config)#network 129.23.0.0 255.255.0.0
```

```
R2#
R2#
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#ip dhcp pool MGMT
R2(dhcp-config)#network 129.23.0.0 255.255.0.0
R2(dhcp-config)#def
R2(dhcp-config)#default-router 129.23.0.1
R2(dhcp-config)#dns
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#lease 1 2 3
R2(dhcp-config)#exit
R2(config)#
R2(config)#ip dhcp ex
R2(config)#ip dhcp excluded-address 129.23.0.1 129.23.0.20
R2(config)#exit
R2#
*Sep 22 16:01:03.134: %SYS-5-CONFIG_I: Configured from console by console
R2#
R2#
R2#
R2#
```

```
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#
R1#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#interface eth0/1
R1(config-if)#ip helper-address 172.50.0.2
R1(config-if)#exit
R1(config)#exit
R1#
*Sep 22 16:17:38.020: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

```
R3#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#
R3(config)#interface eth0/1
R3(config-if)#ip helper-address 12.0.0.1
R3(config-if)#exit
R3(config)#exit
R3#
*Sep 22 16:19:00.214: %SYS-5-CONFIG_I: Configured from console by console
R3#
```

```
R4
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#
R4(config)#interface eth0/1
R4(config-if)#ip helper-address 222.215.0.1
R4(config-if)#exit
R4(config)#exit
R4#
*Sep 22 16:20:57.281: %SYS-5-CONFIG_I: Configured from console by console
R4#
```

```
R5
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#
R5(config)#interface eth0/1
R5(config-if)#ip helper-address 62.0.0.1
R5(config-if)#exit
R5(config)#exit
R5#
*Sep 22 16:22:22.274: %SYS-5-CONFIG_I: Configured from console by console
R5#
```

