Ticco Ross

UNIT-808

Update History

UPDATE HISTORY

Version 0.4.0

4 November 2026

- Inside the box: flip the POWER switch to open the circuit board with 29 trimmers: BD Tune, Click, Drive; SD Tune, Decay; Tom and Conga Decay and Bend for low, mid and hi; RS and CL Tune and Decay; CP Tone and Decay; CB Tune and Decay; CY Tune; HH Tune, Tone and CH Decay.
- The trimmers start at the UNIT 808 device's settings, so the sound is unchanged until you turn one. They are saved with your project, can be automated, and reset with a double-click. Click the Ticco Ross plate on the board to close it.
- POWER no longer switches UNIT808 off: the sound keeps playing while the board is open.
- Right-click menus are twice as big, in the panel's colours.

Version 0.3.0

4 November 2026

- Copy and paste rhythms: right-click a STEP key (in MANUAL PLAY, PLAY, PATTERN CLEAR or COMPOSE) to copy or paste a whole rhythm or one variation, A or B.
- Copy and paste parts and instruments: in 1st or 2nd PART, right-click CLEAR (or a STEP key) to copy or paste the part, or just the selected instrument.
- Copies include accents, flams and step numbers; Undo paste takes back the last paste. Each UNIT808 has its own clipboard.
- The channel name windows now also mute (Option/Alt-click) and solo (Shift-click) their instrument; right-click for the menu. A plain click still selects it.
- New Rhythm Composer lettering on the panel, closer to the original.

Version 0.2.0

4 November 2026

- FLAM: Option/Alt-click a STEP key in 1st or 2nd PART to play the selected instrument on that step as a flam (a soft grace note, then the main hit). Flams are per instrument; flammed steps light blue.
- The former FINE SWING knob is now FLAM: it sets the flam spacing from TIGHT (5 ms) to LOOSE (40 ms). SWING alone sets the swing.
- Mute and solo on the labels around INSTRUMENT-SELECT: Option/Alt-click to mute (the label dims), Shift-click to solo (it glows red), right-click for a menu. Muting AC removes the accents. All can be automated.
- The instrument name windows on the channels (ACCENT, BASS DRUM ... and LOW CONGA ... MARACAS) select the instrument for writing; the selected one has an orange frame.
- Changing MODE while the rhythm plays no longer restarts the bar or leaves a gap: the new mode carries on from the same step.
- Snare Drum level now starts at 3.0.
- No more help windows on the controls: only the small value read-outs while turning a knob. The mouse wheel no longer turns knobs and selectors; double-click still resets a knob.

Version 0.1.0

4 November 2026

- First release of the UNIT808 Rhythm Composer plug-in.
- The sound engine of the UNIT 808 Max for Live device, ported to the plug-in: Bass Drum, Snare Drum, Low/Mid/Hi Tom or Conga, Rim Shot or Claves, Hand Clap or Maracas (new), Cow Bell, Cymbal, Open and Closed Hi-Hat, with Accent.
- Hardware-style panel from the UNIT808 artwork with working knobs, selectors, switches, levers, keys and indicators. Resizable from 40 % to 100 %.
- 808-style sequencer: 12 Basic Rhythms and 4 Intro/Fill In patterns, variations A and B, 1st and 2nd Part, step number, tap writing, Pattern Clear.
- BASIC-VARIATION A / AB / B, I/F-VARIATION, TAP fill in trigger and MEASURES AUTO FILL IN (2 - 16 bars).
- 12 Rhythm Tracks of up to 64 bars (COMPOSE and PLAY, chosen with INSTRUMENT-SELECT).
- Always in time with your DAW: follows the tempo and transport; SWING and FINE SWING; PRE-SCALE 1 - 4.
- Plays from MIDI (General MIDI drum map, velocity as accent). Every control can be automated and MIDI-mapped; everything is saved with your project.
- About window with contact, store and the built-in manual. AU, VST3, LV2 and standalone application for macOS, Windows and Linux.

UNIT808

Ticco Ross

Update History