



Customer Service

Generated on: 2026-09-29 10:19:46 GMT+0000

SAP S/4HANA | 2025 FPS01 (Feb 2026)

Public

Original content: https://help.sap.com/docs/SAP_S4HANA_ON-PREMISE/f4a255a5de524e3992155767996fb1fd?locale=en-US&state=PRODUCTION&version=2025.001

Warning

This document has been generated from SAP Help Portal and is an incomplete version of the official SAP product documentation. The information included in custom documentation may not reflect the arrangement of topics in SAP Help Portal, and may be missing important aspects and/or correlations to other topics. For this reason, it is not for production use.

For more information, please visit <https://help.sap.com/docs/disclaimer>.

Disconnection/Reconnection of a Utility Installation

Use

This component enables you to manage disconnections and reconnections. This component is optional. You need to use it if you want to temporarily interrupt supply to customers (especially within the bounds of a legal dunning procedure). A disconnection is a temporary interruption in the supply of a utility service that does not involve the meter removal. This is due to the following reasons, for example:

- Introduction of a collection procedure for outstanding payment
- Technical disconnection due to request of utilities company or customer

In the first instance, the service is resumed (reconnection) when the customer has paid the outstanding bill; in the second, it is done at the request of the customer.

Disconnections and Reconnections in an Advanced Metering Infrastructure Environment

If you are working in an advanced metering infrastructure (AMI) environment, you can find more information under [Advanced Metering Infrastructure](#).

Integration

Notifying Customers of Upcoming Disconnections and Reconnections

Depending on legal requirements or on intra-enterprise guidelines, you might be required to contact your customers before you carry out a disconnection or reconnection. The customer contact process is called **Notification**. In such situations, you (or a CRM agent) need to execute additional steps between the disconnection or reconnection request and the actual disconnection or reconnection.

Invoicing

You can invoice flat-rate charges for a disconnection or reconnection using the **SAP Utilities** component (IS-U). For more information, see the [Invoicing](#) component.

If you create a service order for the field service employee, and want to invoice the order then you require the **Customer Service** (CS) and **Sales and Distribution** (SD) components. For more information, see View: Customer Service (CS) and Plant Maintenance (PM) and Sales and Distribution.

Confirming Disconnection and Reconnection Order Data

You can confirm disconnection and reconnection order data in the system using the IDoc **ISU_DISC_UPLOAD** (IS-U/CCS: upload disconnection/reconnection order data).

For more information about IDocs see the following documentation:

- For general information, see IDoc Interface/Electronic Data Interchange
- For detailed information, see Using Documentation Tools


If you disconnect a business partner because he/she has reached the disconnection dunning level, the system changes the creditworthiness of the business partner for each disconnection. To do this, go to Customizing under ► **SAP Utilities** ► **Customer Service** ► **Process Execution** ► **Disconnection/Reconnection** ► **Define Processing Variants for Disconnection Documents** ► and make an entry in the **Creditworthiness Weighting** field. The change is reversed if the disconnection that triggered it is canceled.

Process

The flow of the business process is not set by the system, but is rather controlled by workflows. There are two main workflows with corresponding sub-workflows. They are as follows:

- Main Workflow for Disconnection/Reconnection/Collection (ISUDISCON12)
- Create Disconnection Order Workflow (ISUDISC12)
- Confirm Disconnection Order Workflow (ISUDISCREP12)
- Reverse Disconnection Workflow (ISUDISCSTORN)
- Interrupt Disconnection Workflow (ISUDISCBREAK)
- Terminate Workflow with Follow-Up (ISUDISCSHUT1)
- Create Reconnection Order Workflow (ISUREC12)
- Confirm Reconnection Order Workflow (ISURECREP12)
- Main Workflow for Disconnection at Customer Request (ISUDISCON12)

Main Workflow for Disconnection/Reconnection/Collection



Workflow Model

The process flow of the main workflow for **Disconnection/Reconnection** is as follows:

The **Reverse Disconnection Workflow** (ISUDISCSTORN) is not depicted in this model since it would affect clarity.

You can configure the system to generate a contract-related proposal for the object to be disconnected/reconnected. You do this in Customizing under **Define Processing Variants for Disconnection Documents**. You can change this proposal in dialog.

⚠ Caution

Workflows and Remote Disconnection and Reconnection of AMI Devices

If you are working in an advanced metering infrastructure (AMI) environment, you cannot integrate activities that feature remote disconnection and reconnection of AMI devices (such as advanced meters or smart meters) into SAP Business Workflow processes – this would conflict with the direct communication processing used for these devices.

Instead, you need to adjust your operating procedures to manually execute any workflow step related to remote disconnection and reconnection activities.

Disconnection/Reconnection of a Utilities Installation

Disconnections and reconnections are managed in [disconnection documents](#) . These log the progress of the individual business transactions.

The system provides functions that you can use in the workflows created for process control. These functions exist as methods of the DISCONNECT business object (utility disconnection).

SAP IS-U provides you with reference workflows for all disconnection reasons. You can use them as examples and templates for your own workflows.

Process Flow

The process flow is usually as follows:

Disconnection reason occurs

Overview of disconnection reasons

Disconnection reason	Triggering type	Triggered by
Disconnection dunning level reached in accounts receivable and payable	Automatic	Dunning run
Vacant status	Automatic	Move-out without move-in
Customer request	Manual	Front office, for example
Technical causes	Manual	Front office, for example

Create disconnection document

During creation of a disconnection document, you determine the processing variant based on the disconnection reason and the reference object of the disconnection document. Some of the basic settings are stored in this processing variant. You can influence this process by means of a user exit.

If the account receivable and payable is blocked, a disconnection document is automatically created for each account containing items that have reached the disconnection level.

Release disconnection document

The disconnection document must have been released in order to carry out the next steps. This procedure is useful if you do not want all of the disconnection documents to immediately lead to disconnection. This is the case, if, for example, you only want to carry out 100 disconnections per day from a pool of 2500 possible disconnections.

The individual disconnection documents are released during document processing.

You can activate or deactivate the release requirement for disconnection documents in the processing variant for disconnection.

Generate disconnection order

Disconnection orders are generated for released disconnection documents. All of the devices and flat-rate installations that belong to the reference object of the disconnection document are proposed for disconnection.

If notification is required, the system generates a [notification work item](#) . The CRM agent assigned to this work item must contact the customer, set an [agreed date](#) and close the work item before the disconnection order can be processed further.

If notification is not required, or if the notification work item is closed, you can continue processing the disconnection order.

During generation of a disconnection order, you can also create a corresponding service order in service management (SM) and continue processing it there. The service order is used for example, as a work instruction for a field service employee. Note however, that if notification is required, the system can only generate service orders after you have set the agreed date and the notification work item is closed.

Enter disconnection and confirm disconnection order

In this step, you enter when and how which devices and flat-rate installations were disconnected. If the disconnections were planned in the processing variant you can carry out the following additional activities:

Generate a customer contact.

Change the budget billing plan or induce a budget billing stop – the budget billing stop is automatically reset when you enter the reconnection.

Enter a meter reading for a disconnected meter – you can create a billing order with the billing transaction [Interim billing](#) for the affected devices.

1

If you are working in an Advanced Metering Infrastructure (AMI) environment, you can configure the system to automatically trigger a meter reading from an AMI device (for example an advanced meter or smart meter).

Post a disconnection charge – in order to post disconnection charges, you must maintain the corresponding charges schema in Customizing by choosing [Contract accounts receivable and payable \(FI-CA\)](#) → [Accounting transaction](#) → [Dunning](#).

The disconnection charges are posted based on the contracts.

1

You can set the confirmation status in Customizing. Statuses must be defined for the entry of either disconnections or reconnections.

1

You can disconnect both metering and non-metering devices, provided you have activated the functions in Customizing accordingly.

1

You can remove disconnected devices, or devices contained in a disconnection order. A removed device is indicated in a disconnection document using the status [Removed](#) or [Removed and Disconnected](#) . A removed device is no longer available for the subsequent disconnection actions. If no additional device besides the removed device exists in the disconnection document, the installation is used as the flat-rate installation for the subsequent disconnection actions. The removed device is no longer disconnected.

Triggering of the Reconnection

Disconnection reason	Events that terminate the disconnection
Disconnection dunning level reached in accounts receivable and payable	Clearing items, move-out
Vacant status	Move-in
Customer request	Customer request
Technical causes	Technical problems solved

1

You can modify event R720 (reference check for reconnection) in the **Standard function module** table (which can be found in Customizing for **Financial Accounting** (FI)) via the program enhancement for contract accounts receivable and payable. This enables you to perform an amount check. You can find a reference for the program enhancement in the ISU_CCEK_RECONNECTION_R720 function module (trigger reconnection upon clearing).

Create reconnection order

Reconnection orders are created for disconnected devices and flat-rate installations in the same way that disconnection orders are created.

You also specify whether you need to contact the corresponding customer (**Notification**) before you carry out the actual device reconnection.

If notification is required, the system generates a **notification work item** . The CRM agent assigned to this work item must contact the customer, set an **agreed date** and close the work item before the reconnection order can be processed further

If notification is not required, or if the notification work item is closed, you can continue processing the reconnection order

You can also generate a corresponding service management (SM) service order (note however, that if notification is required, the system can only generate service orders after you have set the agreed date and the notification work item is closed).

Enter reconnection and confirm reconnection order

Following reconnection, you enter the reconnection data in the system. You can also generate a customer contact, adjust the budget billing plan, post charges, and enter meter readings for the reconnection.

Disconnection Document Release

Use

Using the release mechanism, an agent can explicitly release [disconnection documents](#) before actual disconnection and reconnection processing. You cannot carry out further steps with the disconnection document (for example, generating a disconnection order) until the disconnection document is released.

In this way, you can control the workload of field service employees, for example by releasing disconnection documents according to priority or regional aspects

You can wait until a disconnection document is released in your workflow before beginning the actual disconnection process.

Prerequisites

In order to use the **Disconnection document release** function, set the release requirement to active in the corresponding disconnection processing variant.

Features

The **Disconnection document release** function sets the corresponding status in the disconnection document and triggers the accompanying event for the workflow system.

Activities

The disconnection documents are released individually. The release can also be defined as a workflow step.

The release and completion of a disconnection document exist as individual disconnection activities in the disconnection document.

Disconnection Order Generation

Use

This function is used to create disconnection orders. A disconnection order is an object that contains the disconnection details for devices that are to be disconnected.

Remote Disconnections in an Advanced Metering Infrastructure Environment

If you are working in an advanced metering infrastructure (AMI) environment, you can configure the disconnection order for the remote disconnection of AMI devices (such as smart meters or advanced meters). For more information, see [Advanced Metering Infrastructure](#).

Integration

Generating Customer Notifications

In the disconnection order, you need to indicate whether a CRM agent is required to contact the corresponding customer before a service agent (or the system – in the case of remote disconnections) carries out the actual device disconnection. The process of contacting a customer for this purpose is called **notification** and the requirement for notification is based on legal requirements or on intra-enterprise guidelines.

- If notification is required, the system generates a **notification work item**. The CRM agent assigned to this work item must contact the customer, set an **agreed date** and close the work item before the disconnection order can be processed further.
- If notification is not required, or if the notification work item is closed, you can continue processing the disconnection order.

Creating and Managing Work Items and Worklists for Customer Notifications

- 21400001 – Disconnection notification agent
- 21400002 – Disconnection notification group
- 21400003 – Disconnection notification department

You can create a simple model using the report [Create Organizational Model in ERP](#).

Automatic Assignment When Work Items are Created

To have automatic assignment when work items are created, you have to enter the responsibilities. On the SAP Easy Access screen, choose [Periodic Processing](#) [For Contract Accounts](#) [Dunning Notice](#) [Areas of Responsibility](#):

- [Maintain Department Responsibilities](#)
- [Maintain Unit Responsibilities](#)
- [Maintain Collection Specialist Responsibilities](#)

Managing Work Items and Worklists

To manage work items and worklists, you use the transaction [Manage Worklists for Disconnection Notifications](#) (from the SAP Easy Access screen, choose [UtilitiesIndustry](#) [Customer Service](#) [Process Execution](#) [Disconnection/Reconnection](#) [Work Item Management](#)).

In this transaction, the manager of a department or group can perform the following tasks:

- Create worklists manually
- Change attributes of a worklist
- Display work items
- Assign work items to new processors or groups
- Change the starting time of work items

Temporary Release of Additional Users for Managing and Processing Worklists

- You can temporarily release additional users for managing worklists, without having to change the organizational model. To do so, on the SAP Easy Access screen, choose [Periodic Processing](#) [For ContractAccounts](#) [Dunning](#) [Areas ofResponsibilities](#) [Define Additional Department or Group Head](#).

The work items are processed in the CRM system in Financial Customer Care (FCC).

- You can temporarily release additional users for processing worklists, without having to change the organizational model. To do so, on the SAP Easy Access screen, choose [Periodic Processing](#) [For ContractAccounts](#) [Dunning](#) [Areas ofResponsibilities](#) [Define Additional Collection Specialist](#).

Generating Service orders and Service Notifications

You can generate a service order or a service notification in the [Service Processing](#) (CS-SE) component that corresponds to a disconnection order in an IS-U disconnection document (note however, that if notification is required, the system can only generate service orders after you have set the agreed date and the notification work item is closed).

corresponding plant.

You can use all **Service Processing (CS-SE)** functions in the service orders/service notifications, as well as print them, and download them to another system. IS-U/CCS data is also available to you.

Service orders are generated using the same procedure described in the [Work Management](#) section.

Prerequisites

If you want to generate a disconnection order, the disconnection document must have a reference object containing devices or flat-rate installations in its data environment.

In the event that open item accounting is blocked, the contract account must contain at least one current contract when the disconnection order is generated.

Features

During generation of a disconnection order, you enter a planned disconnection date and the number of devices or flat-rate installations to be disconnected.

The system proposes all potential disconnection objects from the data environment of the reference object. In the disconnection processing variant, you can determine whether this proposal is to be division-dependent (according to the items of the contract account that are relevant to disconnection).

Disconnection orders cannot contain any installations or devices, for which a reason for guarantee of supply has been specified. The same is true for disconnection objects that are already disconnected. You can generate a disconnection order for devices that are allocated to installations other than the installation from the environment of the reference object. However, a warning will be displayed so that the disconnection will not inadvertently affect other customers.

The Planned Disconnection Date and Time

When you create a disconnection order, you specify a **planned disconnection date** and **time** (**Plan. Disc. Date** and **Disc.Time** fields), indicating when an agent (or the system – in the case of remote disconnections) is to process the device disconnection.

The Agreed Date and Time

If notification is required, the system generates a **notification work item**. When the CRM agent assigned to this work item contacts the customer, the customer can agree to the planned disconnection date and time, or propose a different one. The final date and time agreed upon by both the CRM agent and the customer are called the **agreed date** and **agreed time**.

- The agreed date and time can equal the planned disconnection date and time
- The agreed date and time can be earlier than the planned disconnection date and time – in this case, the agreed date and time must fall on or after the current date and time.
- The agreed date and time can be later than the planned disconnection date and time – in this case, the agreed date must fall on or before:
 - The **maximum agreed date** – this date is calculated by adding the **planned disconnection date** to the **maximum agreed offset**

The maximum agreed offset and maximum notification offset are specified by way of the Customizing activity [Define Processing Variants for Disconnection Documents](#). You access this activity by way of the following path: [SAPUtilities](#) > [CustomerService](#) > [Process Execution](#) > [Disconnection/Reconnection](#)

Notification Start Date and Due Date

If notification is required, the CRM agent must contact the customer within a specified time period:

- The earliest date and time that the agent can contact the customer are defined as the **notification start date** and **time**.
- The notification due date and time that appears on an agent's work list is defined as the **notification due date** and **time** – note however that it is still possible to contact the customer after this date, if required.

These dates and times are calculated using the planned disconnection date and time – more specifically, the system subtracts the **start date offset** and **due date offset** from this date to determine the notification start and end dates.

The start date offset and due date offset are specified by way of the Customizing activity [Define Processing Variants for Disconnection Documents](#). You access this activity by way of the following path: [SAPUtilities](#) > [CustomerService](#) > [Process Execution](#) > [Disconnection/Reconnection](#)

An Agreed Date is Always Set in the Backend

When notification is not required, an agreed date is not set from the standpoint of the user – however in the backend, the system automatically sets the agreed date to equal the planned disconnection date.

Therefore an agreed date is always set in the backend, whether or not customer notification is required.

The Agreed Date is the Actual Date That a Technician or the System Disconnects a Device

Devices selected in the disconnection order are always disconnected on the **agreed date**, since it is set, either by customer notification or by automatic mapping to the planned disconnection date.

Processing Disconnection Orders

Once an agreed date has been set, you can complete the disconnection order. Choose the **Save** button to save the order. If an order code and PM plant order number are provided, the system generates a service order, which can be processed by a service technician.

Generating Disconnection Orders Without a Dialog

Disconnection orders can also be generated without a dialog. However, you do not have any control over the number of objects to be disconnected or over the other parameters in this case.

Monitoring Disconnection Activities

You can monitor the status of disconnection orders and access all corresponding screens related to these orders (for example, object information screen, work order information screen). For more information, see [Monitoring Disconnection and Reconnection Activities](#).

Changing Disconnection Dates

- Customer requests – changing the agreed date

- **Internal requests or requirements – rescheduling the planned date**

It is possible to change the planned disconnection date by way of the **rescheduling** process. For example, you might not have any technicians who are available to visit the disconnection site on the original agreed date. In this case, you will need to reschedule the visit and thus, need to change the planned disconnection date.

Rescheduling therefore, is defined as the **modification of the planned disconnection date** and is typically initiated by the utilities provider and not by the customer.

For more information on rescheduling a planned disconnection, see [Rescheduling of Disconnection and Reconnection Orders](#) .

1

Note that it is not possible to change either of the the disconnection dates (agreed date or planned date) if a service order has already been generated.

Activities

Disconnection orders are usually generated in a workflow step. You can also generate them directly using the **Change Disconnection Document** transaction (from the SAP Easy Access menu, select **UtilitiesIndustry > CustomerService > Process Execution > Disconnection/Reconnection**). 

If you are working in an advanced metering infrastructure (AMI) environment, the system can generate the disconnection order automatically during the dunning run. For more information, see [Advanced Metering Infrastructure](#) .

Disconnection Entry

Use

During the disconnection entry, you inform the system when and how which devices and flat-rate installations were disconnected. Disconnection entry can also include confirmation of the corresponding disconnection order.

Integration

When entering disconnections, you can:

- Post charges
- Enter meter reading results for disconnected devices
- Change budget billing plans

Prerequisites

You can maintain parameters for the disconnection entry in Customizing for the **disconnection processing variant**. You can for example define whether budget billing plan change are admissible or whether disconnection charges are to be levied.

Features

The disconnections that have been documented are then observed, for example in the following transactions:

- Display Installation
- Change Installation
- Display Device
- Change Device

They are also observed during the following:

- Meter reading
- Billing
- Extrapolation
- Device replacement

You can disconnect disconnection objects in several disconnection documents simultaneously. The reconnection is not actually executed until the last reconnection request is received.

Activities

The disconnection is usually entered using the Change Disconnection Document transaction. However, you can also define it as a workflow step.

Confirmation of the optional service order generated


- takes place directly in Service Management
- Can be done directly in disconnection entry
- Can be controlled by making the corresponding settings in Customizing.

In Customizing under **Utilities Industry** → **Customer Service** → **Process Execution** → Disconnection/ **Reconnection** → Define Processing Variants for Disconnection Documents, you can specify that the service orders or service notifications are to be closed. In the individual confirmation status, you can define whether service orders are to be set to technically closed or not performed. Service notifications are always closed if this has been defined in Customizing.

Disconnection Document

Definition

The disconnection document is the processing unit for the agent. A disconnection document is generated for each disconnection. It is used to log the process and enables you to directly reach all the entities involved.



Disconnection Document


Use

The disconnection document is automatically generated when the disconnection dunning level is reached. It contains all the items that reach the disconnection dunning level during a dunning print run. Generally the devices for disconnection are proposed from all the contracts belonging to a contract account. This makes the contract account the reference object of the disconnection document.

A processing variant is uniquely allocated to each processing variant. It contains default values for the disconnection document functions and is configured in Customizing. The variant is assigned a unique disconnection reason and a long text.

The disconnection document guarantees consistency in the overall disconnection and reconnection business process. A reconnection cannot be performed without a disconnection having occurred beforehand. If a disconnection has already been carried out on a device or flat-rate installation, a new disconnection order cannot be generated for this disconnection object.

The disconnection/reconnection orders are confirmed in the disconnection document. They are assigned a status. Disconnection actions that have already been carried out can be reversed via the disconnection document (note that can only be done successively from the last action to the first).




Disconnection Actions

Structure

From the disconnection document, you can display the reference object logged within the document, go to the data hierarchy of the object or change it.

In the disconnection document all the created disconnection and reconnection orders, as well as entry transactions for disconnection and reconnection are logged as disconnection actions. From the disconnection document you can access the service orders and disconnection data.

All the devices contained in the disconnection document are logged in the document as disconnection objects. You can display the material serial numbers of all the devices. The disconnection is based on the device. Flat-rate installations can also be disconnected.



Disconnection Document - Structure

Reconnection Order Generation

Use

You use this function to generate reconnection orders. A reconnection order is an object that contains the reconnection details for devices that are to be reconnected.

Remote Reconnections in an Advanced Metering Infrastructure Environment

If you are working in an advanced metering infrastructure (AMI) environment, you can configure the reconnection order for the remote reconnection of AMI devices (such as smart meters or advanced meters). For more information, see [Advanced Metering Infrastructure](#).

Integration

Generating Customer Notifications

In the reconnection order, you need to indicate whether a CRM agent is required to contact the corresponding customer before a disconnection (for example, in the case of a disconnection) or a reconnection. This is done by setting the "CRM agent required" flag.

- If notification is required, the system generates a **notification work item**. The CRM agent assigned to this work item must contact the customer, set an **agreed date** and close the work item before the reconnection order can be processed further.
- If notification is not required, or if the notification work item is closed, you can continue processing the reconnection order.

Creating and Managing Work Items and Worklists for Customer Notifications

You can create work items and worklists for processing notifications related to reconnection and reconnection of services. To be able to do so, you have to create organizational units in Contract Accounts Receivable and Payable, and assign the following standard tasks to them:

- 21400001 – Disconnection notification agent
- 21400002 – Disconnection notification group
- 21400003 – Disconnection notification department

You can create a simple model using the report **Create Organizational Model in ERP**.

Automatic Assignment When Work Items are Created

To have automatic assignment when work items are created, you have to enter the responsibilities. On the SAP Easy Access screen, choose **►Periodic Processing►For Contract Accounts►Dunning Notice►Areas of Responsibility►**:

- **Maintain Department Responsibilities**
- **Maintain Unit Responsibilities**
- **Maintain Collection Specialist Responsibilities**

Managing Work Items and Worklists

To manage work items and worklists, you use the transaction **Manage Worklists for Disconnection Notifications** (from the SAP Easy Access screen, choose **►UtilitiesIndustry►Customer Service►Process Execution►Disconnection/Reconnection►Work Item Management►**).

In this transaction, the manager of a department or group can perform the following tasks:

- Create worklists manually
- Change attributes of a worklist
- Display work items
- Assign work items to new processors or groups
- Change the starting time of work items

Temporary Release of Additional Users for Managing and Processing Worklists

- You can temporarily release additional users for managing worklists, without having to change the organizational model. To do so, on the SAP Easy Access screen, choose **►PeriodicProcessing►For ContractAccounts►Dunning►Areas ofResponsibilities►Define Additional Department or Group Head►**.

The work items are processed in the CRM system in Financial Customer Care (FCC).

Generating Service orders and Service Notifications

You can generate a service order or a service notification in the [Service Processing](#) (CS-SE) component that corresponds to a reconnection order in an IS-U reconnection document (note however, that if notification is required, the system can only generate service orders after you have set the agreed date and the notification work item is closed).

i Note

You can also configure the system to automatically propose a maintenance planning plant for the service order. If there is an order code, but no maintenance planning plant has been specified for the order, then the system automatically determines the corresponding plant.

You can use all [Service Processing \(CS-SE\)](#) functions in the service orders/service notifications, as well as print them, and download them to another system. IS-U/CCS data is also available to you.

Service orders are generated using the same procedure described in the [Work Management](#) section.

Prerequisites

You can only generate a reconnection order if the disconnection document contains disconnection objects that have either already been disconnected or are planned for disconnection. Prior to executing a reconnection, you do not have to enter a disconnection in the system. This simplifies processing in cases where a quick reconnection is desirable after the disconnection reason has been canceled.

Features

Reconnection orders are generated in the same manner as disconnection orders.

Activities

Reconnection orders are usually generated in a workflow step. You can also generate them directly using the [Change Disconnection Document](#) transaction (from the SAP Easy Access menu, select [UtilitiesIndustry](#) [CustomerService](#) [Process Execution](#) [Disconnection/Reconnection](#)). 

If you are working in an advanced metering infrastructure (AMI) environment, the system can generate the reconnection order automatically during the dunning run. For more information, see [Advanced Metering Infrastructure](#).

Reconnection Entry

Use

After the reconnection has been carried out at the customer site, you enter the accompanying data in the system. You can also confirm the corresponding reconnection order.

Integration

You can perform the following activities during reconnection:

Prerequisites

You have to enter a disconnection in the system before you can enter a reconnection.

Features

You enter a reconnection in the same manner as entry of a disconnection. ([▶Customer service](#) [▶Process execution](#) [▶Disconnection/reconnection](#) [▶Change disconnection document](#)).

Activities

Reconnections are usually entered using the [Change disconnection document](#) transaction. However, you can also enter a reconnection as a workflow step.

i Note

The optionally generated service order is confirmed directly in Service Management. You can also branch to Service Management directly from the reconnection entry.

Monitoring Disconnection and Reconnection Activities

Use

You can execute the [Monitoring for Disconnection/Reconnection Orders](#) report, which allows you to search for disconnection or reconnection orders, monitor their status and access all corresponding screens (for example, object information, work order information) related to these orders .

Activities

1. Access the corresponding screen by way of the SAP Easy Access menu ([▶UtilitiesIndustry](#) [▶CustomerService](#) [▶ProcessExecution](#) [▶Disconnection/ Reconnection](#) [▶Monitor Disconnection Orders](#)).
2. Specify the selection criteria for the orders you wish to monitor.
3. Choose the [Execute](#) button to run the monitoring report.

For more information on the selection criteria, refer to the corresponding report documentation, which you can access from the selection screen.

i

If you are working in an advanced metering infrastructure (AMI) environment and are disconnecting or reconnecting AMI devices (such as advanced meters or smart meters), you can monitor the status of the disconnection or reconnection request and all messages made between the system and the meter data unification and synchronization (MDUS) system. For more information, see [AMI Monitoring](#) .

Rescheduling of Disconnection and Reconnection Orders

You can execute the [Rescheduling of Disconnection/Reconnection Orders](#) report, which allows you to reschedule one or several disconnection or reconnection orders.

Activities

1. Access the corresponding screen by way of the SAP Easy Access menu ([UtilitiesIndustry](#) [CustomerService](#) [ProcessExecution](#) [Disconnection/Reconnection](#) [Reschedule Disconnection Orders](#)).
2. Specify the selection criteria for the orders you wish to reschedule.
3. Choose the [Execute](#) button to reschedule the selected orders right away, or choose the [Schedule Job](#) button to specify a date and time.

For more information on the selection criteria, refer to the corresponding report documentation, which you can access from the selection screen.

1

Note that it is not possible to change either of the the disconnection dates (agreed date or planned date) if a service order has already been generated.