



Device Management

Generated on: 2026-09-29 09:41:52 GMT+0000

SAP S/4HANA | 2025 FPS01 (Feb 2026)

Public

Original content: https://help.sap.com/docs/SAP_S4HANA_ON-PREMISE/2ac7fe29a0c94cdd88fb80c2cb9f7758?locale=en-US&state=PRODUCTION&version=2025.001

Warning

This document has been generated from SAP Help Portal and is an incomplete version of the official SAP product documentation. The information included in custom documentation may not reflect the arrangement of topics in SAP Help Portal, and may be missing important aspects and/or correlations to other topics. For this reason, it is not for production use.

For more information, please visit <https://help.sap.com/docs/disclaimer>.

Device Management

Purpose

This component manages technical data, installations, meter readings, and the inspection of devices.


If you have activated the **Advanced Metering Infrastructure** business function (ISU_AMI_1) and you are in an advanced metering infrastructure, you can find more information under [Advanced Metering Infrastructure](#).

Integration

The following table lists the standard application components that must be integrated into device management before you can manage devices. The device, device category, and device number in the **Utilities Industry** (IS-U) component correspond to equipment, material, and the serial number in the standard system:

Name in IS-U	From Component	Name in Standard System
Device	Plant Maintenance (PM)	Equipment
Device Category	Logistics Basic Data (LO-MD)	Material
Device Number	Logistics Basic Data (LO-MD)	Serial Number

The device number is created in MM with the **Goods Receipt** function and transferred to the device. It can also be generated when you create a device in IS-U. The device is identified by a unique material and serial number combination to distinguish it from other pieces of material that may have the same serial number. The equipment number is the same throughout the system.



MM is also used for the following functions in device flow:

Function	Component
Procurement	Purchase Requisition and Purchase Order from Purchasing (MM-PUR)
Delivery	Goods Receipt from Inventory Management (MM-IM)
Outward Movement (such as scrapping or sales)	Goods Issue and Return Delivery from MM-IM
Stock Transfer	Goods Issue and Return Delivery from MM-IM

Equipment records are created automatically during **goods receipt**. Therefore, functions from the PM application component are used, including standard ordering functions and creation of maintenance plans or task lists. Billing is then carried out with the **Sales and Distribution** (SD) component.

See Also

- PM: [Equipment](#)
- LO-MD: [Material Master](#)
- MM-PUR: [Purchase Requisitions](#), [Purchase Orders](#)