
TranslatorAwareInterface + setTranslator(?Translator Interface \$translator=null, \$textDomain=null) + getTranslator() + hasTranslator() + setTranslatorEnabled (\$enabled=true) + isTranslatorEnabled() + setTranslatorTextDomain (\$textDomain='default') + getTranslatorTextDomain()



#\$defaultTranslator #\$defaultTranslatorTextDomain #\$messageLength

AbstractValidator

\$value

\$abstractOptions

- + __construct(\$options =null)
- + getOption(\$option)
- + getOptions()
- + setOptions(\$options=[])
- + getMessages()
- + __invoke(\$value)
- + getMessageVariables()
- + getMessageTemplates()
- + setMessage(\$messageString, \$messageKey=null)
- + setMessages(array \$messages)
 - et 10 de plus...
- + static setDefaultTranslator
 (?Translator\TranslatorInterface \$translator=null, \$textDomain=null)
- + static getDefaultTranslator()
- + static hasDefaultTranslator()
- + static setDefaultTranslator TextDomain(\$textDomain='default')
- + static getDefaultTranslator TextDomain()
- + static getMessageLength()
- + static setMessageLength (\$length=-1)
- # createMessage(\$messageKey, \$value)
- # error(\$messageKey, \$value=null)
- # getValue()
- # setValue(\$value)
- # translateMessage(
 \$messageKey, \$message)

const

+HEIGHT_TOO_BIG +HEIGHT_TOO_SMALL +NOT_DETECTED +NOT_READABLE +WIDTH_TOO_BIG +WIDTH_TOO_SMALL

ImageSize

- # \$messageTemplates
- # \$messageVariables
- # \$width
- # \$height
- # \$options
- + __construct(\$options =null)
- + getMinWidth()
- + setMinWidth(\$minWidth)
- + getMaxWidth()
- + setMaxWidth(\$maxWidth)
- + getMinHeight()
- + setMinHeight(\$minHeight)
- + getMaxHeight()
- + setMaxHeight(\$maxHeight)
- + getImageMin() et 8 de plus...