TranslatorAwareInterface

- + setTranslator(?Translator Interface \$translator=null, \$textDomain=null)
- + getTranslator()
- + hasTranslator()
- + setTranslatorEnabled (\$enabled=true)
- + isTranslatorEnabled()
- + setTranslatorTextDomain (\$textDomain='default')
- + getTranslatorTextDomain()

ValidatorInterface

- + isValid(\$value)
- + getMessages()

AbstractValidator

- # \$value
- # \$abstractOptions
- # static \$defaultTranslator
- # static \$defaultTranslator TextDomain
- # static \$messageLength
- + __construct(\$options =null)
- + getOption(\$option)
- + getOptions()
- + setOptions(\$options=[])
- + getMessages()
- + __invoke(\$value)
- + getMessageVariables()
- + getMessageTemplates()
- + setMessage(\$messageString, \$messageKey=null)
- + setMessages(array \$messages) et 10 de plus
- et 10 de plus...
 + static setDefaultTranslator
- (?Translator\TranslatorInterface \$translator=null, \$textDomain=null)
- + static getDefaultTranslator()
- + static hasDefaultTranslator()
- + static setDefaultTranslator TextDomain(\$textDomain='default')
- + static getDefaultTranslator TextDomain()
- + static getMessageLength()
- + static setMessageLength (\$length=-1)
- # createMessage(\$messageKey, \$value)
- # error(\$messageKey, \$value=null)
- # getValue()
- # setValue(\$value)
- # translateMessage(
 \$messageKey, \$message)

ValidatorPluginManagerAware Interface

- + setValidatorPluginManager (ValidatorPluginManager \$pluginManager)
- + getValidatorPluginManager()

Explode

- + const INVALID
- # \$pluginManager
- # \$messageTemplates
- # \$messageVariables
- # \$valueDelimiter
- # \$validator
- # \$breakOnFirstFailure
- + setValueDelimiter (\$delimiter)
- + getValueDelimiter()
- + setValidatorPluginManager (ValidatorPluginManager \$pluginManager)
- + getValidatorPluginManager()
- + setValidator(\$validator)
- + getValidator()
- + setBreakOnFirstFailure (\$break)
- + isBreakOnFirstFailure()
- + isValid(\$value, \$context =null)