






EC2 > Instances > Launch an instance

Launch an instance info

Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.

Name and tags info

Name

Windows_Server

Add additional tags

Application and OS Images (Amazon Machine Image) info

An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

Search

Search our full catalog including 1000s of application and OS images

Quick Start

Amazon Linux

macOS

Ubuntu

Windows

Red Hat

SUSE Linux

Debian

Browse more AMIs

Including AMIs from AWS, Marketplace and the Community

Amazon Machine Image (AMI)

Microsoft Windows Server 2025 Base

ami-01a15dfc48279df55 (64-bit x86)

Virtualization: hvm ENA enabled: true Root device type: ebs

Free tier eligible

Description

Microsoft Windows 2025 Datacenter edition. [English]

Summary

Number of instances info

1

Software Image (AMI)

Microsoft Windows Server 2025 ...read more

ami-01a15dfc48279df55

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 30 GiB

Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

Cancel

Launch instance

Preview code

EC2 > Instances > Launch an instance

Description

Microsoft Windows 2025 Datacenter edition. [English]

Microsoft Windows Server 2025 Full Locale English AMI provided by Amazon

Architecture

AMI ID

Publish Date

64-bit (x86)

ami-01a15dfc48279df55

2026-03-11

Instance type info | [Get advice](#)

Instance type

t3.micro

Family: t3 2 vCPU 1 GiB Memory Current generation: true On-Demand Linux for ARM On-Demand Windows 3-year pricing: 0.0796 USD per Hour On-Demand Ubuntu Pro for ARM On-Demand SUSE base pricing: 0.0104 USD per Hour On-Demand RHEL base pricing

Additional costs apply for AMIs with pre-installed software

Key pair (login) info

You can use a key pair to securely connect to your instance. Ensure that you have a key pair before launching your instance.

Key pair name - required

Select

For Windows instances, you use a key pair to decrypt the administrator password. You then use the password to log in to the instance.

Network settings info

Network info

Create key pair

Key pair name

Key pairs allow you to connect to your instance securely.

win_server

The name can include up to 255 ASCII characters. It can't include leading or trailing spaces.

Key pair type

RSA

RSA encrypted private and public key pair

ED25519

ED25519 encrypted private and public key pair (Not supported for Windows instances)

Private key file format

.pem

For use with OpenSSH

.ppk

For use with PuTTY

When prompted, store the private key in a secure and accessible location on your computer. You will need it later to connect to your instance. [Learn more](#)

Cancel

Create key pair

EC2 > Instances > Launch an instance

Network settings info

VPC - required info

vpc-026481e80797dd0a7 (default) [↻](#)

Subnet info

subnet-0053f7d764528a52e [↻](#) [Create new subnet](#)

VPC: vpc-026481e80797dd0a7 Owner: 350715735841 Availability Zone: us-east-1b (use 1-az5) Zone type: Availability Zone IP addresses available: 4091 CIDR: 172.31.32.0/20

Auto-assign public IP info

Enable

Additional charges apply when outside of free tier allowance

Firewall (security groups) info

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

Create security group

Select existing security group

Security group name - required

launch-wizard-1

This security group will be added to all network interfaces. The name can't be edited after the security group is created. Max length is 255 characters. Valid characters: a-z, A-Z, 0-9, spaces, and _-./[!@#\$%^&*(){}|;':",~`]

Description - required info

launch-wizard-1 created 2026-04-21T21:32:40.888Z

Inbound Security Group Rules

Security group rule 1 (TCP, 3389, 0.0.0.0/0)

Remove

Summary

Number of instances info

1

Software Image (AMI)

Microsoft Windows Server 2025 ...read more

ami-01a15dfc48279df55

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 30 GiB

Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

Cancel

Launch instance

Preview code

EC2 > Instances > Launch an instance

Description - requiredInfo

launch-wizard-1 created 2026-04-21T21:32:40.888Z

Inbound Security Group Rules

▼ Security group rule 1 (TCP, 3389, 0.0.0.0/0)

TypeInfo

rdp

ProtocolInfo

TCP

Port rangeInfo

3389

Source typeInfo

Anywhere

SourceInfo

Q Add CIDR, prefix list or security group

0.0.0.0/0 X

Description - optionalInfo

e.g. SSH for admin desktop

Add security group rule

▶ Advanced network configuration

▼ Configure storageInfo

Advanced

1x 30 GiB gp3 Root volume, 3000 IOPS, Not encrypted

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage

▼ Summary

Number of instancesInfo

1

Software Image (AMI)

Microsoft Windows Server 2025 ...read more

ami-01a15dfc48279ef55

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 30 GiB

Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2

Cancel

Launch instance

Preview code

aws

Search

[Alt+S]

United States (N. Virginia)

kami-aws-prod-982 (3507-1573-5841)

kk_labs_user_9177771

EC2 > Instances > Launch an instance

▶ Launching instance

Launch Initiation

80%

▶ Details

Please wait while we launch your instance.

Do not close your browser while this is loading.

aws

Search

[Alt+S]

United States (N. Virginia)

kami-aws-prod-982 (3507-1573-5841)

kk_labs_user_9177771

EC2 > Instances > Launch an instance

Success

Successfully initiated launch of Instance (i-04e85060caad51f64)

▶ Launch log

Next Steps

Q What would you like to do next with this instance, for example "create alarm" or "create backup"

Create billing and free tier usage alerts

To manage costs and avoid surprise bills, set up email notifications for billing and free tier usage thresholds.

Create billing alerts

Connect to your instance

Once your instance is running, log into it from your local computer.

Connect to instance

Learn more

Connect an RDS database

Configure the connection between an EC2 instance and a database to allow traffic flow between them.

Connect an RDS database

Create a new RDS database

Learn more

Create EBS snapshot policy

Create a policy that automates the creation, retention, and deletion of EBS snapshots

Create EBS snapshot policy

Manage detailed monitoring

Enable or disable detailed monitoring for the instance. If you enable detailed monitoring, the Amazon EC2

Create Load Balancer

Create a application, network gateway or classic Elastic Load Balancer

Create AWS budget

AWS Budgets allows you to create budgets, forecast spend, and take action on your costs and usage from a

Manage CloudWatch alarms

Create or update Amazon CloudWatch alarms for the instance.

EC2 > Instances

Instances (1/1) info

Connect Instance state Actions Launch instances

Windows_Server i-04e85060caad51f64 Running t3.micro Initializing View alarms us-east-1b ec2-52-90-103-219.co...

i-04e85060caad51f64 (Windows_Server)

Details Status and alarms Monitoring Security Networking Storage Tags

Instance summary info

Instance ID Public IPv4 address Private IPv4 addresses

EC2 > Instances > i-04e85060caad51f64 > Connect to instance

Connect info

Connect to an instance using the browser-based client.

Instance ID i-04e85060caad51f64 (Windows_Server) VPC ID vpc-026481e80797d80a7 Security groups sg-09c1c8b75b6e032d (launch-wizard-1) IAM role -

SSM Session Manager RDP client EC2 serial console

Record RDP connections

Instance ID i-04e85060caad51f64 (Windows_Server)

Connection Type

Connect using RDP client

Download remote desktop file

When prompted, connect to your instance using the following username and password:

Public DNS ec2-52-90-103-219.compute-1.amazonaws.com Username Administrator

Password Get password

EC2 > Instances > i-04e85060caad51f64 > Get Windows password

Get Windows password info

Use your private key to retrieve and decrypt the initial Windows administrator password for this instance.

Instance ID i-04e85060caad51f64 (Windows_Server)

Key pair associated with this instance win_server

Private key

Upload private key file

win_server.pem 1.68 KB

Private key contents

Cancel Decrypt password

bDHJo9B(Ft-G4v3PihjEY;.cdeQJ4u80

AWS Management Console - EC2 Instances

Search [Alt+S] | United States (N. Virginia) | kmi-aws-prod-882 (1507-1573-5841) | kmi-lab-user_917771

EC2 > Instances

Instances (1/1) Info | Last updated 2 minutes ago | [Connect](#) | [Instance state](#) | [Actions](#) | [Launch instances](#)

Filter: Find Instance by attribute or tag (case-sensitive)

Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone	Public IPv4 DNS	Public IPv4 ...	Elastic IP
Windows_Server	i-04e85060caad51f64	Running	t3.micro	3/3 checks passed	View alarms	us-east-1b	ec2-52-90-103-219.co...	52.90.103.219	-

Remote Desktop Connection

Computer: 2-52-90-103-219.compute-1.amazonaws.com

User name: None specified

You will be asked for credentials when you connect.

[Show Options](#) | [Connect](#) | [Help](#)

i-04e85060caad51f64 (Windows_Server)

[Details](#) | [Status and alarms](#) | [Monitoring](#) | [Security](#) | [Networking](#) | [Storage](#) | [Tags](#)

Instance summary Info

Instance ID: i-04e85060caad51f64 | Public IPv4 address: ec2-52-90-103-219.co... | Private IPv4 addresses: -

CloudShell | Feedback | Console Mobile App | © 2026, Amazon Web Services, Inc. or its affiliates. | Privacy | Terms | Cookie preferences

AWS Management Console - EC2 Instances

Search [Alt+S] | United States (N. Virginia) | kmi-aws-prod-882 (1507-1573-5841) | kmi-lab-user_917771

EC2 > Instances

Instances (1/1) Info | [Actions](#) | [Launch instances](#)

Filter: Find Instance by attribute or tag (case-sensitive)

Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone	Public IPv4 DNS	Public IPv4 ...	Elastic IP
Windows_Server	i-04e85060caad51f64	Running	t3.micro	3/3 checks passed	View alarms	us-east-1b	ec2-52-90-103-219.co...	52.90.103.219	-

ec2-52-90-103-219.compute-1.amazonaws.com - Remote Desktop Connection

The Remote Desktop Connection window displays a blue background with abstract white and green curved lines, representing the Windows desktop environment.

i-04e85060caad51f64 (Windows_Server)

[Details](#) | [Status and alarms](#) | [Monitoring](#) | [Security](#) | [Networking](#) | [Storage](#) | [Tags](#)

Instance summary Info

Instance ID: i-04e85060caad51f64 | Public IPv4 address: ec2-52-90-103-219.co... | Private IPv4 addresses: -

CloudShell | Feedback | Console Mobile App | © 2026, Amazon Web Services, Inc. or its affiliates. | Privacy | Terms | Cookie preferences