



Methods from supertypes are hidden in subtypes



Accessible


ScrollPane
ScrollPane () \(\)
ScrollPane (int scrollbarDisplayPolicy) \(\)
Adjustable getHAdjustable ()
int getHScrollbarHeight ()
Point get / setScrollPosition ()
int getScrollbarDisplayPolicy ()
Adjustable getVAdjustable ()
int getVScrollbarWidth ()
Dimension getViewportSize ()
boolean is / setWheelScrollingEnabled ()
void setScrollPosition (int x, int y)
int SCROLLBARS_AS_NEEDED,
SCROLLBARS_ALWAYS,
SCROLLBARS_NEVER











RootPaneContainer

Container get / setContentPane ()

Dialog

Dialog (Frame owner) Dialog (Dialog owner)

Dialog (Frame owner, boolean modal) Dialog (Frame owner, String title) Dialog (Dialog owner, String title)

Dialog (Frame owner, String title, boolean modal) **Dialog** (Dialog owner, String title, boolean modal)

Dialog (Frame owner, String title, boolean modal, GraphicsConfiguration gc) Dialog (Dialog owner, String title, boolean modal, GraphicsConfiguration gc)

String get / setTitle () boolean is / setModal () boolean is / setResizable () boolean is / setUndecorated ()

RootPaneContainer

Container get / setContentPane () Component get / setGlassPane () JLayeredPane get / setLayeredPane () JRootPane getRootPane ()

🔭 javax.swing. JWindow

JWindow ()

JWindow (GraphicsConfiguration gc) JWindow (Frame owner)

JWindow (Window owner) JWindow (Window owner, GraphicsConfiguration gc)

boolean is / setRootPaneCheckingEnabled ()

void setRootPane (JRootPane root)

Other Protected Methods # JRootPane createRootPane ()

void windowlnit ()

WindowConstants

HIDE_ON_CLOSE DISPOSE ON CLOSE.

int DO_NOTHING_ON_CLOSE, EXIT_ON_CLOSE

Component get / setGlassPane () JLayeredPane get / setLayeredPane () JRootPane getRootPane ()

RootPaneContainer

Container get / setContentPane ()

🋅 javax.swing. JFrame

JFrame (GraphicsConfiguration gc)

JFrame (String title) \(\frac{1}{3}\)
JFrame (String title, GraphicsConfiguration gc)

Static Methods boolean is / setDefaultLookAndFeelDecorated ()

int get / setDefaultCloseOperation () JMenuBar get / setJMenuBar ()

boolean is / setRootPaneCheckingEnabled () void setRootPane (JRootPane root)

Other Protected Methods

JRootPane createRootPane ()

void framelnit ()

int EXIT_ON_CLOSE

w.falkhausen.de Version 0.8 Copyright 2002 by Markus Falkhausen. All rights reserved.

